

---

# **Micro Focus Fortify Static Code Analyzer Tools**

Software Version: 21.1.0

## **Properties Reference Guide**

Document Release Date: July 2021

Software Release Date: July 2021



## Legal Notices

Micro Focus  
The Lawn  
22-30 Old Bath Road  
Newbury, Berkshire RG14 1QN  
UK

<https://www.microfocus.com>

## Warranty

The only warranties for products and services of Micro Focus and its affiliates and licensors ("Micro Focus") are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Micro Focus shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

## Restricted Rights Legend

Confidential computer software. Except as specifically indicated otherwise, a valid license from Micro Focus is required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

## Copyright Notice

© Copyright 2015 - 2021 Micro Focus or one of its affiliates

## Trademark Notices

All trademarks, service marks, product names, and logos included in this document are the property of their respective owners.

## Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number
- Document Release Date, which changes each time the document is updated
- Software Release Date, which indicates the release date of this version of the software

This document was produced on May 19, 2021. To check for recent updates or to verify that you are using the most recent edition of a document, go to:

<https://www.microfocus.com/support/documentation>

# Contents

Preface .....	4
Contacting Micro Focus Fortify Customer Support .....	4
For More Information .....	4
About the Documentation Set .....	4
Change Log .....	5
Chapter 1: Fortify Static Code Analyzer Applications and Java IDE Plugin Configuration .....	6
Where to Find the Properties File .....	6
Fortify Static Code Analyzer Applications and Java IDE Plugin Properties .....	7
Chapter 2: Fortify Extension for Visual Studio Configuration .....	26
Fortify Extension for Visual Studio Properties .....	26
Azure DevOps Server Configuration Property .....	29
Chapter 3: Shared Properties .....	30
Server Properties .....	30
Command-Line Tools Properties .....	32
Send Documentation Feedback .....	33

# Preface

## Contacting Micro Focus Fortify Customer Support

Visit the Support website to:

- Manage licenses and entitlements
- Create and manage technical assistance requests
- Browse documentation and knowledge articles
- Download software
- Explore the Community

<https://www.microfocus.com/support>

## For More Information

For more information about Fortify software products:

<https://www.microfocus.com/solutions/application-security>

## About the Documentation Set

The Fortify Software documentation set contains installation, user, and deployment guides for all Fortify Software products and components. In addition, you will find technical notes and release notes that describe new features, known issues, and last-minute updates. You can access the latest versions of these documents from the following Micro Focus Product Documentation website:

<https://www.microfocus.com/support/documentation>

# Change Log

The following table lists changes made to this document. Revisions to this document are published between software releases only if the changes made affect product functionality.

Software Release / Document Version	Changes
21.1.0	Updated: <ul style="list-style-type: none"><li>• <a href="#">"Fortify Static Code Analyzer Applications and Java IDE Plugin Properties" on page 7</a> - New property: <code>com.fortify.awb.forceGCOnProjectClose</code>, updated property description for <code>com.fortify.UseSourceProjectTemplate</code></li><li>• <a href="#">"Command-Line Tools Properties" on page 32</a> - Default value for <code>com.fortify.log.console</code> is now <code>false</code></li></ul>
20.2.0	Updated: Minor edits
20.1.0	Added: <ul style="list-style-type: none"><li>• <a href="#">"Command-Line Tools Properties" on page 32</a> - New logging property</li></ul>
19.2.0	Updated: Release date and version number

# Chapter 1: Fortify Static Code Analyzer Applications and Java IDE Plugin Configuration

This chapter describes the properties used to configure Micro Focus Fortify Static Code Analyzer applications and Java IDE plugins:

- Micro Focus Fortify Audit Workbench
- Micro Focus Fortify Custom Rules Editor
- Micro Focus Fortify Plugins for Eclipse, JetBrains IDEs, and Android Studio

The following table lists the Fortify Static Code Analyzer application acronyms used in this chapter.

Acronym	Fortify Static Code Analyzer Application / Plugin / Extension
AWB	Fortify Audit Workbench
CRE	Fortify Custom Rules Editor
ECP	Fortify Complete Plugin for Eclipse
ERP	Fortify Remediation Plugin for Eclipse
IAP	Fortify Analysis Plugin for IntelliJ and Android Studio
JRP	Fortify Remediation Plugin for JetBrains IDEs and Android Studio

## Where to Find the Properties File

The location of the properties files varies for the different Micro Focus Fortify Static Code Analyzer tools. The following table provides the location of the properties file for tools described in this chapter.

Fortify Static Code Analyzer Tool	Property File Location
AWB, CRE	<code>&lt;sca_install_dir&gt;/Core/config</code>
ECP	<code>&lt;eclipse_install_dir&gt;/plugins/com.fortify.dev.ide.eclipse_&lt;version&gt;/Core/config</code>

Fortify Static Code Analyzer Tool	Property File Location
ERP	<eclipse_install_dir>/plugins/com.fortify.plugin.remediation_<version>/Core/config
IAP	<user_home>/.<IDE_product_name>/config/plugins/FortifyAnalysis/config
JRP	<user_home>/.<IDE_product_name>/config/plugins/Fortify/config

## Fortify Static Code Analyzer Applications and Java IDE Plugin Properties

Some of the properties described in this section already exist in the `fortify.properties` file, and some of them you must add yourself. The colored boxes in the Details column indicate which Micro Focus Fortify Static Code Analyzer tools use the property. To find this properties file for the various products, see ["Where to Find the Properties File" on the previous page](#).

The following table describes the properties in the `fortify.properties` file.

Property	Details						
com.fortify.audit.ui.DisableAddingFolders	<p>If set to <code>true</code>, disables the add folder functionality.</p> <p><b>Default:</b> <code>false</code></p> <p><b>Tools Affected:</b></p> <table border="1"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
com.fortify.audit.ui.DisableBugtrackers	<p>If set to <code>true</code>, disables bug tracker integration.</p> <p><b>Default:</b> <code>false</code></p> <p><b>Tools Affected:</b></p> <table border="1"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		

Property	Details						
com.fortify.audit.ui.DisableEditing CustomTags	If set to <code>true</code> , removes the ability to edit custom tags.  <b>Default:</b> <code>false</code>  <b>Tools Affected:</b> <table border="1" data-bbox="623 464 1411 531"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
com.fortify.audit.ui.DisableSuppress	If set to <code>true</code> , disables issue suppression.  <b>Default:</b> <code>false</code>  <b>Tools Affected:</b> <table border="1" data-bbox="623 743 1411 810"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
com.fortify.AuthenticationKey	Specifies the directory used to store the Micro Focus Fortify Software Security Center client authentication token.  <b>Default:</b> <code>\${com.fortify.WorkingDirectory}/config/tools</code>  <b>Tools Affected:</b> <table border="1" data-bbox="623 1104 1411 1171"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td style="background-color: #92d050;">ERP</td> <td style="background-color: #92d050;">CRE</td> <td style="background-color: #92d050;">IAP</td> <td style="background-color: #92d050;">JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
com.fortify.awb.Debug	If set to <code>true</code> , Fortify Audit Workbench runs in debug mode.  <b>Default:</b> <code>false</code>  <b>Tools Affected:</b> <table border="1" data-bbox="623 1383 1411 1451"> <tr> <td style="background-color: #92d050;">AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
com.fortify.awb.javaExtensions	Specifies the file extensions (comma-delimited) to treat as Java files during a scan.  If no value is specified, Fortify Audit Workbench and the Fortify Complete Plugin for Eclipse recognize <code>.java</code> , <code>.jsp</code> , and <code>.jspx</code> files as Java files. The property is used only to determine whether a project includes Java files and to add Java-specific controls to the Advanced Scan wizard.  <b>Default:</b> <code>none</code>						

Property	Details						
	<p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 338 1409 407"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. awb.forceGConProjectClose</p>	<p>If set to true, garbage collection is run and heap space is released when you close a project. This reduces the increased Java process memory consumption when working with small FPR files. When Fortify Audit Workbench runs with G1GC garbage collection, this allows the Java process to return free memory back to the operating system when the project is closed.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 829 1409 898"> <tr> <td style="background-color: #92d050;">AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. awb.LinuxFontAdjust</p>	<p>Specifies the font size to use on Linux platforms. Fortify Audit Workbench adds the specified size to original font size.</p> <p><b>Default:</b> 0</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1152 1409 1222"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td style="background-color: #92d050;">CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. awb.MacFontAdjust</p>	<p>Specifies the size to tune font size for Mac platform. Fortify Audit Workbench adds the specified size to the original font size.</p> <p><b>Default:</b> 2</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1476 1409 1545"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td style="background-color: #92d050;">CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. awb.WindowsFontAdjust</p>	<p>Specifies to tune font size for Windows platform. Fortify Audit Workbench adds the specified size to original font size.</p> <p><b>Default:</b> 0</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1799 1409 1869"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td style="background-color: #92d050;">CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		

Property	Details						
<p>com.fortify. Debug</p>	<p>If set to <code>true</code>, runs the Fortify Static Code Analyzer tools in debug mode.</p> <p><b>Default:</b> <code>false</code></p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 506 1409 573"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td style="background-color: #92d050;">ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. DisableDescriptionXML Escaping</p>	<p>If set to <code>true</code>, disables XML escaping in issue descriptions (for example, changing <code>&amp;quot;</code> in XML/FVDL to <code>"</code>).</p> <p><b>Default:</b> <code>false</code></p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 827 1409 894"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. DisableExternalEntry Correlation</p>	<p>If set to <code>true</code>, parses URL in the ExternalEntries/Entry element in <code>audit.fvdl</code>.</p> <p><b>Default:</b> <code>false</code></p> <pre data-bbox="621 1094 1401 1549" style="background-color: #f0f0f0; padding: 10px;"> &lt;ExternalEntries&gt;   &lt;Entry name="HTML Form" type="URL"&gt;     &lt;URL&gt;/auth/PerformChangePass.action&lt;/URL&gt;     &lt;SourceLocation path="pages/content/       ChangePass.jsp" line="16" lineEnd="16"       colStart="0" colEnd="0"       snippet=         "1572130B944CEC7A3D98775A499AE8FA#pages/         content/ChangePass.jsp:16:16"/&gt;     &lt;/Entry&gt;   &lt;/ExternalEntries&gt; </pre> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1635 1409 1703"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. DisableMinVirtCallConfidence Computation</p>	<p>If set to <code>true</code>, disables computing minimum virtual call confidence. Fortify Audit Workbench and the Fortify Complete Plugin for Eclipse use this attribute to compute minimum virtual call</p>						

Property	Details						
	<p>confidence and enable issue filtering. For example, you can use it to filter out all issues that contain virtual call with confidence lower than 0.46.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 548 1414 615"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. DisableRemovedIssue Persistence</p>	<p>If set to true, disables removed issue persistence (clears removed issues from the results file).</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 869 1414 936"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. DisableReportCategory Rendering</p>	<p>If set to true, disables rendering issue description into report.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 1152 1414 1220"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. DisplayEventID</p>	<p>If set to true, displays the event ID in the issue node tooltip in the Issues view.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 1478 1414 1545"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. eclipse.Debug</p>	<p>If set to true, runs the plugin in debug mode.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 1757 1414 1824"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		

Property	Details						
<p>com.fortify. InstallationUserName</p>	<p>Specifies the default user name for logging in to Fortify Software Security Center for the first time.</p> <p><b>Default:</b> <code>\${user.name}</code></p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 506 1409 573"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. locale</p>	<p>Specifies the locale (for rules and metadata only). Possible values are:</p> <p>en (English)</p> <p>es (Spanish)</p> <p>ja (Japanese)</p> <p>ko (Korean)</p> <p>pt_BR (Brazilian Portuguese)</p> <p>zh_CN (Simplified Chinese)</p> <p>zh_TW (Traditional Chinese)</p> <p><b>Default:</b> en</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1262 1409 1329"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.CheckSig</p>	<p>If set to true, verifies signature in FPR.</p> <p>If <code>com.fortify.model.UseIssueParseFilters</code> is set to true, then <code>com.fortify.model.MinimalLoad</code> is set to true, <code>com.fortify.model.IssueCutoffStartIndex</code> is not null, <code>com.fortify.model.IssueCutoffEndIndex</code> is not null, <code>com.fortify.model.IssueCutoffByCategoryStartIndex</code> is not null or <code>com.fortify.model.IssueCutoffByCategoryEndIndex</code> is not null, <code>com.fortify.model.CheckSig</code> is false, and the signature in FPRs are not verified.</p> <p><b>Default:</b> true (normal) / false (minimum load)</p>						

Property	Details						
	<p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 338 1412 407"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.CustomDescriptionsHeader</p>	<p>Specifies the custom prefix for the description header. It prepends the text in the Description/Recommendation header, so that you see “My Recommendations” instead of “Custom Recommendations.”</p> <div style="background-color: #f0f0f0; padding: 5px; border: 1px solid #ccc;"> <p><b>Note:</b> To update description headers, Fortify recommends that you use the &lt;CustomDescriptionRule&gt; rule with the &lt;Header&gt; element text instead.</p> </div> <p><b>Default:</b> none</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 911 1412 980"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.DisableChopBuildID</p>	<p>If set to true, does not shorten the build ID, even if the build ID exceeds 250 characters.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1234 1412 1304"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.DisableContextPool</p>	<p>If set to true, disables loading of the ContextPool section of the audit.fvdl file.</p> <p>You can configure this property if com.fortify.model.MinimalLoad is not set to true. If com.fortify.model.MinimalLoad is set to true, then com.fortify.model.DisableContextPool is automatically set to true.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1787 1412 1856"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		

Property	Details						
<p>com.fortify.model.DisableDescription</p>	<p>If set to true, disables loading the Description section from audit.fvdl.</p> <p>You can configure this property if com.fortify.model.MinimalLoad is not set to true. If com.fortify.model.MinimalLoad is true, then com.fortify.model.DisableDescription is automatically set to true.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 730 1409 800"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.DisableEngineData</p>	<p>If set to true, disables loading the EngineData section of audit.fvdl to save memory when large FPR files are opened. This data is displayed on the <b>Analysis Information</b> tab of <b>Project Summary</b> view. The property is useful if too many analysis warnings occur during a scan. However, Fortify recommends that you instead set a limit for com.fortify.model.MaxEngineErrorCount to open FPR files that have many Fortify Static Code Analyzer warnings.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1304 1409 1373"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.DisableProgramInfo</p>	<p>You can configure this property if com.fortify.model.MinimalLoad is not true. If com.fortify.model.MinimalLoad is set to true, then this property is automatically set to true.</p> <p>If set to true, prevents loading of metatable from the ProgramData section of FPR files. If set to false, loads metatable from the FPR file.</p> <p><b>Default:</b> false</p>						

Property	Details						
	<p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 338 1409 407"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.DisableProgramPoint</p>	<p>If set to true, disables loading of the ProgramPoint section from the runtime.fvdl file.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 659 1409 728"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.DisableReplacement Parsing</p>	<p>If set to true, disables replacing conditional description.</p> <p>You can configure this property if com.fortify.model.MinimalLoad is not set to true. If com.fortify.model.MinimalLoad is true, then this property is automatically set to true.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1129 1409 1199"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.DisableSnippets</p>	<p>If set to true, disables loading the Snippets section from the audit.fvdl file.</p> <p>You can configure this property if com.fortify.model.MinimalLoad is set to false. If com.fortify.model.MinimalLoad is set to true, then com.fortify.model.DisableSnippets is automatically set to true.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1682 1409 1751"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.DisableUnified Inductions</p>	<p>If set to true, disables loading the UnifiedInductionPool section from the audit.fvdl file.</p>						

Property	Details						
	<p>You can configure this property if <code>com.fortify.model.MinimalLoad</code> is not set to <code>true</code>. If <code>com.fortify.model.MinimalLoad</code> is set to <code>true</code>, then <code>com.fortify.model.DisableUnifiedInductions</code> is automatically set to <code>true</code>.</p> <p><b>Default:</b> <code>false</code></p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 627 1411 695"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p><code>com.fortify.model.DisableUnifiedPool</code></p>	<p>If set to <code>true</code>, disables loading the <code>UnifiedNodePool</code> section from the <code>audit.fvdl</code> file.</p> <p>You can configure this property if <code>com.fortify.model.MinimalLoad</code> is set to <code>false</code>. If <code>com.fortify.model.MinimalLoad</code> is <code>true</code>, then <code>com.fortify.model.DisableUnifiedPool</code> is automatically set to <code>true</code>. If the value is not specified or <code>false</code>, this property is set to <code>none</code>.</p> <p><b>Default:</b> <code>false</code></p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1222 1411 1289"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p><code>com.fortify.model.DisableUnifiedTrace</code></p>	<p>If set to <code>true</code>, disables loading the <code>UnifiedTracePool</code> section from the <code>audit.fvdl</code> file.</p> <p>You can configure this property if <code>com.fortify.model.MinimalLoad</code> is not set to <code>true</code>. If <code>com.fortify.model.MinimalLoad</code> is <code>true</code>, then <code>com.fortify.model.DisableUnifiedTrace</code> is automatically set to <code>true</code>.</p> <p><b>Default:</b> <code>false</code></p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1772 1411 1839"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		

Property	Details						
com.fortify. model.EnablePathElement BaseIndexShift	<p>If set to <code>true</code>, enables backward compatibility with pre-2.5 migrated projects.</p> <p><b>Default:</b> none</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 506 1409 573"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
com.fortify. model.EnableSource Correlation	<p>If set to <code>true</code>, takes data flow source into consideration for issue correlation. The default is <code>false</code> because correlations with runtime results might not be reliable with this setting enabled.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 869 1409 936"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
com.fortify. model.ExecMemorySetting	<p>Specifies the JVM heap memory size used by Fortify Audit Workbench to launch external utilities.</p> <p><b>Default:</b></p> <p>600—iidmigrator</p> <p>300—fortifyupdate</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 1314 1409 1381"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
com.fortify. model.ForceIIDMigration	<p>If set to <code>true</code>, forces running Instance ID migration during a merge.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 1640 1409 1707"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
com.fortify. model.FullReportFileNames	<p>If set to <code>true</code>, uses full file name in reports.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p>						

Property	Details						
	<table border="1" data-bbox="621 275 1401 342"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.IIDmigratorOptions</p>	<p>Specifies iidmigrator options (space-delimited values) run by FPRUtility, Fortify Audit Workbench, or the Fortify Complete Plugin for Eclipse.</p> <p><b>Default:</b> none</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 642 1401 709"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.IssueCutoffByCategory StartIndex</p>	<p>Specifies the start index for issue cutoff by category.</p> <p><b>Default:</b> 0</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 926 1401 993"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.IssueCutoffByCategory EndIndex</p>	<p>Specifies the end index for issue cutoff by category.</p> <p><b>Default:</b> java.lang.Integer.MAX_VALUE</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1211 1401 1278"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.IssueCutoffStartIndex</p>	<p>Specifies the start index for issue cutoff. Select the first issue (by number) to be loaded.</p> <p><b>Default:</b> 0</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1530 1401 1598"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.IssueCutoffEndIndex</p>	<p>Determines the end index for issue cutoff. Select the last issue (by number) to be loaded.</p> <p><b>Default:</b> java.lang.Integer.MAX_VALUE</p> <p><b>Tools Affected:</b></p>						

Property	Details						
	<table border="1" style="width: 100%; text-align: center;"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.MaxEngineErrorCount</p>	<p>Determines how many reported Fortify Static Code Analyzer warnings are loaded. To allow an unlimited number, specify -1.</p> <p>Fortify recommends that you keep the default value of 3000 because this can speed up the load time of large FPR files.</p> <p><b>Default:</b> 3000</p> <p><b>Tools Affected:</b> Also used by FPRUtility</p> <table border="1" style="width: 100%; text-align: center;"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.MergeResolveStrategy</p>	<p>Specifies merge resolve strategy from:</p> <ul style="list-style-type: none"> <li>• DefaultToMasterValue (use primary project)</li> <li>• DefaultToImportValue (use secondary project)</li> <li>• NoStrategy (prompt for project to use)</li> </ul> <p><b>Default:</b> DefaultToMasterValue</p> <p><b>Tools Affected:</b></p> <table border="1" style="width: 100%; text-align: center;"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.MinimalLoad</p>	<p>If set to true, minimizes the data loaded from an FPR file.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" style="width: 100%; text-align: center;"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.NProcessingThreads</p>	<p>Specifies the number of threads to process FPR files.</p> <p>If com.fortify.model.PersistDataToDisk is set to true, defaults to 1 thread.</p> <p>If the number specified exceeds the number of available processors: int</p> <pre>maxThreads=java.lang.Runtime.getRuntime().availableProcessors(), then Fortify Static Code Analyzer tools use the number of available processors as the</pre>						

Property	Details						
	<p>number of threads to process FPR files.</p> <p><b>Default:</b> Number of available processors</p> <p><b>Tools Affected:</b> Also used by FPRUtility</p> <table border="1" data-bbox="623 464 1409 531"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.PersistDataToDisk</p>	<p>If set to <code>true</code>, enables a persistence strategy to reduce the memory footprint and uses the disk drive to swap FPR data out of memory.</p> <p><b>Default:</b> <code>false</code></p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 829 1409 896"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.PersistenceBlockSize</p>	<p>If <code>com.fortify.model.PersistenceStrategy</code> is set to <code>CUSTOM</code>, <code>com.fortify.model.PersistenceBlockSize</code> specifies the number of attribute values that comprise a single block of attributes. These blocks are cached to disk and read back in as needed. A higher number decreases the total number of cache files, but increases the file size and the amount of memory that is read in each time.</p> <p><b>Default:</b> <code>250</code></p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 1360 1409 1428"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.PersistenceQueue Capacity</p>	<p>If <code>com.fortify.model.PersistenceStrategy</code> is set to <code>CUSTOM</code>, this property specifies the maximum number of attribute value blocks that can exist in the producer/consumer queue.</p> <p><b>Default:</b> queue is unbounded</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 1726 1409 1793"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		

Property	Details						
<p>com.fortify.model.PriorityImpactThreshold</p>	<p>Specifies the threshold for issue impact. The valid values are 0.0F–5.0F. If the impact of an issue is greater than or equal to the threshold, the issue is considered High. If the impact of an issue is less than the threshold, the issue is considered Low. Issues are then categorized as follows:</p> <ul style="list-style-type: none"> <li>• <b>Critical</b>—High Impact and High Likelihood</li> <li>• <b>High</b>—High Impact and Low Likelihood</li> <li>• <b>Medium</b>—Low Impact and High Likelihood</li> <li>• <b>Low</b>—Low Impact and Low Likelihood</li> </ul> <p>Also see <a href="#">com.fortify.model.PriorityLikelihoodThreshold</a></p> <p><b>Default:</b> 2.5F</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 898 1409 966"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.PriorityLikelihoodThreshold</p>	<p>Specifies the threshold for issue likelihood. The valid values are 0.0F–5.0F. If the likelihood of an issue is greater than or equal to the threshold, the issue is considered High. If the likelihood of an issue is less than the threshold, the issue is considered Low. Issues are then categorized as follows:</p> <ul style="list-style-type: none"> <li>• <b>Critical</b>—High Impact and High Likelihood</li> <li>• <b>High</b>—High Impact and Low Likelihood</li> <li>• <b>Medium</b>—Low Impact and High Likelihood</li> <li>• <b>Low</b>—Low Impact and Low Likelihood</li> </ul> <p>Also see <a href="#">com.fortify.model.PriorityImpactThreshold</a></p> <p><b>Default:</b> 2.5F</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1612 1409 1680"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify.model.report.useSystemLocale</p>	<p>If set to true, uses system locale for report output. If set to false, uses com.fortify.locale in the fortify.properties file. If a value is not specified, the tool uses java.util.Locale.getDefault().</p>						

Property	Details						
	<p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 401 1411 470"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.ReportLineLimit</p>	<p>Specifies the character limit for each issue code snippet in reports.</p> <p><b>Default:</b> 500</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 682 1411 751"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.UseIIDMigrationFile</p>	<p>Specifies the full path of the instance ID migration file to use.</p> <p><b>Default:</b> none</p> <p><b>Tools Affected:</b> Also used by FPRUtility</p> <table border="1" data-bbox="623 963 1411 1033"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.UseIssueParseFilters</p>	<p>If set to true, respects the settings in the IssueParseFilters.properties configuration file. This file is in the following directories:</p> <p><b>AWB</b>—&lt;scs_install_dir&gt;/Core/config</p> <p><b>ECP</b>—&lt;eclipse_install_dir&gt;/plugins/com.fortify.dev.ide.eclipse_&lt;version&gt;/Core/config</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 1491 1411 1560"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. model.UseOldIIDMigration Attributes</p>	<p>If set to true, uses attributes of old issues during instance ID migration while merging similar issues of old and new scans.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 1814 1411 1883"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		

Property	Details						
<p>com.fortify. remediation.PaginateIssues</p>	<p>If set to true or if no value is specified, the remediation plugins use pagination during issue download.</p> <p>If set to false, these plugins download all issues at once.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 564 1411 636"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. remediation.PaginationCount</p>	<p>If com.fortify.remediation.PaginateIssues is set to true, specifies the page count.</p> <p><b>Default:</b> 1000</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 888 1411 959"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. RemovedIssuePersistenceLimit</p>	<p>Specifies how many removed issues to keep when you save an FPR.</p> <p><b>Default:</b> 1000</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1213 1411 1285"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. SCAExecutablePath</p>	<p>Specifies file path to sourceanalyzer.exe.</p> <div data-bbox="621 1371 1403 1556" style="background-color: #f0f0f0; padding: 5px;"> <p><b>Note:</b> The Fortify Static Code Analyzer and Applications installer sets this property during installation and it only requires modification if you manually move the executable files.</p> </div> <p><b>Default:</b> &lt;sca_install_dir&gt;/bin/sourceanalyzer.exe</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="621 1703 1411 1774"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. search.defaultSyntaxVer</p>	<p>Determines whether to use the AND and OR operators in searches. These are enabled in search syntax by default.</p>						

Property	Details						
	<ul style="list-style-type: none"> <li>To block the use of the AND and OR operators, set the value to 1.</li> <li>To use ANDs and ORs without parentheses, set the value to 2.</li> </ul> <p><b>Default:</b> 2</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 501 1411 569"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. StoreOriginalDescriptions</p>	<p>If set to true, stores original plain text issue descriptions (before parsing) as well as the parsed ones with tags replaced with specific values.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 867 1411 934"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. taintFlagBlacklist</p>	<p>Specifies taint flags to exclude (comma-delimited values).</p> <p><b>Default:</b> none</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 1150 1411 1218"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. tools.iidmigrator.scheme</p>	<p>Set this property to migrate instance IDs created with different versions of Fortify Static Code Analyzer using a custom matching scheme. This is generally handled by Fortify Static Code Analyzer. If you need a custom matching scheme, contact Micro Focus Fortify Customer Support.</p> <p><b>Default:</b> none</p> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 1598 1411 1665"> <tr> <td style="background-color: #92d050;">AWB</td> <td style="background-color: #92d050;">ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. UseSourceProjectTemplate</p>	<p>This property determines the issue template to use when merging analysis information from two audit projects. If set to true, it forces the use of filter sets and folders from the issue template associated with the original scan results (secondary project). The issue template from the new scan results (primary project) are</p>						

Property	Details						
	<p>used by default.</p> <p><b>Default:</b> false</p> <p><b>Tools Affected:</b> Also used by FPRUtility</p> <table border="1" data-bbox="623 464 1411 531"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		
<p>com.fortify. WorkingDirectory</p>	<p>Specifies the working directory that contains all user configuration and working files for all Fortify Static Code Analyzer components. To configure this property, you must have write access to the directory.</p> <p><b>Defaults:</b></p> <ul style="list-style-type: none"> <li>Windows—<code>\${win32.LocalAppdata}/Fortify</code></li> <li>Unix—<code>\${user.home}/.fortify</code></li> </ul> <p><b>Tools Affected:</b></p> <table border="1" data-bbox="623 968 1411 1035"> <tr> <td>AWB</td> <td>ECP</td> <td>ERP</td> <td>CRE</td> <td>IAP</td> <td>JRP</td> </tr> </table>	AWB	ECP	ERP	CRE	IAP	JRP
AWB	ECP	ERP	CRE	IAP	JRP		

# Chapter 2: Fortify Extension for Visual Studio Configuration

This section describes the properties used by the Micro Focus Fortify Extension for Visual Studio. The properties are listed in alphabetical order based on the files in which they belong.

This section contains the following topics:

- [Fortify Extension for Visual Studio Properties](#) .....26
- [Azure DevOps Server Configuration Property](#) .....29

## Fortify Extension for Visual Studio Properties

Some of the properties described here already exist in the `fortify.properties` file, and some of them you must add yourself. The following table describes the properties in the `<sca_install_dir>/Core/config/fortify.properties` file.

Property	Details
<code>com.fortify.audit.ui.DisableBugtrackers</code>	If set to <code>true</code> , disables bug tracker integration. <b>Default:</b> <code>false</code>
<code>com.fortify.audit.ui.DisableSuppress</code>	If set to <code>true</code> , disables issue suppression. <b>Default:</b> <code>false</code>
<code>com.fortify.AuthenticationKey</code>	Specifies the directory used to store the Micro Focus Fortify Software Security Center client authentication token. <b>Default:</b> <code>\${com.fortify.WorkingDirectory}/config/tools</code>
<code>com.fortify.Debug</code>	If set to <code>true</code> , runs all Fortify Static Code Analyzer tools in debug mode. <b>Default:</b> <code>false</code>
<code>com.fortify.model.CustomDescriptionsHeader</code>	Specifies the custom prefix for the description header. It prepends the text in the <code>Description/Recommendation</code> header, so that you see “My Recommendations” instead of “Custom Recommendations.”

Property	Details
	<p><b>Note:</b> To update description headers, Fortify recommends that you use the <code>&lt;CustomDescriptionRule&gt;</code> rule with the <code>&lt;Header&gt;</code> element text instead.</p> <p><b>Default:</b> none</p>
<p>com.fortify. model.ForcellDMigration</p>	<p>If set to <code>true</code>, forces running Instance ID migration during a merge.</p> <p><b>Default:</b> <code>false</code></p>
<p>com.fortify. model.PriorityImpactThreshold</p>	<p>Specifies the threshold for issue impact. The valid values are 0.0F–5.0F. If the impact of an issue is greater than or equal to the threshold, the issue is considered High. If the impact of an issue is less than the threshold, the issue is considered Low. Issues are then categorized as follows:</p> <ul style="list-style-type: none"> <li>• <b>Critical</b>—High Impact and High Likelihood</li> <li>• <b>High</b>—High Impact and Low Likelihood</li> <li>• <b>Medium</b>—Low Impact and High Likelihood</li> <li>• <b>Low</b>—Low Impact and Low Likelihood</li> </ul> <p>Also see <a href="#">com.fortify.model.PriorityLikelihoodThreshold</a></p> <p><b>Default:</b> 2.5F</p>
<p>com.fortify. model.PriorityLikelihoodThreshold</p>	<p>Specifies the threshold for issue likelihood. The valid values are 0.0F–5.0F. If the likelihood of an issue is greater than or equal to the threshold, the issue is considered High. If the likelihood of an issue is less than the threshold, the issue is considered Low. Issues are then categorized as follows:</p> <ul style="list-style-type: none"> <li>• <b>Critical</b>—High Impact and High Likelihood</li> <li>• <b>High</b>—High Impact and Low Likelihood</li> <li>• <b>Medium</b>—Low Impact and High Likelihood</li> <li>• <b>Low</b>—Low Impact and Low Likelihood</li> </ul> <p>Also see <a href="#">com.fortify.model.PriorityImpactThreshold</a></p> <p><b>Default:</b> 2.5F</p>

Property	Details
com.fortify.model.UseIDMigrationFile	<p>Specifies the full path of the instance ID migration file to use.</p> <p><b>Default:</b> none</p>
com.fortify.SCAExecutablePath	<p>Specifies file path to sourceanalyzer.exe.</p> <div style="background-color: #f0f0f0; padding: 5px; margin: 5px 0;"> <p><b>Note:</b> The Fortify Static Code Analyzer and Applications installer sets this property during installation and it only requires modification if you manually move the executable files.</p> </div> <p><b>Default:</b> &lt;scinstall_dir&gt;/bin/sourceanalyzer.exe</p>
com.fortify.search.defaultSyntaxVer	<p>Determines whether to use the AND and OR operators in searches. These are enabled in search syntax by default.</p> <ul style="list-style-type: none"> <li>• To block the use of the AND and OR operators, set the value to 1.</li> <li>• To use ANDs and ORs without parentheses, set the value to 2.</li> </ul> <p><b>Default:</b> 2</p>
com.fortify.tools.iidmigrator.scheme	<p>Set this property to migrate instance IDs created with different versions of Fortify Static Code Analyzer using a custom matching scheme. This is generally handled by Fortify Static Code Analyzer. If you need a custom matching scheme, contact Micro Focus Fortify Customer Support.</p> <p><b>Default:</b> none</p>
com.fortify.visualstudio.vm.args	<p>Specifies JVM options.</p> <p><b>Default:</b> -Xmx256m</p>
com.fortify.VS.Debug	<p>If set to true, runs the Fortify Extension for Visual Studio in debug mode.</p> <p><b>Default:</b> false</p>
com.fortify.VS.DisableCIntegration	<p>If set to true, disables C/C++ build integration in Visual Studio.</p> <p><b>Default:</b> false</p>

Property	Details
com.fortify. VS.disableMigrationCheck	If set to true, disables instance ID migration checking. <b>Default:</b> false
com.fortify. VS.DisableReferenceLibDirs AndExcludes	If set to true, disables using references added to a project. <b>Default:</b> false
com.fortify. VS.ListProjectProperties	If set to true, lists the Visual Studio project properties in a log file. <b>Default:</b> false
com.fortify. VS.NETFrameworkRoot	Specifies the file path to the .NET Framework root. <b>Default:</b> none
com.fortify. WorkingDirectory	Specifies the working directory that contains all user configuration and working files for all Fortify Static Code Analyzer components. To configure this property, you must have write access to the directory. <b>Default:</b> <code>\${win32.LocalAppdata}/Fortify</code>

## Azure DevOps Server Configuration Property

The property for the Azure DevOps Server is stored in the `TFSconfiguration.properties`. This file is located in the Fortify working directory in the `config\VS<vs_version>-<sca_version>` directory.

**Note:** The `TFSconfiguration.properties` file is created only after the first time you configure a connection to your Azure DevOps Server from the Fortify Extension for Visual Studio.

The following property is in the `TFSconfiguration.properties` file:

`server.url`

**Details:** Specifies the Azure DevOps Server location.

**Default:** none

# Chapter 3: Shared Properties

This chapter describes the properties shared by Micro Focus Fortify Static Code Analyzer command-line tools, standalone applications, and plugins.

This section contains the following topics:

- [Server Properties](#) ..... 30
- [Command-Line Tools Properties](#) ..... 32

## Server Properties

Because some of the values in this file are encrypted (such as proxy user name and password), you must use the `scapostinstall` tool to configure these properties. For information about how to use the `scapostinstall` tool, see the *Micro Focus Fortify Static Code Analyzer User Guide*.

Other properties are updated using command-line tools, standalone applications (such as Fortify Audit Workbench), and remediation plugins. Fortify recommends that you use these tools to edit the properties in this file instead of editing the file manually.

The following table describes the properties in the `<sc*_install_dir>/Core/config/server.properties` file.

Property	Details
<code>autoupgrade.server</code>	Specifies the Fortify Static Code Analyzer and Applications automatic update server. This enables users to check for new versions of the Fortify Static Code Analyzer and Applications installer on a web server and run the installer if an update is available.  <b>Default:</b> <code>http://localhost:8180/ssc/update-site/installers</code>
<code>install.auto.upgrade</code>	If set to <code>true</code> , enables Fortify Audit Workbench automatic update feature.  <b>Default:</b> <code>false</code>
<code>oneproxy.http.proxy.port</code>	Specifies the proxy server port to access bug trackers.  <b>Default:</b> <code>none</code>
<code>oneproxy.http.proxy.server</code>	Specifies the proxy server name to access bug trackers.

Property	Details
	<b>Default:</b> none
oneproxy.https.proxy.port	Specifies the proxy server port to access bug trackers through an SSL connection.  <b>Default:</b> none
oneproxy.https.proxy.server	Specifies the proxy server name to access bug trackers through an SSL connection.  <b>Default:</b> none
rp.update.from.manager	If set to true, updates security content from the Fortify Software Security Center instead of from the Fortify Rulepack update server.  <b>Default:</b> false
rulepack.auto.update	If set to true, updates security content automatically.  <b>Default:</b> false
rulepack.days	Specifies the interval (in days) between security content updates.  <b>Default:</b> 15
rulepackupdate.proxy.port	Specifies the proxy server port to access the Fortify Rulepack update server (uploadclient.proxy.port is used if rp.update.from.manager is set to true).  <b>Default:</b> none
rulepackupdate.proxy.server	Specifies proxy server name to access the Fortify Rulepack update server (uploadclient.proxy.server is used if rp.update.from.manager is set to true).  <b>Default:</b> none
rulepackupdate.server	Specifies the Fortify Rulepack update server location.  <b>Default:</b> https://update.fortify.com
uploadclient.proxy.port	Specifies the proxy server port to access the Fortify Software Security Center server.  <b>Default:</b> none
uploadclient.proxy.server	Specifies the proxy server name to access the Fortify Software Security Center server.

Property	Details
	<b>Default:</b> none
uploadclient.server	Specifies the URL of the Fortify Software Security Center server. <b>Default:</b> http://localhost:8180/ssc

## Command-Line Tools Properties

The following table describes the properties in the `<sca_install_dir>/Core/config/fortify.properties` file that are used by the command-line tools.

Property	Details
com.fortify.log.console	Specifies whether logging messages are written to the console. Logging information is always written to the log file. <b>Default:</b> false

# Send Documentation Feedback

If you have comments about this document, you can [contact the documentation team](#) by email.

**Note:** If you are experiencing a technical issue with our product, do not email the documentation team. Instead, contact Micro Focus Fortify Customer Support at <https://www.microfocus.com/support> so they can assist you.

If an email client is configured on this computer, click the link above to contact the documentation team and an email window opens with the following information in the subject line:

**Feedback on Properties Reference Guide (Fortify Static Code Analyzer Tools 21.1.0)**

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to [FortifyDocTeam@microfocus.com](mailto:FortifyDocTeam@microfocus.com).

We appreciate your feedback!