



CORBA Programmer's Guide
C++

Version 6.0, February 2003

Making Software Work Together™

IONA, IONA Technologies, the IONA logo, Orbix, Orbix/E, Orbacus, Artix, Orchestrator, Mobile Orchestrator, Enterprise Integrator, Adaptive Runtime Technology, Transparent Enterprise Deployment, and Total Business Integration are trademarks or registered trademarks of IONA Technologies PLC and/or its subsidiaries.

Java and J2EE are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and other countries.

CORBA is a trademark or registered trademark of the Object Management Group, Inc. in the United States and other countries. All other trademarks that appear herein are the property of their respective owners.

While the information in this publication is believed to be accurate, IONA Technologies PLC makes no warranty of any kind to this material including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. IONA Technologies PLC shall not be liable for errors contained herein, or for incidental or consequential damages in connection with the furnishing, performance or use of this material.

COPYRIGHT NOTICE

No part of this publication may be reproduced, stored in a retrieval system or transmitted, in any form or by any means, photocopying, recording or otherwise, without prior written consent of IONA Technologies PLC. No third party intellectual property right liability is assumed with respect to the use of the information contained herein. IONA Technologies PLC assumes no responsibility for errors or omissions contained in this book. This publication and features described herein are subject to change without notice.

Copyright © 2001, 2003 IONA Technologies PLC. All rights reserved.

All products or services mentioned in this manual are covered by the trademarks, service marks, or product names as designated by the companies who market those products.

Updated: 25-Nov-2003

M 3 1 7 1

Contents

List of Figures	xiii
List of Tables	xvii
Preface	xix
Chapter 1 Introduction to Orbix	1
Why CORBA?	2
CORBA Objects	4
Object Request Broker	6
CORBA Application Basics	7
Servers and the Portable Object Adapter	8
Orbix Plug-In Design	10
Development Tools	12
Orbix Application Deployment	14
CORBA Features and Services	16
Orbix C++ Development on OS/390	19
Chapter 2 Getting Started with Orbix	21
Setting the Orbix Environment	22
Hello World Example	23
Development Using the Client/Server Wizard	25
Development from the Command Line	35
Chapter 3 First Application	41
Development Using Code Generation	43
Development Without Using Code Generation	46
Locating CORBA Objects	48
Development Steps	50
Enhancing Server Functionality	74
Create a Termination Handler Object	75
Complete Source Code for server.cxx	87

Chapter 4	Defining Interfaces	93
	Modules and Name Scoping	95
	Interfaces	97
	Interface Contents	99
	Operations	100
	Attributes	103
	Exceptions	104
	Empty Interfaces	105
	Inheritance of IDL Interfaces	106
	Forward Declaration of IDL Interfaces	110
	Local Interfaces	111
	Valuetypes	113
	Abstract Interfaces	114
	IDL Data Types	116
	Built-in Types	117
	Extended Built-in Types	119
	Complex Data Types	122
	Pseudo Object Types	127
	Defining Data Types	128
	Constants	129
	Constant Expressions	132
Chapter 5	Developing Applications with Genies	135
	Starting Development Projects	137
	Genie Syntax	138
	Specifying Application Components	140
	Selecting Interfaces	142
	Including Files	143
	Implementing Servants	144
	Implementing the Server Mainline	148
	Implementing a Client	152
	Generating a Makefile	153
	Controlling Code Completeness	154
	General Options	158
	Compiling the Application	159
	Generating Signatures of Individual Operations	160
	Configuration Settings	161

Chapter 6 ORB Initialization and Shutdown	163
Initializing the ORB Runtime	164
Shutting Down the ORB	166
Shutting Down a Client	167
Shutting down a server	168
Chapter 7 Using Policies	171
Creating Policy and PolicyList Objects	173
Setting Orb and Thread Policies	175
Setting Server-Side Policies	178
Setting Client Policies	180
Setting Policies at Different Scopes	181
Managing Object Reference Policies	182
Getting Policies	185
Chapter 8 Developing a Client	187
Mapping IDL Interfaces to Proxies	188
Using Object References	190
Counting References	192
Nil References	194
Object Reference Operations	195
Using _ptr References	198
Using _var References	201
String Conversions	205
Initializing and Shutting Down the ORB	209
Invoking Operations and Attributes	210
Passing Parameters in Client Invocations	211
Simple Parameters	212
Fixed-Length Complex Parameters	213
Fixed-Length Array Parameters	215
String Parameters	217
_out Types	220
Variable-Length Complex Parameters	223
Variable-Length Array Parameters	225
Object Reference Parameters	227
Parameter-Passing Rules: Summary	229
Client Policies	233
RebindPolicy	234

SyncScopePolicy	235
Timeout Policies	236
Implementing Callback Objects	245
Chapter 9 Developing a Server	247
POAs, Skeletons, and Servants	249
Mapping Interfaces to Skeleton Classes	251
Creating a Servant Class	254
Implementing Operations	256
Activating CORBA Objects	257
Handling Output Parameters	259
Simple Parameters	260
Fixed-Length Complex Parameters	261
Fixed-Length Array Parameters	263
String Parameters	265
Variable-Length Complex Parameters	267
Variable-Length Array Parameters	269
Object Reference Parameters	271
Counting Servant References	273
Delegating Servant Implementations	274
Implementation Inheritance	276
Interface Inheritance	277
Multiple Inheritance	278
Explicit Event Handling	279
Termination Handler	280
Compiling and Linking	282
Chapter 10 Managing Server Objects	283
Mapping Objects to Servants	285
Creating a POA	287
Setting POA Policies	289
Root POA Policies	293
Using POA Policies	294
Enabling the Active Object Map	295
Processing Object Requests	296
Setting Object Lifespan	298
Assigning Object IDs	301
Activating Objects with Dedicated Servants	302

Activating Objects	303
Setting Threading Support	304
Explicit Object Activation	305
Implicit Object Activation	306
Calling <code>_this()</code> Inside an Operation	307
Calling <code>_this()</code> Outside an Operation	308
Managing Request Flow	311
Work Queues	313
ManualWorkQueue	315
AutomaticWorkQueue	317
Using a WorkQueue	320
Controlling POA Proxification	323
Chapter 11 Managing Servants	325
Using Servant Managers	327
Servant Activators	329
Servant Locators	335
Using a Default Servant	340
Setting a Default Servant	343
Creating Inactive Objects	344
Chapter 12 Asynchronous Method Invocations	347
Implied IDL	350
Calling Back to Reply Handlers	351
Interface-to-Reply Handler Mapping	352
Implementing a Client with Reply Handlers	355
Chapter 13 Exceptions	359
Exception Code Mapping	361
User-Defined Exceptions	362
Handling Exceptions	364
Handling User Exceptions	365
Handling System Exceptions	367
Evaluating System Exceptions	369
Throwing Exceptions	373
Exception Safety	374
Throwing System Exceptions	377

Chapter 14 Using Type Codes	379
Type Code Components	380
Type Code Operations	383
General Type Code Operations	384
Type Code Constants	390
Chapter 15 Using the Any Data Type	393
Inserting Typed Values Into Any	395
Extracting Typed Values From Any	398
Inserting and Extracting Booleans, Octets, Chars and WChars	401
Inserting and Extracting Array Data	402
Inserting and Extracting String Data	403
Inserting and Extracting Alias Types	406
Querying a CORBA::Any's Type Code	408
Using DynAny Objects	409
Creating a DynAny	412
create_dyn_any()	413
create_dyn_any_from_type_code()	415
Inserting and Extracting DynAny Values	417
Insertion Operations	418
Extraction Operations	420
Iterating Over DynAny Components	422
Accessing Constructed DynAny Values	424
Chapter 16 Generating Interfaces at Runtime	435
Using the DII	437
Constructing a Request Object	439
_request()	440
_create_request()	443
Invoking a Request	446
Retrieving Request Results	447
Invoking Deferred Synchronous Requests	448
Using the DSI	449
DSI Applications	450
Programming a Server to Use DSI	451
Chapter 17 Using the Interface Repository	453
Interface Repository Data	455

Abstract Base Interfaces	456
Repository Object Types	457
Containment in the Interface Repository	464
Contained Interface	467
Container Interface	469
Repository Object Descriptions	471
Retrieving Repository Information	474
Sample Usage	478
Repository IDs and Formats	480
Controlling Repository IDs with Pragma Directives	482
Chapter 18 Naming Service	485
Naming Service Design	487
Defining Names	489
Representing Names as Strings	491
Initializing a Name	492
Converting a Name to a StringName	493
Obtaining the Initial Naming Context	494
Building a Naming Graph	495
Binding Naming Contexts	496
Binding Object References	500
Rebinding	501
Using Names to Access Objects	502
Exceptions Returned to Clients	505
Listing Naming Context Bindings	506
Using a Binding Iterator	507
Maintaining the Naming Service	510
Federating Naming Graphs	512
Sample Code	518
Object Groups and Load Balancing	521
Using Object Groups in Orbix	525
Load Balancing Example	528
Creating an Object Group and Adding Objects	530
Accessing Objects from a Client	537
Chapter 19 Persistent State Service	539
Defining Persistent Data	540
Datastore Model	541

Abstract Types and Implementations	543
Defining Storage Objects	544
Defining Storage Homes	546
Implementing Storage Objects	551
Implementing Storage Homes	553
Accessing Storage Objects	555
Creating Transactional Sessions	556
Using the SessionManager	559
Managing Transactional Sessions	566
Getting a Storage Object Incarnation	576
Querying Data	577
Associating CORBA and Storage Objects	578
Thread Safety	579
Using Replication	580
PSDL Language Mappings	585
abstract storagehome	587
abstract storagetype	588
Ref_var Classes	592
State Members	593
Operation Parameters	595
storagetype	596
storagehome	598
Factory Native Types	600
Chapter 20 Event Service	601
Overview	602
Event Communication Models	604
Developing an Application Using Untyped Events	608
Obtaining an Event Channel	609
Implementing a Supplier	612
Implementing a Consumer	618
Developing an Application Using Typed Events	624
Creating the Interface	625
Obtaining a Typed Event Channel	626
Implementing the Supplier	630
Implementing the Consumer	634
Chapter 21 Portable Interceptors	639

Interceptor Components	641
Interceptor Types	642
Service Contexts	644
PICurrent	645
Tagged Components	647
Codec	648
Policy Factory	650
ORB Initializer	651
Writing IOR Interceptors	652
Using RequestInfo Objects	655
Writing Client Interceptors	657
Interception Points	659
Interception Point Flow	660
ClientRequestInfo	664
Client Interceptor Tasks	667
Writing Server Interceptors	671
Interception Points	672
Interception Point Flow	673
ServerRequestInfo	677
Server Interceptor Tasks	680
Registering Portable Interceptors	684
Implementing an ORB Initializer	685
Registering an ORBInitializer	691
Setting Up Orbix to Use Portable Interceptors	692
Appendix A Orbix IDL Compiler Options	693
Command Line Switches	694
Plug-in Switch Modifiers	695
IDL Configuration File	700
Appendix B IONA Foundation Classes Library	705
Installed IFC Directories	706
Selecting an IFC Library	707
Appendix C Orbix C++ Libraries	709
Appendix D IONA Policies	713
Client Side Policies	714

CONTENTS

POA Policies	717
Security Policies	719
Firewall Proxy Policies	721
Index	723

List of Figures

Figure 1: The nature of abstract CORBA objects	4
Figure 2: The object request broker	6
Figure 3: Invoking on a CORBA object	7
Figure 4: The portable object adapter	8
Figure 5: Client makes a single operation call on a server	23
Figure 6: Simple strategy for passing object references to clients	49
Figure 7: Multiple inheritance of IDL interfaces	107
Figure 8: Reference count for Account proxy is set to one.	192
Figure 9: Reference for Account proxy is incremented to 2.	193
Figure 10: Multiple <code>_ptr</code> references to a proxy object can leave the reference count unchanged.	199
Figure 11: The server-side ORB conveys client requests to the POA via its manager, and the POA dispatches the request to the appropriate servant.	250
Figure 12: A servant class can inherit base class implementations.	276
Figure 13: A servant class can implement operations of all base skeleton classes.	277
Figure 14: Inheritance options among servant and base skeleton classes.	278
Figure 15: A portable object adapter (POA) maps abstract objects to their concrete implementations (servants)	285
Figure 16: On the first request on an object, the servant activator returns a servant to the POA, which establishes the mapping in its active object map.	329
Figure 17: The POA directs each object request to the servant locator, which returns a servant to the POA to process the request.	335
Figure 18: Reply handler implementation	355
Figure 19: The C++ mapping arranges exceptions into a hierarchy	361
Figure 20: Interfaces that derive from the <code>DynAny</code> interface	409
Figure 21: Hierarchy of interface repository objects	460
Figure 22: A naming graph is a hierarchy of naming contexts	487

LIST OF FIGURES

Figure 23: Checking context bound to initial naming context	497
Figure 24: Savings and Loans naming contexts bound to initial naming context	497
Figure 25: Binding an object reference to a naming context	500
Figure 26: Destroying a naming context and removing related bindings	511
Figure 27: A naming graph that spans multiple servers	513
Figure 28: Multiple naming graphs are linked by binding initial naming contexts of several servers to a root server.	515
Figure 29: The root server's initial naming context is bound to the initial naming contexts of other servers, allowing clients to locate the root naming context.	516
Figure 30: Associating a name with an object group	522
Figure 31: Architecture of the stock market example	528
Figure 32: A server process uses sessions to establish a logical connection with a datastore and its contents	555
Figure 33: Transactional session states	570
Figure 34: Suppliers and consumers communicating through an event channel	602
Figure 35: Event propagation in a CORBA system	603
Figure 36: Push model of event transfer	604
Figure 37: Pull Model suppliers and consumers communicating through an event channel	605
Figure 38: Push suppliers and pull consumers communicating through an event channel	606
Figure 39: Push consumers pushing typed events to typed push consumers	607
Figure 40: Client interceptors allow services to access outgoing requests and incoming replies.	643
Figure 41: PICurrent facilitates transfer of thread context data to a request or reply.	645
Figure 42: Client interceptors process a normal reply.	660
Figure 43: Client interceptors process a LOCATION_FORWARD reply.	661
Figure 44: send_request throws an exception in a client-side interceptor	662
Figure 45: Client interceptors can change the nature of the reply.	663
Figure 46: Server interceptors receive request and send exception thrown by target object.	674
Figure 47: receive_request_service_contexts throws an exception and interception flow is aborted.	675
Figure 48: Server interceptors can change the reply type.	676

Figure 49: Configuration file format	700
Figure 50: Distributed IDL configuration file	701

LIST OF FIGURES

List of Tables

Table 1: CORBA::LocalObject pseudo-operation returns	112
Table 2: Built-in IDL types	117
Table 3: Extended built-in IDL types	119
Table 4: Component specifier arguments to <code>cpp_poa_genie.tcl</code>	138
Table 5: Optional switches to <code>cpp_poa_genie.tcl</code>	138
Table 6: Wildcard pattern matching to interface names	142
Table 7: Arguments that control servant generation	144
Table 8: Options affecting the server	148
Table 9: Parameter passing for low-level mapping	230
Table 10: Parameter passing with <code>_var</code> types	231
Table 11: Timeout Policies	236
Table 12: POA policy factories and argument options	290
Table 13: POA manager states and interface operations	311
Table 14: Reply Handler Operation Types for Normal Replies	353
Table 15: Reply Handler Operation Types for Exceptional Replies	353
Table 16: Base minor code values for Orbix subsystems	370
Table 17: Type Codes and Parameters	381
Table 18: Type-Specific Operations	386
Table 19: Information Obtained by Type-Specific Operations	388
Table 20: Interface Repository Object Types	457
Table 21: Container and Contained Objects in the Interface Repository	465
Table 22: <code>SessionManager</code> parameters	561
Table 23: <code>ParameterList</code> settings for a <code>TransactionalSession</code>	569
Table 24: Isolation levels	573
Table 25: Mapping for PSDL parameters	595

LIST OF TABLES

Table 26: Client Interception Point Access to ClientRequestInfo	664
Table 27: Server Interception Point Access to ServerRequestInfo	678
Table 28: Modifiers for all C++ plug-in switches	695
Table 29: Modifier for -base, -psdl, and -pss_r plugin switches	696
Table 30: Modifiers for -jbase and -jpoa switches	697
Table 31: Modifiers for -poa switch	698

Preface

Orbix is a full implementation from IONA Technologies of the Common Object Request Broker Architecture (CORBA), as specified by the Object Management Group. Orbix complies with the following specifications:

- CORBA 2.3
- GIOP 1.2 (default), 1.1, and 1.0

Read [Chapter 1](#) for an overview of Orbix. [Chapter 2](#) shows how you can use code-generation genies to build a distributed application quickly and easily. [Chapter 3](#) describes in detail the basic steps in building client and server programs. Subsequent chapters expand on those steps by focusing on topics that are related to application development.

Orbix documentation is periodically updated. New versions between releases are available at this site:

<http://www.iona.com/docs>

If you need help with this or any other IONA products, contact IONA at support@iona.com. Comments on IONA documentation can be sent to docs-support@iona.com.

Audience

The *CORBA Programmer's Guide* is intended to help you become familiar with Orbix, and show how to develop distributed applications using Orbix components. This guide assumes that you are familiar with programming in C++.

This guide does not discuss every API in great detail, but gives a general overview of the capabilities of the Orbix development kit and how various components fit together.

Document conventions

This guide uses the following typographical conventions:

Fixed-width Fixed-width font in normal text represents portions of code and literal names of items such as classes, functions, variables, and data structures. For example, text might refer to the `CORBA:ObjectClass`.

Constant width paragraphs represent code examples or information a system displays on the screen. For example:

```
# include <stdio.h>
```

Italic Italic words in normal text represent *new terms*.

italic Italicized fixed-width font in syntax and in text denotes variables that you supply, such as arguments to commands, or path names. For example:

```
% cd /users/your-name
```

This guide may use the following keying conventions:

% A percent sign represents the UNIX command shell prompt for a command that does not require root privileges.

> The notation `>` represents the DOS, Windows NT, Windows95, or Windows98 command prompt.

... Ellipses in sample code and syntax descriptions indicate that material has been eliminated to simplify a discussion.

[] Italicized brackets enclose optional items in format and syntax descriptions.

{ } Braces enclose a list from which you must choose an item in format and syntax descriptions.

| A vertical bar separates items in a list of choices enclosed in `{ }` (braces) in format and syntax descriptions.

Introduction to Orbix

With Orbix, you can develop and deploy large-scale enterprise-wide CORBA systems in C++ and Java. Orbix has an advanced modular architecture that lets you configure and change functionality without modifying your application code, and a rich deployment architecture that lets you configure and manage a complex distributed system.

In this chapter

This chapter contains the following sections:

Why CORBA?	page 2
CORBA Application Basics	page 7
Servers and the Portable Object Adapter	page 8
Orbix Plug-In Design	page 10
Development Tools	page 12
Orbix Application Deployment	page 14
CORBA Features and Services	page 16
Orbix C++ Development on OS/390	page 19

Why CORBA?

Overview

Today's enterprises need flexible, open information systems. Most enterprises must cope with a wide range of technologies, operating systems, hardware platforms, and programming languages. Each of these is good at some important business task; all of them must work together for the business to function.

The common object request broker architecture—CORBA—provides the foundation for flexible and open systems. It underlies some of the Internet's most successful e-business sites, and some of the world's most complex and demanding enterprise information systems.

What is CORBA?

CORBA is an open, standard solution for distributed object systems. You can use CORBA to describe your enterprise system in object-oriented terms, regardless of the platforms and technologies used to implement its different parts. CORBA objects communicate directly across a network using standard protocols, regardless of the programming languages used to create objects or the operating systems and platforms on which the objects run.

CORBA solutions are available for every common environment and are used to integrate applications written in C, C++, Java, Ada, Smalltalk, and COBOL, running on embedded systems, PCs, UNIX hosts, and mainframes. CORBA objects running in these environments can cooperate seamlessly. Through COMet, IONA's dynamic bridge between CORBA and COM, they can also interoperate with COM objects.

CORBA is widely available and offers an extensive infrastructure that supports all the features required by distributed business objects. This infrastructure includes important distributed services, such as transactions, security, and messaging.

Orbix E2A

Orbix E2A provides a CORBA development platform for building high-performance systems. Orbix's modular architecture supports the most demanding requirements for scalability, performance, and deployment flexibility. The Orbix E2A architecture is also language-independent and can

be implemented in Java and C++. Orbix E2A CORBA applications can interoperate via the standard IOP protocol with applications built on any CORBA-compliant technology.

CORBA Objects

CORBA objects are abstract objects in a CORBA system that provide distributed object capability between applications in a network. [Figure 1](#) shows that any part of a CORBA system can refer to the abstract CORBA object, but the object is only implemented in one place and time on some server of the system.




Figure 1: *The nature of abstract CORBA objects*

An *object reference* is used to identify, locate, and address a CORBA object. Clients use an object reference to invoke requests on a CORBA object. CORBA objects can be implemented by servers in any supported programming language, such as C++ or Java.

Although CORBA objects are implemented using standard programming languages, each CORBA object has a clearly-defined interface, specified in the *CORBA Interface Definition Language (IDL)*. The *interface definition* specifies which member functions, data types, attributes, and exceptions are available to a client, without making any assumptions about an object's implementation.

With a few calls to an ORB's application programming interface (API), servers can make CORBA objects available to client programs in your network.

To call member functions on a CORBA object, a client programmer needs only to refer to the object's interface definition. Clients can call the member functions of a CORBA object using the normal syntax of the chosen programming language. The client does not need to know which programming language implements the object, the object's location on the network, or the operating system in which the object exists.

Using an IDL interface to separate an object's use from its implementation has several advantages. For example, you can change the programming language in which an object is implemented without affecting the clients that access the object. You can also make existing objects available across a network.

Object Request Broker

CORBA defines a standard architecture for object request brokers (ORB). An ORB is a software component that mediates the transfer of messages from a program to an object located on a remote network host. The ORB hides the underlying complexity of network communications from the programmer.

An ORB lets you create standard software objects whose member functions can be invoked by *client* programs located anywhere in your network. A program that contains instances of CORBA objects is often known as a *server*. However, the same program can serve at different times as a client and a server. For example, a server program might itself invoke calls on other server programs, and so relate to them as a client.

When a client invokes a member function on a CORBA object, the ORB intercepts the function call. As shown in [Figure 2](#), the ORB redirects the function call across the network to the target object. The ORB then collects results from the function call and returns these to the client.




Figure 2: *The object request broker*

CORBA Application Basics

You start developing a CORBA application by defining interfaces to objects in your system in CORBA IDL. You compile these interfaces with an IDL compiler. An IDL compiler generates C++ or Java code from IDL definitions. This code includes *client stub code* with which you develop client programs, and *object skeleton code*, which you use to implement CORBA objects.

When a client calls a member function on a CORBA object, the call is transferred through the client stub code to the ORB. Because the implemented object is not located in the client's address space, CORBA objects are represented in client code by *proxy objects*.

A client invokes on object references that it obtains from the server process. The ORB then passes the function call through the object skeleton code to the target object.




Figure 3: Invoking on a CORBA object

Servers and the Portable Object Adapter

Server processes act as containers for one or more *portable object adapters*. A portable object adapter, or POA, maps abstract CORBA objects to their actual implementations, or *servants*, as shown in [Figure 4](#). Because the




Figure 4: *The portable object adapter*

POA assumes responsibility for mapping servants to abstract CORBA objects, the way that you define or change an object's implementation is transparent to the rest of the application. By abstracting an object's identity from its implementation, a POA enables a server to be portable among different implementations.

Depending on the policies that you set on a POA, object-servant mappings can be static or dynamic. POA policies also determine whether object references are persistent or transient, and the threading model that it uses. In all cases, the policies that a POA uses to manage its objects are invisible to clients.

A server can have one or more nested POAs. Because each POA has its own set of policies, you can group objects logically or functionally among multiple POAs, where each POA is defined in a way that best accommodates the needs of the objects that it processes.

Orbix Plug-In Design

Orbix has a modular *plug-in* architecture. The ORB core supports abstract CORBA types and provides a plug-in framework. Support for concrete features like specific network protocols, encryption mechanisms, and database storage is packaged into plug-ins that can be loaded into the ORB based on runtime configuration settings.

Plug-ins

A plug-in is a code library that can be loaded into an Orbix application at runtime. A plug-in can contain any type of code; typically, it contains objects that register themselves with the ORB runtimes to add functionality.

Plug-ins can be linked directly with an application, loaded when an application starts up, or loaded on-demand while the application is running. This gives you the flexibility to choose precisely those ORB features that you actually need. Moreover, you can develop new features such as protocol support for direct ATM or HTTPNG. Because ORB features are *configured* into the application rather than *compiled* in, you can change your choices as your needs change without rewriting or recompiling applications.

For example, an application that uses the standard IIOF protocol can be reconfigured to use the secure SSL protocol simply by configuring a different transport plug-in. No one transport is inherent to the ORB core; you simply load the transport set that suits your application best. This architecture makes it easy for IONA to support additional transports in the future such as multicast or special purpose network protocols.

ORB core

The ORB core presents a uniform programming interface to the developer: *everything is a CORBA object*. This means that everything appears to be a local C++ or Java object within the process. In fact it might be a local object, or a remote object reached by some network protocol. It is the ORB's job to get application requests to the right objects no matter where they live.

To do its job, the ORB loads a collection of plug-ins as specified by ORB configuration settings—either on startup or on demand—as they are needed by the application. For remote objects, the ORB intercepts local function calls and turns them into CORBA *requests* that can be dispatched to a remote object.

In order to send a request on its way, the ORB core sets up a chain of *interceptors* to handle requests for each object. The ORB core neither knows nor cares what these interceptors do, it simply passes the request along the interceptor chain. The chain might be a single interceptor which sends the request with the standard IIOP protocol, or a collection of interceptors that add transaction information, encrypt the message and send it on a secure protocol such as SSL. All of this is transparent to the application, so you can change the protocol or services used by your application simply by configuring a different set of interceptors.

Development Tools

The CORBA developer's environment contains a number of facilities and features that help you and your development team be more productive.

Code generation toolkit

IONA provides a code generation toolkit that simplifies and streamlines the development effort. You only need to define your IDL interfaces; out-of-the-box scripts generate a complete client/server application automatically from an IDL file.

The toolkit also can be useful for debugging: you can use an auto-generated server to debug your client, and vice versa. Advanced users can write code generation scripts to automate repetitive coding in a large application.

For more information about the code generation toolkit, refer to the *CORBA Code Generation Toolkit Guide*.

Multi-threading support

Orbix provides excellent support for multi-threaded applications. Orbix libraries are multi-threaded and thread-safe. Orbix servers use standard POA policies to enable multi-threading. The ORB creates a thread pool that automatically grows or shrinks depending on demand load. Thread pool size, growth and request queuing can be controlled by configuration settings without any coding.

Of course, multi-threaded applications must themselves be thread-safe. This usually means they need to use thread-synchronization objects such as mutexes or semaphores. Although most platforms provide similar thread synchronization facilities, the interfaces vary widely. Orbix includes an object-oriented thread synchronization portability library which allows you to write portable multi-threaded code.

Configuration and logging interfaces

Applications can store their own configuration information in Orbix configuration domains, taking advantage of the infrastructure for ORB configuration. CORBA interfaces provide access to configuration information in application code.

Applications can also take advantage of the Orbix logging subsystem, again using CORBA interfaces to log diagnostic messages. These messages are logged to log-stream objects that are registered with the ORB. Log streams

for local output, file logging and system logging (Unix syslogd or Windows Event Service) are provided with Orbix. You can also implement your own log streams, which capture ORB and application diagnostics and send them to any destination you desire.

Portable interceptors

Portable interceptors allow an application to intervene in request handling. They can be used to log per-request information, or to add extra “hidden” data to requests in the form of GIOP service contexts—for example, transaction information or security credentials.

Orbix Application Deployment

Orbix provides a rich deployment environment designed for high scalability. You can create a *location domain* that spans any number of hosts across a network, and can be dynamically extended with new hosts. Centralized domain management allows servers and their objects to move among hosts within the domain without disturbing clients that use those objects. Orbix supports load balancing across object groups. A *configuration domain* provides the central control of configuration for an entire distributed application.

Orbix offers a rich deployment environment that lets you structure and control enterprise-wide distributed applications. Orbix provides central control of all applications within a common domain.

Location domains

A location domain is a collection of servers under the control of a single locator daemon. The locator daemon can manage servers on any number of hosts across a network. The locator daemon automatically activates remote servers through a stateless activator daemon that runs on the remote host.

The locator daemon also maintains the implementation repository, which is a database of available servers. The implementation repository keeps track of the servers available in a system and the hosts they run on. It also provides a central forwarding point for client requests. By combining these two functions, the locator lets you relocate servers from one host to another without disrupting client request processing. The locator redirects requests to the new location and transparently reconnects clients to the new server instance. Moving a server does not require updates to the naming service, trading service, or any other repository of object references.

The locator can monitor the state of health of servers and redirect clients in the event of a failure, or spread client load by redirecting clients to one of a group of servers.

Configuration domains

A configuration domain is a collection of applications under common administrative control. A configuration domain can contain multiple location domains.

Orbix supports two mechanisms to administer a configuration domain:

- During development, or for small-scale deployment, configuration can be stored in an ASCII text file, which is edited directly.
- For larger deployments, Orbix provides a distributed configuration server that enables centralized configuration for all applications spread across a network.

The configuration mechanism is loaded as a plug-in, so future configuration systems can be extended to load configuration from any source such as example HTTP or third-party configuration systems.

CORBA Features and Services

Orbix fully supports the latest CORBA specification, and in some cases anticipates features to be included in upcoming specifications.

Full CORBA 2.3 support and interoperability

All CORBA 2.3 IDL data types are fully supported, including:

- Extended precision numeric types for 64 bit integer and extended floating point calculations.
- Fixed point decimals for financial calculations.
- International character sets, including support for code-set negotiation where multiple character sets are available.
- Objects by value: you can define objects that are passed by value as well as the traditional pass-by-reference semantics of normal CORBA objects. This is particularly relevant in Java based systems, but also supported for C++ using object factories.

Orbix supports the most recent 1.2 revision of the CORBA standard General Inter-ORB Protocol (GIOP) and Internet Inter-ORB Protocol (IIOP), and also supports previous 1.1 and 1.0 revisions for backwards compatibility with applications based on other ORBs. Orbix is interoperable with any CORBA-compliant application that uses the standard IIOP protocol.

Asynchronous messaging and quality of service

Orbix implements two key parts of the CORBA messaging specification that are included in CORBA 3.0.

- Asynchronous messaging interfaces allow easy, type-safe asynchronous calls to normal CORBA operations. This means that clients can make a request on a remote service, and then carry on with other work until the reply is ready.
- ORB quality-of-service policies provide finer standardized control over how the ORB processes requests. For example, you can specify how quickly a client resumes processing after sending one-way requests.

Interoperable naming service and load balancing extensions

Orbix supports the interoperable naming service specification. This is a superset of the original CORBA naming service which adds some ease-of-use features and provides a standard URL format for CORBA object references to simplify configuration and administration of CORBA services.

The Orbix naming service also supports IONA-specific load-balancing extensions of OrbixNames 3. A group of objects can be registered against a single name; the naming service hands out references to clients so that the client load is spread across the group.

Object transaction service

Orbix includes the object transaction service (OTS) which is optimized for the common case where only a single resource (database) is involved in a transaction. Applications built against the single resource OTS can easily be reconfigured to use a full-blown OTS when it is available, since the interfaces are identical. With Orbix plug-in architecture, applications will not even need to be recompiled. For the many applications where transactions do not span multiple databases, the single-resource OTS will continue to be a highly efficient solution, compared to a full OTS that performs extensive logging to guarantee transaction integrity.

Event service

Orbix supports the CORBA event service specification, which defines a model for indirect communications between ORB applications. A client does not directly invoke an operation on an object in a server. Instead, the client sends an event that can be received by any number of objects. The sender of an event is called a *supplier*; the receivers are called *consumers*. An intermediary *event channel* takes care of forwarding events from suppliers to consumers.

Orbix supports both the *push* and *pull* model of event transfer, as defined in the CORBA event specification. Orbix performs event transfer using the *untyped* format, whereby events are based on a standard operation call that takes a generic parameter of type `any`.

SSL/TLS

Orbix SSL/TLS provides data security for applications that communicate across networks by ensuring authentication, privacy, and integrity features for communications across TCP/IP connections.

TLS is a transport layer security protocol layered between application protocols and TCP/IP, and can be used for communication by all Orbix SSL/TLS components and applications.

COMet

OrbixCOMet provides a high performance dynamic bridge that enables transparent communication between COM/Automation clients and CORBA servers.

OrbixCOMet is designed to give COM programmers—who use tools such as Visual C++, Visual Basic, PowerBuilder, Delphi, or Active Server Pages on the Windows desktop—easy access to CORBA applications running on Windows, UNIX, or mainframe environments. COM programmers can use the tools familiar to them to build heterogeneous systems that use both COM and CORBA components within a COM environment.

Persistent state service

Orbix includes the first implementation of the persistent state service (PSS). PSS interposes a CORBA-based abstraction layer between a server and its persistent storage. Orbix's implementation of PSS is based on Berkeley DB, an efficient embedded database that is included with Orbix. By adding new PSS driver plug-ins, applications that use PSS can be reconfigured to store their data in any database without code changes or recompilation.

Dynamic type support: interface repository and dynany

Orbix has full support for handling data values that are not known at compile time. The interface repository stores information about all CORBA types known to the system and can be queried at runtime. Clients can construct requests based on runtime type information using the dynamic invocation interface (DII), and servers can implement “universal” objects that can implement any interface at run time with the dynamic skeleton interface (DSI).

Although all of these features have been available since early releases of the CORBA specification, they are incomplete without the addition of the DynAny interface. This interface allows clients and servers to interpret or construct values based purely on runtime information, without any compiled-in data types.

These features are ideal for building generic object browsers, type repositories, or protocol gateways that map CORBA requests into another object protocol.

Orbix C++ Development on OS/390

Overview

This section outlines the main information sources relating to Orbix C++ application development in both a native OS/390 and UNIX System Services environment.

Note: You cannot use the CORBA Code Generation Toolkit in either a native OS/390 or UNIX System Services environment.

Native OS/390

The material in this guide that relates to writing C++ applications is relevant to C++ application development on native OS/390. However, the material that relates to the use of the CORBA Code Generation Toolkit, and to building and running applications, is not relevant.

For details about building and running Orbix C++ applications in a native OS/390 environment, see the readme files and JCL that are supplied in your Orbix Mainframe product installation as follows (where *orbixhlq* represents your higher-level qualifier):

- *orbixhlq* DEMOS CPP README
- *orbixhlq* DEMOS CPP BLD JCL
- *orbixhlq* DEMOS CPP RUN JCL

OS/390 UNIX System Services

The material in this guide that relates to writing C++ applications, and to building and running them in a UNIX environment, is relevant to C++ application development on OS/390 UNIX System Services. However, the material that relates to the use of the CORBA Code Generation Toolkit is not relevant.

Getting Started with Orbix

You can use the CORBA Code Generation Toolkit to develop an Application Server Platform application quickly.

Given a user-defined IDL interface, the toolkit generates the bulk of the client and server application code, including makefiles. You then complete the distributed application by filling in the missing business logic.

In this chapter

This chapter contains the following sections:

Setting the Orbix Environment	page 22
Hello World Example	page 23
Development Using the Client/Server Wizard	page 25
Development from the Command Line	page 35

Setting the Orbix Environment

Prerequisites

Before proceeding with the demonstration in this chapter you need to ensure:

- The CORBA developer's kit is installed on your host.
- Application Server Platform is configured to run on your host platform.

The *Orbix Administrator's Guide* contains more information on Application Server Platform configuration, and details of Application Server Platform command line utilities.

Note: Orbix Mainframe does not support the code generation toolkit and distributed genies. For information about building applications in a native OS/390 environment, see the readme files and JCL that are supplied in the DEMO data sets of your Orbix Mainframe installation.

Setting the Domain

The scripts that set the Orbix environment are associated with a particular *domain*, which is the basic unit of Orbix configuration. Consult the *Orbix Installation Guide*, and the *Orbix Administrator's Guide* for further details on configuring your environment.

To set the Orbix environment associated with the *domain-name* domain, enter:

Windows

```
> config-dir\etc\bin\domain-name_envbat
```

UNIX

```
% .config-dir/etc/bin/domain-name_env
```

config-dir is the root directory where Orbix stores its configuration information. You specify this directory while configuring your domain. *domain-name* is the name of a configuration domain.

Hello World Example

This chapter shows how to create, build, and run a complete client/server demonstration with the help of the CORBA code generation toolkit. The architecture of this example system is shown in [Figure 5](#).




Figure 5: Client makes a single operation call on a server

The client and server applications communicate with each other using the Internet Inter-ORB Protocol (IIOP), which sits on top of TCP/IP. When a client invokes a remote operation, a request message is sent from the client to the server. When the operation returns, a reply message containing its return values is sent back to the client. This completes a single remote CORBA invocation.

All interaction between the client and server is mediated via a set of IDL declarations. The IDL for the Hello World! application is:

```
//IDL
interface Hello {
    string getGreeting();
};
```

The IDL declares a single `Hello` interface, which exposes a single operation `getGreeting()`. This declaration provides a language neutral interface to CORBA objects of type `Hello`.

The concrete implementation of the `HeIb` CORBA object is written in C++ and is provided by the server application. The server could create multiple instances of `HeIb` objects if required. However, the generated code generates only one `HeIb` object.

The client application has to locate the `HeIb` object—it does this by reading a stringified object reference from the file `HeIb.ref`. There is one operation `getGreeting()` defined on the `HeIb` interface. The client invokes this operation and exits.

Development Using the Client/Server Wizard

On the Windows NT platform, Orbix provides a wizard add-on to the Microsoft Visual Studio integrated development environment (IDE) that enables you to generate starting point code for CORBA applications.

If you are not working on a Windows platform or if you prefer to use a command line approach to development, see [“Development from the Command Line” on page 35](#).

Ordinarily, the client/server wizard is installed at the same time as Orbix. If the wizard is not on your system, however, consult the *Orbix Installation Guide* for instructions on how to install it.

You implement the `HelloWorld` application with the following steps:

1. [Define the IDL interface](#), `Helb`.
2. [Generate the server](#).
3. [Complete the server program](#) by implementing the single IDL `getGreeting()` operation.
4. [Build the server program](#).
5. [Generate the client](#).
6. [Complete the client program](#) by inserting a line of code to invoke the `getGreeting()` operation.
7. [Build the client program](#).
8. [Run the demonstration](#).

Define the IDL interface

Create the IDL file for the Hello World! application. First of all, make a directory to hold the example code:

```
> mkdir C:\OCGT\HelloExample
```

Create an IDL file `C:\OCGT\HelloExample\helb.idl` using a text editor.

Enter the following text into the `helb.idl` file:

```
//IDL
interface Helb {
    string getGreeting();
};
```


This interface mediates the interaction between the client and the server halves of the distributed application.

Generate the server

Generate files for the server application using the Orbix Code Generation Toolkit.


To create a server project using the Orbix client/server wizard:

1. Open the Microsoft Visual C++ 6.0 integrated development environment (IDE).
2. From the Visual C++ menus, select **File | New**
3. In the New dialog, click on the Projects tab.
4. In the Projects tab, perform these actions:
 - ◆ Select **IONA Orbix Client/Server Wizard**
 - ◆ In the **Project name** text box, enter `server`
 - ◆ Under the **Location** text box, enter `C:\OCGT\HelloExample\server`




5. Click **OK**.
The client/server wizard dialog displays.
6. Answer two questions as follows:


- ◆ **What CORBA IDL file would you like to use for this project?**
Enter the location of `hello.idl`
- ◆ **Would you like to generate a working client or server?**
Select **Server**



7. Advance to the next screen by clicking **Next**.
8. The server wizard displays the following dialog:



9. Accept the default settings and generate the server project by clicking **Finish**.
10. The New Project Information scrollbox tells you about the generated files. Browse the information and select **OK**.
11. The server workspace is generated with the following source files:



12. Read the text file `ReadmeOrbixServer.txt`.

Complete the server program

Complete the implementation class, `HelloImpl` by providing the definition of `getGreeting()`. This method implements the IDL operation `Hello::getGreeting()`.

Delete the generated boilerplate code that occupies the body of `HelloImpl::getGreeting()` and replace it with the highlighted line of code:

```
//C++
...
char*
HelloImpl::getGreeting()
{
    char* _result;

    _result = CORBA::string_dup("Hello World!");

    return _result;
}
...
```

The function `CORBA::string_dup()` allocates a copy of the string on the free store. This is needed to be consistent with the style of memory management used in CORBA programming.

Build the server program

From within the Visual C++ IDE select **Build | Build server.exe** to compile and link the server.

By default, the project builds with debug settings and the server executable is stored in `C:\CGT\HelloExample\server\debug\server.exe`.

Close the server workspace by selecting **File | Close Workspace**


Generate the client

Generate files for the client application using the Orbix code generation toolkit.

To create a client project using the IONA Application Server Platform client/server wizard:


1. Open the Microsoft Visual C++ 6.0 IDE.
2. From the Visual C++ menu, select **File | New**
3. In the New dialog, click on the Projects tab.
4. In the Projects tab, perform the following actions:
 - ◆ Select **IONA Application Server Platform Client/Server Wizard**
 - ◆ In the **Project name** text box, enter `client`

- ◆ Under the **Location** text box, enter
c:\OCGT\HelloExample\client




5. Click **OK**.
6. The client/server wizard displays.
7. Answer two questions as follows:
 - ◆ **What CORBA IDL file would you like to use for this project?**
Enter the location of `hello.idl`
 - ◆ **Would you like to generate a working client or server?**

Select Client



8. To generate the client project, click **Finish**
9. The New Project Information scrollbox tells you about the generated files. Browse the information and select **OK**
10. The client workspace is generated with the following source files:



11. Read the text file `ReadmeOrbixClient.txt`

Complete the client program

Complete the implementation of the client `main()` function in the `client.cxx` file. You must add a couple of lines of code to make a remote invocation of the operation `getGreeting()` on the `HeIb` object.

Search for the line where the `call_HeIb_getGreeting()` function is called. Delete this line and replace it with the two lines of code highlighted in bold font below:

```

/C++
/File: client.cpp
...
if (CORBA::is_nil(HeIb1))
{
    cerr << "Could not narrow reference to interface "
         << "HeIb" << endl;
}
else
{
    CORBA::String_var strV = Hello1->getGreeting();
    cout << "Greeting is: " << strV << endl;
}
...

```

The object reference `HeIb1` refers to an instance of a `HeIb` object in the server application. It is already initialized for you.

A remote invocation is made by invoking `getGreeting()` on the `HeIb1` object reference. The ORB automatically establishes a network connection and sends packets across the network to invoke the `HeIbImpl::getGreeting()` function in the server application.

The returned string is put into a C++ object, `strV`, of the type `CORBA::String_var`. The destructor of this object will delete the returned string so that there is no memory leak in the above code.

Build the client program

From within the Visual C++ IDE select **Build | Build client.exe** to compile and link the client.

By default, the project will build with debug settings and the client executable will be stored in

```
C:\OCGT\HelloExample\client\Debug\client.exe.
```

Close the client workspace by selecting **File | Close Workspace**.

Run the demonstration

Run the application as follows:

1. Run the Orbix services (if required).

If you have configured Orbix to use file-based configuration, no services need to run for this demonstration. Proceed to step [2](#).

If you have configured Orbix to use configuration repository based configuration, start up the basic Orbix services.

```
> start_domain-name_services.bat
```

Where *domain-name* is the name of your configuration domain.

2. Set Orbix's environment.

```
> domain-name_env.bat
```

3. Run the server program.

```
> cd C:\OCGT\HelloExample\server\Debug
> server.exe
```

The server outputs the following lines to the screen:

```
Initializing the ORB
Writing stringified object reference to Hello.ref
Waiting for requests...
```

The server performs the following steps when it is launched:

- ◆ It instantiates and activates a single `Hello` CORBA object.
- ◆ The stringified object reference for the `Hello` object is written to the file `C:\temp>Hello.ref`.
- ◆ The server opens an IP port and begins listening on the port for connection attempts by CORBA clients.

4. Run the client program.

Open a new MS-DOS prompt.

```
> cd C:\OCGT\HelloExample\client\Debug
> client.exe
```

The client outputs the following lines to the screen:

```
Client using random seed 0
Reading stringified object reference from Hello.ref
Greeting is: Hello World!
```

The client performs the following steps when it is run:

- ◆ It reads the stringified object reference for the `HeIb` object from the `C:\temp\HeIb.ref` file.
 - ◆ It converts the stringified object reference into an object reference.
 - ◆ It calls the remote `HeIb:getGreeting()` operation by invoking on the object reference. This causes a connection to be established with the server and the remote invocation to be performed.
5. When you are finished, terminate all processes.
 - ◆ The server can be shut down by typing `ctrl-c` in the window where it is running.
 6. Stop the Orbix services (if they are running).
From a DOS prompt enter:

```
> stop_domain-name_services
```

Development from the Command Line

Starting point code for CORBA client and server applications can also be generated using the `idgen` command line utility, which offers equivalent functionality to the client/server wizard presented in the previous section.

The `idgen` utility can be used on Windows and UNIX platforms.

You implement the `HeIbW oIdl` application with the following steps:

1. [Define the IDL interface](#), `HeIb`.
2. [Generate starting point code](#).
3. [Complete the server program](#) by implementing the single IDL `getGreeting()` operation.
4. [Complete the client program](#) by inserting a line of code to invoke the `getGreeting()` operation.
5. [Build the demonstration](#).
6. [Run the demonstration](#).

Define the IDL interface

Create the IDL file for the `HeIbW oIdl` application. First of all, make a directory to hold the example code:

Windows

```
> mkdir C:\OCGT\HeIbExample
```

UNIX

```
% mkdir -p OCGT/HeIbExample
```

Create an IDL file `C:\OCGT\HeIbExample\heIb.idl` (Windows) or `OCGT/HeIbExample/heIb.idl` (UNIX) using a text editor.

Enter the following text into the file `heIb.idl`:

```
//IDL
interface HeIb {
    string getGreeting();
};
```

This interface mediates the interaction between the client and the server halves of the distributed application.

Generate starting point code

Generate files for the server and client application using the CORBA Code Generation Toolkit.

In the directory `C:\OCGT\HelloExample` (Windows) or `OCGTHelloExample` (UNIX) enter the following command:

```
idlgen cpp_poa_genie.tcl -all hello.idl
```

This command logs the following output to the screen while it is generating the files:

```
hello.idl:
cpp_poa_genie.tcl: creating it_servant_base_overrides.h
cpp_poa_genie.tcl: creating it_servant_base_overrides.cxx
cpp_poa_genie.tcl: creating HelloIn.plh
cpp_poa_genie.tcl: creating HelloIn.plcxx
cpp_poa_genie.tcl: creating server.cxx
cpp_poa_genie.tcl: creating client.cxx
cpp_poa_genie.tcl: creating call_funcs.h
cpp_poa_genie.tcl: creating call_funcs.cxx
cpp_poa_genie.tcl: creating it_print_funcs.h
cpp_poa_genie.tcl: creating it_print_funcs.cxx
cpp_poa_genie.tcl: creating it_random_funcs.h
cpp_poa_genie.tcl: creating it_random_funcs.cxx
cpp_poa_genie.tcl: creating Makefile
```

You can edit the following files to customize client and server applications:

Client:

`client.cxx`

Server:

`server.cxx`
`HelloIn.plh`
`HelloIn.plcxx`

Complete the server program

Complete the implementation class, `HelloInPl`, by providing the definition of the `HelloInPl::getGreeting()` function. This C++ function provides the concrete realization of the `Hello::getGreeting()` IDL operation.

Edit the `HelbImpl.cpp` file, and delete most of the generated boilerplate code occupying the body of the `HelbImpl::getGreeting()` function. Replace it with the line of code highlighted in bold font below:

```
//C++
//File HelbImpl.cpp
...
char*
HelbImpl::getGreeting() throw (
    CORBA::SystemException
)
{
    char*          _result;

    _result = CORBA::string_dup("Hello World!");

    return _result;
}
...
```

The function `CORBA::string_dup()` allocates a copy of the `"Hello World!"` string on the free store. It would be an error to return a string literal directly from the CORBA operation because the ORB automatically deletes the return value after the function has completed. It would also be an error to create a copy of the string using the C++ `new` operator.

Complete the client program

Complete the implementation of the client `main()` function in the `client.cpp` file. You must add a couple of lines of code to make a remote invocation of the `getGreeting()` operation on the `Helb` object.

Edit the `client.cpp` file and search for the line where the `callHello_getGreeting()` function is called. Delete this line and replace it with the two lines of code highlighted in bold font below:

```

/C++
/File: client.cpp
...
if (CORBA::is_nil(Hello1))
{
    cerr << "Could not narrow reference to interface "
        << "Hello" << endl;
}
else
{
    CORBA::String_var strV = Hello1->getGreeting();
    cout << "Greeting is: " << strV << endl;
}
...

```

The object reference `Hello1` refers to an instance of a `Hello` object in the server application. It is already initialized for you.

A remote invocation is made by invoking `getGreeting()` on the `Hello1` object reference. The ORB automatically establishes a network connection and sends packets across the network to invoke the `HelloImpl::getGreeting()` function in the server application.

The returned string is put into a C++ object, `strV`, of the type `CORBA::String_var`. The destructor of this object will delete the returned string so that there is no memory leak in the above code.

Build the demonstration

The `Makefile` generated by the code generation toolkit has a complete set of rules for building both the client and server applications.

To build the client and server complete the following steps:

1. Open a command line window.
2. Go to the `..OCGTHelloExample` directory.
3. Enter:

Windows

```
> nmake
```

UNIX

```
% make -e
```

Run the demonstration

Run the application as follows:

1. Run the Orbix services (if required).

If you have configured Orbix to use file-based configuration, no services need to run for this demonstration. Proceed to step 2.

If you have configured Orbix to use configuration repository based configuration, start up the basic Orbix services.

Open a DOS prompt in Windows, or `xterm` in UNIX. Enter:

```
start_domain-name_services
```

Where `domain-name` is the name of the configuration domain.

2. Set Orbix's environment.

```
> domain-name_env
```

3. Run the server program.

Open a DOS prompt, or `xterm` window (UNIX). From the `C:\OCGT\HelbExample` directory enter the name of the executable file—`server.exe` (Windows) or `server` (UNIX). The server outputs the following lines to the screen:

```
initializing the ORB
Writing stringified object reference to Helb.ref
Waiting for requests...
```

The server performs the following steps when it is launched:

- ◆ It instantiates and activates a single `Helb` CORBA object.
- ◆ The stringified object reference for the `Helb` object is written to the local `Helb.ref` file.
- ◆ The server opens an IP port and begins listening on the port for connection attempts by CORBA clients.

4. Run the client program.

Open a new DOS prompt, or `xterm` window (UNIX). From the `C:\OCCT\HelloExample` directory enter the name of the executable file—`client.exe` (Windows) or `client` (UNIX).

The client outputs the following lines to the screen:

```
Client using random seed 0
Reading stringified object reference from Hello.ref
Greeting is:Hello World!
```

The client performs the following steps when it is run:

- ◆ It reads the stringified object reference for the `Hello` object from the `Hello.ref` file.
 - ◆ It converts the stringified object reference into an object reference.
 - ◆ It calls the remote `Hello::getGreeting()` operation by invoking on the object reference. This causes a connection to be established with the server and the remote invocation to be performed.
5. When you are finished, terminate all processes. Shut down the server by typing `ctrl-c` in the window where it is running.
 6. Stop the Orbix services (if they are running). From a DOS prompt in Windows, or `xterm` in UNIX, enter:

```
stop_domain-name_services
```

The passing of the object reference from the server to the client in this way is suitable only for simple demonstrations. Realistic server applications use the CORBA naming service to export their object references instead (see [Chapter 18](#)).

First Application

This chapter uses sample code to show how to develop an enterprise application with Orbix.

Orbix enterprise applications consist of CORBA objects with clearly defined interfaces that can be accessed across a network.

This chapter uses a simple application to describe the basic programming steps required to define CORBA objects, write server programs that implement those objects, and write client programs that access them. The programming steps are the same whether the client and server run on a single host or are distributed across a network.

The application described here performs these tasks:

- A server program creates a single object that represents a building such as a warehouse.
- A client program uses the object's interface to get the building's address, check its availability, and reserve it for specific dates.

To recreate this program, you must have installed and configured Orbix for your particular platform.

In this chapter


This chapter covers the following topics:

Development Using Code Generation	page 43
Development Without Using Code Generation	page 46
Locating CORBA Objects	page 48
Development Steps	page 50

Enhancing Server Functionality	page 74
Complete Source Code for server.cxx	page 87

Development Using Code Generation

With the code generation toolkit, you can automatically generate a large amount of the code required for the client and server programs:



First, you define a set of interfaces written in the OMG interface definition language (IDL). The IDL forms the basis of development for both the client and the server. The toolkit takes the IDL file as input and, based on the

declarations in the IDL file, generates a complete, working Orbix application. You can then modify the generated code to add business logic to the application.

WARNING: Orbix Mainframe does not support the code generation toolkit and distributed genies. You must develop Orbix applications in a mainframe environment without the code generation toolkit. (see [page 46](#)).

Client development

Client development consists of the following steps:

1. An IDL compiler takes the IDL file as input and generates client stub code.
2. The code generation toolkit takes the IDL file as input and generates a complete client application.

The generated client is a dummy implementation that invokes every operation on each interface in the IDL file exactly once. The dummy client is a working application that can be built and run right away.

3. You can modify the dummy client to complete the application.
You do not have to write boilerplate CORBA code.
 4. You build the application.
A makefile is generated by the code generation toolkit.
-

Server development

Server development consists of the following steps:

1. An IDL compiler takes the IDL file as input and generates server skeleton code.
2. The code generation toolkit takes the IDL file as input and generates a complete server application.


Dummy implementation classes are generated for each interface appearing in the IDL file. The dummy server is a working application that can be built and run right away.

3. You can modify the dummy server to complete the application logic.
You do not have to write boilerplate CORBA code.
The implementations of IDL interfaces can be modified by adding business logic to the class definitions.

4. You build the application.
A makefile is generated by the code generation toolkit.

Development Without Using Code Generation

The following section outlines the steps for developing clients and servers without using the code generation toolkit (see page 43):.



First, you define a set of interfaces written in the OMG interface definition language (IDL). The IDL file forms the basis of development for both the client and the server.

Client development

Client development consists of the following steps:

1. An IDL compiler takes the IDL file as input and generates client stub code.
The *client stub code* is a set of files that enable clients to make remote invocations on the interfaces defined in the IDL file.
2. You write the rest of the client application from scratch.

3. You build the application.
Typically, you write a customized makefile to build the client program.
-

Server development

Server development consists of the following steps:

1. An IDL compiler takes the IDL file as input and generates server skeleton code.
The *server skeleton code* is a set of files that enables the server to service requests on the interfaces in the IDL file.
2. You write the rest of the server application from scratch.
You must write an implementation class for each interface appearing in the IDL file.
3. You build the application.
You typically write a customized makefile to build the server program.

Locating CORBA Objects

Before developing an Orbix application, you must choose a strategy for locating CORBA objects.

To find a CORBA object, a client needs to know both the identity of the object and the location of the server process that provides a home for that object. In general, CORBA encapsulates both the identity and location of a CORBA object inside an entity known as an *object reference*.

In this chapter, a simple strategy is adopted to pass the object reference from the server to the client. The strategy, illustrated in [Figure 6](#), has three steps:

-
- 1 The server converts the object reference into a string (*stringified object reference*) and writes this stringified object reference to a file.
-
- 2 The client reads the stringified object reference from the file and converts it to a real object reference.

- 3 The client can now make remote invocations by invoking on the object reference.




Figure 6: *Simple strategy for passing object references to clients*

This approach is convenient for simple demonstrations but is not recommended for use in realistic applications. The CORBA naming service, described in [Chapter 18 on page 485](#), provides a more sophisticated and scalable approach to distributing object references.

Development Steps

You typically develop an Orbix application in the following steps:

1. **Define IDL interfaces:** Identify the objects required by the application and define their public interfaces in IDL.
2. **Generate starting point code:** Use the code generation toolkit to generate starting point code for the application. You can then edit the generated files to add business logic.
3. **Compile the IDL definitions:** The compiler generates the C++ header and source files that you need to implement client and server programs.
4. **Develop the server program:** The server acts as a container for a variety of CORBA objects, each of which supports one IDL interface. You must add code to provide the business logic for each type of CORBA object. The server makes its CORBA objects available to clients by exporting *object references* to a well-known location.
5. **Develop the client program:** The client uses the IDL compiler-generated mappings to invoke operations on the object references that it obtains from the server.
6. **Build the application.**
7. **Run the application.**

Step 1: Define IDL interfaces

Begin developing an Orbix enterprise application by defining the IDL interfaces to the application's objects. These interfaces implement CORBA distributed objects on a server application. They also define how clients access objects regardless of the object's location on the network.

An interface definition contains *operations* and *attributes*:

- Operations correspond to methods that clients can call on an object.
- Attributes give you access to a single data value.

Each attribute corresponds either to a single accessor method (readonly attribute) or an accessor method and a modifier method (plain attribute).

For example, the following IDL code defines an interface for an object that represents a building. This building object could be the beginning of a facilities management application such as a warehouse allocation system:

```
//IDL
//File: building.idl
interface Building {
1   readonly attribute string address;
2   boolean available(in long date);
   boolean reserveDate(in long date, out long confirmation);
};
```

The IDL contains these components:

1. The `address` attribute is preceded by the IDL keyword `readonly`, so clients can read but can not set its value.
2. The `Building` interface contains two operations: `available()` and `reserveDate()`. Operation parameters can be labeled `in`, `out`, or `inout`
 - ◆ `in` parameters are passed from the client to the object.
 - ◆ `out` parameters are passed from the object to the client.
 - ◆ `inout` parameters are passed in both directions.

`available()` lets a client test whether the building is available on a given date. This operation returns a boolean (true/false) value.

`reserveDate()` takes the date as input, returns a confirmation number as an `out` parameter, and has a boolean (`true/false`) return value.

All attributes and operations in an IDL interface are implicitly public. IDL interfaces have no concept of private or protected members.

Step 2: Generate starting point code

It's recommended that you start developing a CORBA application by using the code generation toolkit to generate starting point code. The toolkit contains two key components:

The `ilgen` interpreter is an executable file that processes IDL files based on the instructions contained in predefined code generation scripts.

A set of *genies* (code generation scripts) are supplied with the toolkit. Most important of these is the `cpp_poa_genie.tcl` genie that is used to generate starting point code for a C++ application.

Taking the `building.idl` IDL file as input, the `cpp_poa_genie.tcl` genie can produce complete source code for a distributed application that includes a client and a server program.

To generate starting point code, execute the following command:

```
ilgen cpp_poa_genie.tcl -all building.idl
```

This command generates all of the files you need for this application. The `-all` flag selects a default set of genie options that are appropriate for simple demonstration applications.

The main client file generated by the `cpp_poa_genie.tcl` genie is:

```
client.cpp
```

Implementation of the client.

The main server files generated by the `cpp_poa_genie.tcl` genie are:

```
server.cpp
```

Server `main()` containing the server initialization code.

```
BuildingImpl.h
```

Header file that declares the `BuildingImpl` servant class.

```
BuildingImpl.cpp
```

Implementation of the `BuildingImpl` servant class.

```
it_servant_base_overrides.h
```

Header file that declares a base class for all servant classes. [See page 308.](#)

```
it_servant_base_overrides.cpp
```

Implementation of the base class for all servant classes. [See page 308.](#)

```
x
```

A makefile is generated for building the application:

`Makefile`

The generated makefile defines rules to build both the client and the server.

The following files are also generated and support a dummy implementation of the client and server programs:

```
call_funcs.h
call_funcs.cpp
it_print_funcs.h
it_print_funcs.cpp
it_random_funcs.h
it_random_funcs.cpp
```

`build.xml`, which is an XML file that contains the rules for building the Hello World! application.

Dummy implementation of client and server programs

The generated starting point code provides a complete dummy implementation of the client and the server programs. The dummy implementation provides:

- A server program that implements every IDL interface. Every IDL operation is implemented with default code that prints the `in` and `inout` parameters to the screen when it is invoked. Return values, `inout` and `out` parameters are populated with randomly generated values. At random intervals a CORBA user exception might be thrown instead.
- A client program that calls every operation on every IDL interface once.

The dummy client and server programs can be built and run as they are.

Modifying dummy client and server programs

Later steps describe in detail how to modify the generated code to implement the business logic of the `Building` application.

In the code listings that follow, modifications are indicated as follows:

- Additions to the generated code are highlighted in bold font. You can manually add this code to the generated files using a text editor.
- In some cases the highlighted additions replace existing generated code, requiring you to manually delete the old code.

Step 3: Compile the IDL definitions

This step is optional if you use the code generation toolkit to develop an application. The `Makefile` generated by the toolkit has a rule to run the IDL compiler automatically.

After defining your IDL, compile it using the CORBA IDL compiler. The IDL compiler checks the validity of the specification and generates code in C++ that you use to write the client and server programs.

Compile the `Building` interface by running the IDL compiler as follows:

```
idl -base -poa building.idl
```

The `-base` option generates client stub and header code in C++. The `-poa` option generates server-side code for the portable object adapter (POA).

Run the IDL compiler with the `-flags` option to get a complete description of the supported options.

Output from IDL compilation

The IDL compiler produces several C++ files when it compiles the `building.idl` file. These files contain C++ definitions that correspond to your IDL definitions. You should never modify this code.

The generated files can be divided into two categories:

- **Client stub code** is compiled and linked with client programs, so they can make remote invocations on `Building` CORBA objects.
- **Server skeleton code** is compiled and linked with server programs, so they can service invocations on `Building` CORBA objects.

Client stub code

The stub code is used by clients and consists of the following files:

<code>building.hh</code>	A header file containing definitions that correspond to the various IDL type definitions. Client source code must include this file using a <code>#include</code> preprocessor directive.
<code>buildingC.cpp</code>	A file containing code that enables remote access to <code>Building</code> objects. This file must be compiled and linked with the client executable.

Any clients that want to invoke on CORBA objects that support the `Building` interface must include the header file `building.hh` and link with the stub code `buildingC.cpp`.

Server skeleton code

The skeleton code is used by servers and consists of the following files:

<code>buildingS.hh</code>	A header file containing type definitions for implementing servant classes. Server source code must include this file using a <code>#include</code> preprocessor directive.
<code>buildingS.cpp</code>	A file containing skeleton code that enables servers to accept calls to <code>Building</code> objects. This file must be compiled and linked with the server executable.
<code>building.hh</code>	A header file common to client stub code and server skeleton code. This file is included by <code>buildingS.hh</code> , so server files do not need to explicitly include it.
<code>buildingC.cpp</code>	Source file common to client stub code and server skeleton code. This file must be compiled and linked with the server executable.

The skeleton code is a superset of the stub code. The additional files contain code that allows you to implement servants for the `Building` interface.

Server files include the `buildingS.hh` header file, which recursively includes the file `building.hh`. The server must be linked with both `buildingC.cpp` and `buildingS.cpp`.

IDL to C++ mapping

The IDL compiler translates IDL into stub and skeleton code for a given language—in this case, C++. As long as the client and server programs comply with the definitions in the generated header files, `building.hh` and `buildingS.hh`, the runtime ORB enables type-safe interaction between the client and the server.

Both the client and the server source files include the generated header file `buildinghh`, which contains the C++ mappings for the `Building` interface (see “Define IDL interfaces” on page 51):

```

1 class Building : public virtual CORBA::Object
  {
  public:
  ...
2  virtual char* address() = 0;
  ...
3  virtual CORBA::Boolean available(CORBA::Long date) = 0;
4  virtual CORBA::Boolean reserveDate(
    CORBA::Long date,
    CORBA::Long_out confirmation
  ) = 0;
  ...
  };

```

The code can be explained as follows:

1. The `Building` class defines proxy objects for the `Building` interface. This class includes member methods that correspond to the attributes and operations of the IDL interface. When a client program calls methods on an object of type `Building`, Orbix forwards the method calls to a server object that supports the `Building` interface.
2. The C++ pure virtual member method `address()` maps to the readonly IDL string attribute `address`. Clients call this method to get the attribute’s current value, which returns the C++ type `char*`.
3. The pure virtual C++ member method `available()` maps to the IDL operation of the same name. It returns type `CORBA::Boolean`, which maps to the equivalent IDL type `boolean`. Its single parameter is of `CORBA::Long` type, which is a `typedef` of a basic C++ integer type. This maps to the operation parameter of IDL type `long`.
4. The operation `reserveDate()` has one input parameter, `date`, and one output parameter, `confirmation`, both of IDL type `long`. The return type is `CORBA::Boolean`. Input parameters (specified as IDL `in` parameters) are passed by value in C++. Output parameters are passed by reference. Every CORBA data type has a corresponding `_out` type that is used to declare output parameters. For basic types, such as `short` and `long`, the `_out` type is

a `typedef` of a reference to the corresponding C++ type. For example, the `CORBA::Long_out` type is defined in the CORBA namespace as:

```
typedefCORBA::Long& CORBA::Long_out;
```

Other helper data types and methods generated in this file are described when they are used in this chapter.

Step 4: Develop the server program

The main programming task on the server side is the implementation of servant classes. In this demonstration there is one interface, `Building`, and one corresponding servant class, `BuildingImpl`.

For each servant class, perform these tasks:

- **Declare the servant class:** The code generation toolkit generates an outline servant header file for every interface. The `BuildingImpl` servant class is declared in the header file `BuildingImpl.h`.
- **Define the servant class:** The code generation toolkit generates a dummy definition of every servant class. The `BuildingImplservant` class is defined in the file `BuildingImpl.cpp`.

The other programming task on the server side is the implementation of the server `main()`. For this simple demonstration, the generated server `main()` does not require any modification. It is discussed in detail in [“Enhancing Server Functionality” on page 74](#).

Declare the servant class

The code generation toolkit generates a header file, `BuildingImpl.h`, that declares the `BuildingImplservant` class. You can use this starting point code to implement the `Building` interface.

Note: The name of the `BuildingImplservant` class is not significant but simply conforms to a naming convention that helps distinguish servant code from other application code.

You can modify the generated code in `BuildingImpl.h` to add member variables needed for the implementation. The code shown here provides a simple implementation of `BuildingImpl`.

Manual additions to the generated code are shown in bold font.

```

1 //File: BuildingImpl.h
  ...
  #include "buildingS.hh"
  #include "t_servant_base_override.h"

```

```

2 class BuildingIn pl:
    public virtual IT_ServantBaseOverrides,
    public virtual POA_Building
    {
    public:
        BuildingIn pl(PortableServer:POA_ptr);
        virtual ~ BuildingIn pl();

        // _create() — create a new servant.
        static POA_Building* _create(PortableServer:POA_ptr);

        // DL operations
        //
3 virtual CORBA::Boolean available(
        CORBA::Long          date
    ) IT_THROW _DECL((CORBA::System Exception));

    virtual CORBA::Boolean reserveDate(
        CORBA::Long          date,
        CORBA::Long_out      confirmation
    ) IT_THROW _DECL((CORBA::System Exception));

        // DL attributes
        //
4 virtual char* address()
        IT_THROW _DECL((CORBA::System Exception));

    private:
5        //-----
        // Private Member Variables
        //-----
        CORBA::Long          m_confirmation_counter;
        CORBA::Long          m_reservation[ 366 ];

        // Instance variables for attributes.
6        CORBA::String_var    m_address;
        ...
    };

```

This code can be described as follows:

1. Servers include the `buildings.hh` skeleton file, which declares the C++ `POA_Building` class. The `POA_Building` class is a class generated by the IDL compiler that allows you to implement the `Building` interface using the inheritance

approach. In general, for any interface, *InterfaceName*, a corresponding class, *POA_InterfaceName*, is generated by the IDL compiler.

2. The `BuildingImplServant` class inherits from `POA_Building` and `II_ServantBaseOverrides`.

The `POA_Building` class is a standard name for the base class generated for the `Building` interface. By inheriting from `POA_Building`, you are indicating to the ORB that `BuildingImpl` is the servant class that implements `Building`. This approach to associating a servant class with an interface is called the *inheritance approach*.

The `II_ServantBaseOverrides` class is used to override the definition of some standard virtual methods. For a discussion of this class, see [page 308](#).

3. A member method declaration is generated for each of the operations in the `Building` interface.

Orbix uses the `II_THROW_DECL(exception-list)` macro to insulate generated code from variations between C++ compilers. The macro maps to `throw(exception-list)` for compilers that support exceptions, or to an empty string, "", for compilers that do not.

4. Member method declarations are generated for each of the attributes in the `Building` interface.

Read-only attributes require a single method that returns the current value of the attribute. Read/write attributes require two methods: one that returns the current value, and another that takes an input parameter to set the value.

5. The lines of code shown in bold font are added to the generated code to complete the application. Two additional private member variables are declared to store the state of a `BuildingImplObject`.
 - ◆ The `m_confirmation_counter` index counter is incremented each time a reservation is confirmed.
 - ◆ The `m_reservation` array has 366 elements (representing the 365 or 366 days in a year). The elements are equal to zero when unreserved or a positive integer (the confirmation number) when reserved.

6. The `m_address` is a CORBA string that stores the address of the building.

The declared type of `m_address`, `CORBA::String_var`, is a smart pointer type that functions as a memory management aid. String pointers declared as `CORBA::String_var` are used in a similar way to plain `char*` pointers, except that it is never necessary to delete the string explicitly.

Note: The code generation toolkit automatically generates a private member `m_address` to represent the state of the IDL `address` attribute. However, this generated class member is *not* part of the standard IDL-to-C++ mapping. It is generated solely for your convenience and you are free to remove this line from the generated code if you so choose.

Define the servant class

The code generation toolkit also generates the `BuildingImpl.cxx` file, which contains an outline of the method definitions for the `BuildingImpl` servant class. You should edit this file to fill in the bodies of methods that correspond to the operations and attributes of the `Building` interface. It is usually necessary to edit the constructor and destructor of the servant class as well.

Manual additions made to the generated code are shown in bold font. In some cases, the additions replace existing generated code requiring you to manually delete the old code.

```
//File: BuildingImpl.cxx
...
# include "BuildingImpl.h"
//_create() — create a new servant.
POA_Building*
```

```

1 BuildingImpl::create(PortableServer::POA_ptr the_poa)
{
    return new BuildingImpl(the_poa);
}

//BuildingImpl constructor
//
//Note: since we use virtual inheritance, we must include an
//initialiser for all the virtual base class constructors that
//require arguments, even those that we inherit indirectly.
//
BuildingImpl::BuildingImpl(
    PortableServer::POA_ptr the_poa
):
    IT_ServantBaseOverrides(the_poa),
2     m_address( "200 West Street, Waltham, MA." ),
    m_confirmation_counter(1)
{
    for (int i=0; i<366; i++) { m_reservation[i] = 0; }
}

//~ BuildingImpl destructor.
//
3 BuildingImpl::~BuildingImpl()
{
    //Intentionally empty.
}

//available() - Implements DL
//      operation 'Building::available()'.
//
CORBA::Boolean
BuildingImpl::available(
    CORBA::Long date
) IT_THROW_DECL((CORBA::SystemException))
{

```

```

4   if (1<=date && date<=366) {
        return (m_reservation[date-1]==0);
    }

    return 0;
}

//reserveDate() — Implements DL
// operation 'Building:reserveDate()'.
//
CORBA::Boolean
BuildingImpl::reserveDate(
    CORBA::Long date,
    CORBA::Long out_confirmation
) IT_THROW _DECL((CORBA::SystemException))
{
5   confirmation = 0;

    if (1<=date && date<=366) {
        if (m_reservation[date-1]==0) {
            m_reservation[date-1]=m_confirmation_counter;
            confirmation = m_confirmation_counter;
            m_confirmation_counter++;
            return 1;
        }
    }
    return 0;
}

//address() — Accessor for DL attribute 'Building:address'.
//
char*
BuildingImpl::address() IT_THROW _DECL((CORBA::SystemException))
{
6   return CORBA::string_dup(m_address);
}

```

The code can be explained as follows:

1. `_create()` is a static member method of `BuildingImpl` that creates `BuildingImpl` instances.

Note that `_create()` is not a standard part of CORBA. It is generated by the code generation toolkit for convenience. You are free to call the constructor directly, or remove the `_create()` method entirely.

2. The `BuildingImpl` constructor is an appropriate place to initialize any member variables. The three private member variables—`m_address`, `m_confirmation_counter` and `m_reservation`—are initialized here.
3. The `BuildingImpl` destructor is an appropriate place to free any member variables that were allocated on the heap. In this example it is empty.
4. A few lines of code are added here to implement the `available()` operation. If an element of the array `m_reservation` is zero, that means the date is available. Otherwise the array element holds the confirmation number (a positive integer).
5. A few lines of code are added here to implement the `reserveDate()` operation. Because `confirmation` is declared as an `out` parameter in IDL, it is passed by reference in C++. The value assigned to it is therefore readable by the code that called `reserveDate()`.
6. `CORBA::string_dup()` is used to allocate a copy of the string `m_address` on the free store.

It would be an error to return the private string pointer directly from the operation because the ORB automatically deletes the return value after the operation has completed.

It would also be an error to allocate the string copy using the C++ `new` operator.

Step 5: Develop the client program

The generated code in the `client.cpp` file takes care of initializing the ORB and getting a `Building` object reference. This allows the client programmer to focus on the business logic of the client application.

You modify the generated client code by implementing the logic of the client program. Use the `Building` object reference to access an object's attributes and invoke its operations.

Client main()

The code in the client `main()` initializes the ORB, reads a `Building` object reference from the file `Building.ref` and hands over control to `run_warehouse_menu()`, which is described in the next section. When `run_warehouse_menu()` returns, the generated code shuts down the ORB. Changes or additions to the code are shown in bold font.

```
1 /File: client.cpp
...
#include "building.h"
...
//global_orb --make ORB global so all code can find it.
//
CORBA::ORB_var
global_orb = CORBA::ORB::_nil();

//read_reference() --read an object reference from file.
//
static CORBA::Object_ptr
```

```

2 read_reference(
    const char* file
)
{
    cout << "Reading stringified object reference from "
         << file << endl;
    ifstream ifs(file);
    CORBA::String_var str;
    ifs >> str;
    if (!ifs) {
        cerr << "Error reading object reference from "
             << file << endl;
        return CORBA::Object::_nil();
    }
    return global_orb->string_to_object(str);
}
...

//main() - the main client program.
int
main(int argc, char**argv)
{
    int exit_status = 0;
    try
    {
        //For temporary object references.
        CORBA::Object_var tmp_ref;

        //Initialise the ORB.
        //
3        global_orb = CORBA::ORB_init(argc, argv);

        //Exercise the Building interface.
        //
4        tmp_ref = read_reference("Building.ref");
5        Building_var Building1 = Building::_narrow(tmp_ref);
        if (CORBA::is_nil(Building1))
        {
            cerr << "Could not narrow reference to interface "
                 << "Building" << endl;
        }
        else
        {

```

```

6      run_warehouse_menu(Building1);
    }
}
catch(CORBA::Exception &ex)
{
    cerr<< "Unexpected CORBA exception:"<< ex<< endl;
    exit_status = 1;
}

//Ensure that the ORB is properly shutdown and cleaned up.
//
try
{
7      global_orb-> shutdown(1);
      global_orb-> destroy();
    }
    catch (...)
    {
        //Do nothing.
    }
    return exit_status;
}

```

The code can be explained as follows:

1. Declare the variable `global_orb` in the global scope so that all parts of the program can easily access the ORB object.
The `global_orb` is temporarily set equal to the value `CORBA::ORB::nil()`, which represents a blank object reference of type `CORBA::ORB_ptr`.
2. Define `read_reference()` to read an object reference from a file. This method reads a stringified object reference from a file and converts the stringified object reference to an object reference using `CORBA::ORB::string_to_object()`. The return type of `read_reference()` is `CORBA::Object_ptr`—the base type for object references.
If there is an error, `read_reference()` returns `CORBA::Object::nil()`, which represents a blank object reference of type `CORBA::Object_ptr`.
3. Call `CORBA::ORB::init()` to get an object reference to the initialized ORB.

A client must associate itself with the ORB in order to get object references to CORBA services such as the naming service or trader service.

4. Get a reference to a CORBA object by calling `read_reference()`, passing the name of a file that contains its stringified object reference. The `tmp_ref` variable is of `CORBA::Object_var` type. This is a smart pointer type that automatically manages the memory it references.

5. Narrow the CORBA object to a `Building` object, to yield the `BuildingI` object reference.

The mapping for every interface defines a static member method `_narrow()` that lets you narrow an object reference from a base type to a derived type. It is similar to a C++ dynamic cast operation, but is used specifically for types related via IDL inheritance.

6. Replace the lines of generated code in the `else` clause with a single call to `run_warehouse_menu()`.

`run_warehouse_menu()` uses the `BuildingI` object reference to make remote invocations on the server.

7. The ORB must be explicitly shut down before the client exits.

`CORBA::ORB::shutdown()` stops all server processing, deactivates all POA managers, destroys all POAs, and causes the `run()` loop to terminate. The boolean argument, `1`, indicates that `shutdown()` blocks until shutdown is complete.

`CORBA::ORB::destroy()` destroys the ORB object and reclaims all resources associated with it.

When an object reference enters a client's address space, Orbix creates a *proxy object* that acts as a stand-in for the remote servant object. Orbix forwards method calls on the proxy object to corresponding servant object methods.

Client business logic

You access an object's attributes and operations by calling the appropriate the `Building` class method using the proxy object. The proxy object redirects the C++ calls across the network to the appropriate servant method.

The following code uses the C++ arrow operator (`->`) on the `Building_ptr` object `warehouse` to access `Building` class methods.

Additions to the code are shown in bold font.

```

/File: client.cpp
void
run_warehouse_menu(Building_ptr warehouseP)
{
    CORBA::String_var addressV = warehouseP->address();
    cout << "The warehouse address is:" << endl
         << addressV.in() << endl;

    CORBA::Long date;
    CORBA::Long confirmation;
    char quit = 'n';
    do {
        cout << "Enter day to reserve warehouse (1,2,...):
";
        cin >> date;
        if(warehouseP->available(date)) {
            if (warehouseP->reserveDate(date, confirmation)
)
                cout << "Confirmation number: "
                    << confirmation << endl;
            else
                cout << "Reservation attempt failed!" <<
endl;
        }
        else {
            cout << "That date is unavailable." << endl;
        }
        cout << "Quit? (y,n)";
        cin >> quit;
    }
    while (quit == 'n');
}

```

Step 6: Build the application

The makefile generated by the code generation toolkit has a complete set of rules for building both the client and server applications.

To build the client and server, go to the example directory and at a command line prompt enter:

Windows

```
> nm ake
```

UNIX

```
% make -e
```

Note: These instructions do not apply to applications that are built in a native OS/390 environment. For more information, see the readme files and JCL that are supplied in the DEMO data sets of your product installation.

Step 7: Run the application

Prerequisites

The prerequisites for running this application are:

- Orbix's deployment environment is installed on the machine where the demonstration is run.
- Orbix has been correctly configured. See the *Orbix Administrator's Guide* for details.

This demonstration assumes that both the client and the server run in the same directory.

Steps

Perform the following steps to run the application:

- 1 Run the Orbix services (if required).

If you have configured Orbix to use file-based configuration, no services need to run for this demonstration. Proceed to step 2.

If you have configured Orbix to use configuration repository based configuration, start up the basic Orbix services.

Open a new DOS prompt in Windows, or `xterm` in UNIX. Enter:

```
start_domain-name_services
```

where *domain-name* is the name of the default configuration domain.

- 2 Run the server program.

Open a new DOS prompt in Windows, or `xterm` in UNIX. The executable file is called `server.exe` (Windows) or `server` (UNIX). The server outputs the following lines to the screen:

```
Initializing the ORB
Writing stringified object reference to Building.ref
Waiting for requests...
```

At this point the server is blocked while executing `CORBA::ORB::run()`.

- 3 Run the client program.

-
- 4 Open a new DOS prompt in Windows, or `xterm` in UNIX. The executable file is called `client.exe` (Windows) or `client` (UNIX).
- When you are finished, terminate all processes. The server can be shut down by typing Ctrl-C in the window where it is running.
-

- 5 Stop the Orbix services (if they are running). From a DOS prompt in Windows, or `xterm` in UNIX, enter:
- ```
stop_domain-name_services
```
- where *domain-name* is the name of the default configuration domain.

---

## Enhancing Server Functionality

In this demonstration, the default implementation of `main()` suffices so there is no need to edit the `server.cpp` file.

However, for realistic applications, you need to customize the server `main()` to specify what kind of POAs are created. You also need to select which CORBA objects get activated as the server boots up.

The default server `main()` contains code to perform these tasks:

1. Create a termination handler object.
2. Initialize the ORB.
3. .
4. .
5. . The default server code activates one CORBA object for each of the interfaces defined in the IDL file.
6. . An object reference is exported for each of the activated CORBA objects.
7. so it can process requests on the CORBA objects it manages.
8. cleanly before exiting. and any heap-allocated memory should be deleted

In this demonstration, there is only one interface, `Building`, and a single CORBA object of this type is activated.

The following subsections discuss the code in the `server.cpp` file piece by piece. For a complete source listing of `server.cpp`, [see page 87](#).

## Create a Termination Handler Object

Orbis provides its own `IT_TerminationHandler` class, which handles server shutdown in a portable manner.

On UNIX, the termination handler handles the following signals:

```
SIGINT
SIGTERM
SIGQUIT
```

On Windows, the termination handler is just a wrapper around `SetConsoleCtrlHandler`, which handles delivery of the following control events:

```
CTRL_C_EVENT
CTRL_BREAK_EVENT
CTRL_SHUTDOWN_EVENT
CTRL_LOGOFF_EVENT
CTRL_CLOSE_EVENT
```

The main routine can create a termination handler object on the stack. On POSIX platforms, it is critical to create this object in the main thread before creation of any other thread, especially before calling `ORBinit()`, as follows:

```
int
main(int argc, char** argv)
{
 IT_TerminationHandler
 termination_handler(termination_handler_callback);
 // ...
}
```

You can create only one termination handler object in a program. The server shutdown mechanism and `termination_handler_callback()` are discussed in detail in [“Shut down the ORB” on page 85](#).

## Step 1: Initialize the ORB

Before a server can make its objects available to the rest of an enterprise application, it must initialize the ORB:

```

...
//global_orb --make ORB global so all code can find it.
CORBA::ORB_var
1 global_orb = CORBA::ORB::_nil();
...

int
main(int argc, char**argv)
{
...
2 cout << "Initializing the ORB" << endl;
 global_orb = CORBA::ORB_init(argc, argv);
...

```

The code can be explained as follows:

1. The type `CORBA::ORB_var` is a smart pointer class that can be used to refer to objects of type `CORBA::ORB`. Syntactically, a `CORBA::ORB_var` is similar to the pointer type `CORBA::ORB*`. The advantage of using a smart pointer is that it automatically deletes the memory pointed at as soon as it goes out of scope. This helps to prevent memory leaks. The value `CORBA::ORB::_nil()` is an example of a *nil object reference*. A nil object reference is a blank value that can legally be passed as a CORBA parameter or return value.
2. `CORBA::ORB_init()` is used to create an instance of an ORB. Command-line arguments can be passed to the ORB via `argc` and `argv`. `ORB_init()` searches `argv` for arguments of the general form `-ORBsuffix`, parses these arguments, and removes them from the argument list.

## Step 2: Create a POA for transient objects

A simple POA object is created using the following lines of code:

```

try {
 //For transient object references.
 CORBA::Object_var tm_p_ref;
 ...

1 tm_p_ref = glibal_orb-> resolve_initial_references("RootPOA");
2 PortableServer::POA_var root_poa =
 PortableServer::POA::narrow (tm_p_ref);
 assert(CORBA::is_nil(root_poa));

3 PortableServer::POAManager_var root_poa_manager
 = root_poa-> the_POAManager();
 assert(CORBA::is_nil(root_poa_manager));

4 //Now create our own POA.
 PortableServer::POA_var my_poa =
 create_simple_poa("my_poa", root_poa, root_poa_manager);
 ...
}
...

```

The code can be explained as follows:

1. Get a reference to the root POA object by calling `resolve_initial_references("RootPOA")` on the ORB. `resolve_initial_references()` provides a bootstrap mechanism for obtaining access to key Orbix objects. It contains a mapping of well-known names to important objects such as the root POA (`RootPOA`), the naming service (`NameService`), and other objects and services.
2. Narrow the root POA reference, `tm_p_ref`, to the type `PortableServer::POA_ptr` using `PortableServer::POA::narrow()`. Because `tm_p_ref` is of `CORBA::Object` type, which is the generic base class for object references, methods specific to the `PortableServer::POA` class are not directly accessible. It is therefore necessary to down-cast the `tm_p_ref` pointer to the actual type of the object reference using `_narrow()`.

3. Obtain a reference to the root POA manager object.  
A POA manager controls the flow of messages to a set of POAs. CORBA invocations cannot be processed unless the POA manager is in an active state (see page 84).
4. Create the `m_y_poa` POA as a child of `root_poa`. The `m_y_poa` POA becomes associated with the `root_poa_manager` POA manager. This means that the `root_poa_manager` object controls the flow of messages into `m_y_poa`.

`create_simple_poa()` is defined as follows:

```
PortableServer::POA_ptr
create_simple_poa(
 const char* poa_name,
 PortableServer::POA_ptr parent_poa,
 PortableServer::POAManager_ptr poa_manager
)
{
 // Create a policy list.
 // Policies not set in the list get default values.
 //
 CORBA::PolicyList policies;
 policies.length(1);
 int i = 0;
 // Make the POA single threaded.
 //
 policies[i++] = parent_poa->create_thread_policy(
 PortableServer::SINGLE_THREAD_MODEL
);
 assert(i == 1);

 return parent_poa->create_POA(
 poa_name,
 poa_manager,
 policies);
}
```

A POA is created by invoking `PortableServer::POA::create_POA()` on an existing POA object. The POA on which this method is invoked is known as the *parent POA* and the newly created POA is known as the *child POA*.

`create_POA()` takes the following arguments:

- `poa_name` is the adapter name. This name is used within the ORB to identify the POA instance relative to its parent.

- `poa_manager` is a reference to a POA manager object with which the newly created POA becomes associated.
- `policies` is a list of policies that configure the new POA. For more information, see [“Using POA Policies” on page 294](#).

The POA instance returned by `create_simple_poa()` accepts default values for most of its policies. The resulting POA is suitable for activating *transient CORBA objects*. A transient CORBA object is an object that exists only as long as the server process that created it. When the server is restarted, old transient objects are no longer accessible.

---

## Step 3: Create servant objects

A number of servant objects must be created. A servant is an object that does the work for a CORBA object. For example, the `BuildingImplServant` class contains the code that implements the `Building` IDL interface.

A single `BuildingImplServant` object is created as follows:

```
#include <BuildingImpl.h>
...
//Note: PortableServer::Servant is a pointer type - its
//actually a typedef for PortableServer::ServantBase*.
//
PortableServer::Servant the_Building = 0;
...
the_Building = BuildingImpl::create(m_y_poa);
```

In this example, `_create()` creates an instance of a `BuildingImplServant`. The POA reference `m_y_poa` that is passed to `_create()` must be the same POA that is used to activate the object in the next section [“Activate CORBA objects”](#).

`_create()` is not a standard CORBA method. It is a convenient pattern implemented by the code generation toolkit. You can use the `BuildingImpl` constructor instead, if you prefer.

## Step 4: Activate CORBA objects

A CORBA object must be activated before it can accept client invocations. Activation is the step that establishes the link between an ORB, which receives invocations from clients, and a servant object, which processes these invocations.

In this step, two fundamental entities are created that are closely associated with a CORBA object:

- An object ID.  
This is a CORBA object identifier that is unique with respect to a particular POA instance. In the case of a persistent CORBA object, the object ID is often a database key that is used to retrieve the state of the CORBA object from the database.
- An object reference.  
This is a handle on a CORBA object that exposes a set of methods mapped from the operations of its corresponding IDL interface. It can be stringified and exported to client programs. Once a client gets hold of an object reference, the client can use it to make remote invocations on the CORBA object.

A single `Building` object is activated using the following code:

```
include < BuildingImpl.h>
...
CORBA::Object_var tmp_ref;
...
PortableServer::ObjectId_var oid;
...
1 oid = m_y_poa->activate_object(the_Building);
2 tmp_ref = m_y_poa->id_to_reference(oid);
```

The code can be explained as follows:

1. Activate the CORBA object.  
A number of things happen when `activate_object()` is called:
  - ◆ An unique object ID, `oid`, is automatically generated by `m_y_poa` to represent the CORBA object's identity. Automatically generated object IDs are convenient for use with transient objects.
  - ◆ The CORBA object becomes associated with the POA, `m_y_poa`.

- ◆ The POA records the fact that the `the_Building` servant provides the implementation for the CORBA object identified by `oid`.
2. Use `PortableServer::POA::id_to_reference()` to generate an object reference, `mp_ref`, from the given object ID.

You can activate a CORBA object in various ways, depending on the policies used to create the POA. For information about activating objects in the POA, see [“Activating CORBA Objects” on page 257](#); for information about activating objects on demand, see [Chapter 11 on page 325](#).

## Step 5: Export object references

A server must advertise its objects so that clients can find them. In this demonstration, the `Building` object reference is exported to clients using

```
write_reference();
```

```
write_reference(tm_p_ref, Building_ref);
```

This call writes the `tm_p_ref` object reference to the `Building_ref` file.

`write_reference()` writes an object reference to a file in stringified form. It is defined as follows:

```
void
write_reference(
 CORBA::Object_ptrref, const char* objef_file
)
{
 CORBA::String_varstringified_ref=
 global_obj->object_to_string(ref);
 cout << " Writing stringified object reference to "
 << objef_file << endl;

 ofstream os(objef_file);
 os << stringified_ref;
 if (!os.good())
 {
 cerr << "Failed to write to " << objef_file << endl;
 }
}
```

The `ref` object reference is converted to a string, of type `char*` by passing `ref` as an argument to `CORBA::ORB::object_to_string()`. The string is then written to the `objef_file` file.

Note that a smart pointer of `CORBA::String_var` type is used to reference the stringified object reference. The smart pointer automatically deletes the string when it goes out of scope, thereby avoiding a memory leak.

CORBA clients can read the `objef_file` file to obtain the object reference.

This approach to exporting object references is convenient to use for this simple demonstration. Realistic applications, however, are more likely to use the CORBA naming service instead.

---

## Step 6: Activate the POA manager

After a server has set up the objects and associations it requires during initialization, it must tell the ORB to start listening for requests:

```
1 //Activate the POA Manager and let the ORB process requests.
//
root_poa_manager-> activate();
2 global_orb-> run();
```

The code can be explained as follows:

1. A POA manager acts as a gatekeeper for incoming object requests. The manager can be in four different states: *active*, *holding*, *discarding*, or *inactive* (see [Table 13 on page 311](#)). A POA manager can accept object requests only after it is activated by calling `PortableServer::POA manager::activate()`.
2. `CORBA::ORB::run()` puts the ORB into a state where it listens for client connection attempts and accepts request messages from existing client connections.

`CORBA::ORB::run()` is a blocking method that returns only when `CORBA::ORB::shutdown()` is invoked.

## Step 7: Shut down the ORB

The shutdown mechanism for the demonstration application uses Orbix's own `IT_TerminationHandler` class, which enables server applications to handle delivery of `CTRL-C` and similar events in a portable manner (see [page 75](#) and [“Termination Handler” on page 280](#)).

Before shutdown is initiated, the server is blocked in the execution of `CORBA::ORB::run()`.

Shutdown is initiated when a `Ctrl-C` or similar event is sent to the server from any source. You can shut down the server application as follows:

- On Windows platforms, switch focus to the MS-DOS box where the server is running and type `Ctrl-C`.
- On UNIX platforms, switch focus to the `xterm` window where the server is running and type `Ctrl-C`.
- On UNIX, send a signal to a background server process using the `kill` system command.

The Orbix termination handler can handle a number of signals or events (see [“Create a Termination Handler Object” on page 75](#)). As soon as the server receives one of these signals or events, a thread started by Orbix executes the registered termination handler callback,

```
termination_handler_callback().
```

The termination handler function is defined as follows:

```
static void
termination_handler_callback(
 long signal
)
{
1 if (!CORBA::is_nil(orb))
2 {
 global_orb->shutdown(IT_FALSE);
 }
}
```

The code executes as follows:

1. A check is made to ensure that the `global_orb` variable is initialized.
2. `CORBA::ORB::shutdown()` is invoked. It takes a single boolean argument, the `wait_for_completion` flag.

When `shutdown()` is called with its `wait_for_completion` flag set to `false`, a background thread is created to handle shutdown and the call returns immediately. See “Explicit Event Handling” on page 279.

As soon as `termination_handler()` returns, the operating system returns to the prior execution point and the server resumes processing in

```
CORBA::ORB::run();
```

Server execution now reverts to `main()`:

```

1 global_orb->run();
 //Delete the servants.
2 delete the_Building;

 //Destroy the ORB and reclaim resources.
 try
 {
3 global_orb->destroy();
 }
 catch (...)
 {
 //Do nothing.
 }
 return exit_status;

```

The code executes as follows:

1. After the termination handler completes shutdown, `CORBA::ORB::run()` unblocks and returns.
2. The `BuildingImpl` servant must be explicitly deleted because it is not referenced by a smart pointer.
3. `CORBA::ORB::destroy()` destroys the ORB object.

**Note:** The `shutdown()` function is not called after `CORBA::ORB::run()` returns, because `shutdown()` is already called in the signal handler. It is illegal to call `shutdown()` more than once on the same ORB object.

---

# Complete Source Code for server.cxx

```
//C++
//-----
//
//Edit idgen config file to get your own copyright notice
//placed here.
//-----
//
//Automatically generated server for the following DL
//interfaces:
// Building
//

#include "it_random_funcs.h"
#include <iostream.h>
#include <fstream.h>
#include <string.h>
#include <stdlib.h>
#include <it_ts/nation_handler.h>
#include <omg/PortableServer.h>
#include "BuildingImpl.h"

//global orb - make ORB global so all code can find it.
//
CORBA::ORB_var
global_orb = CORBA::ORB::_nil();
```

```

//termination handler callback handles Ctrl-C-like
//signals/events
//by shutting down the ORB. This causes ORB::run() to return,
//and allows the server to shut down gracefully.

static void
termination_handler_callback(
 long signal
)
{
 cout << "Processing shutdown signal " << signal << endl;
 if (CORBA::is_nil(obj))
 {
 cout << "ORB shutdown ... " << flush;
 obj->shutdown(II_FALSE);
 cout << "done." << endl;
 }
}

//write_reference() — export object reference to file.
//This is a useful way to advertise objects for simple tests and
//demos.
//The CORBA naming service is a more scalable way to advertise
//references.
//
void
write_reference(
 CORBA::Object_ptr ref,
 const char* objef_file
)
{
 CORBA::String_var stringified_ref =
 global_obj->object_to_string(ref);
 cout << "Writing stringified object reference to "
 << objef_file << endl;

 ofstream os(objef_file);
 os << stringified_ref;
 if (!os.good())
 {
 cerr << "Failed to write to " << objef_file << endl;
 }
}

```

```

//create_simple_poa() - Create a POA for simple servant
//management.
//
PortableServer::POA_ptr
create_simple_poa(
 const char* poa_name,
 PortableServer::POA_ptr parent_poa,
 PortableServer::POA_manager_ptr poa_manager
)
{
 //Create a policy list.
 //Policies not set in the list get default values.
 //
 CORBA::PolicyList policies;
 policies.length(1);
 int i = 0;
 //Make the POA single threaded.
 //
 policies[i++] = parent_poa->create_thread_policy(
 PortableServer::SINGLE_THREAD_MODEL
);
 assert(i == 1);

 return parent_poa->create_POA(poa_name,
 poa_manager,
 policies);
}

//main() - set up a POA, create and export object references.
//
int
main(int argc, char** argv)
{
 int exit_status = 0; //Return code from main().

 //Instantiate termination handler
 IT_TerminationHandler
 termination_handler(termination_handler_callback);

 //Variables to hold our servants.
 //Note: PortableServer::Servant is a pointer type - it's
 //actually a typedef for PortableServer::ServantBase*.
 //
 PortableServer::Servant the_Building = 0;

```

```

try
{
 //For temporary object references.
 CORBA::Object_var tmp_ref;

 //Initialise the ORB and RootPOA.
 //
 cout << "Initializing the ORB" << endl;
 global_orb = CORBA::ORB_init(argc, argv);
 tmp_ref =
 global_orb->resolve_initial_references("RootPOA");
 PortableServer::POA_var root_poa =
 PortableServer::POA::narrow(tmp_ref);
 assert(CORBA::is_nil(root_poa));
 PortableServer::POAManager_var root_poa_manager
 = root_poa->the_POAManager();
 assert(CORBA::is_nil(root_poa_manager));

 //Now create our own POA.
 //
 PortableServer::POA_var my_poa =
 create_simple_poa("my_poa", root_poa,
 root_poa_manager);

 //Create servants and export object references.
 //
 //Note: _create is a useful convenience function
 //created by the genie; it is not a standard CORBA
 //function.
 //
 PortableServer::ObjectImpl_var oid;

 //Create a servant for interface Building.
 //
 the_Building = BuildingImpl::_create(my_poa);
 oid = my_poa->activate_object(the_Building);
 tmp_ref = my_poa->id_to_reference(oid);
 write_reference(tmp_ref, "Building.ref");
}

```

```
//Activate the POA Manager and let the ORB process
//requests
//
root_poa_manager-> activate();
cout<< " Waiting for requests..."<< endl;
global_orb-> run();
}
catch (CORBA::Exception& e)
{
 cout<< "Unexpected CORBA exception:"<< e<< endl;
 exit_status = 1;
}

//Delete the servants
//
delete the_Building;

//Destroy the ORB and reclaim resources.
//
try
{
 global_orb-> destroy();
}
catch (...)
{
 //Do nothing.
}
return exit_status;
}
```



# Defining Interfaces

*The CORBA Interface Definition Language (IDL) is used to describe interfaces of objects in an enterprise application. An object's interface describes that object to potential clients—its attributes and operations, and their signatures.*

An IDL-defined object can be implemented in any language that IDL maps to, such as C++, Java, and COBOL. By encapsulating object interfaces within a common language, IDL facilitates interaction between objects regardless of their actual implementation. Writing object interfaces in IDL is therefore central to achieving the CORBA goal of interoperability between different languages and platforms.

CORBA defines standard mappings from IDL to several programming languages, including C++, Java, and Smalltalk. Each IDL mapping specifies how an IDL interface corresponds to a language-specific implementation. Orbix's IDL compiler uses these mappings to convert IDL definitions to language-specific definitions that conform to the semantics of that language.

This chapter describes IDL semantics and uses. For mapping information, refer to language-specific mappings in the Object Management Group's latest CORBA specification.

---

## In this chapter

This chapter contains the following sections:

|                                          |                         |
|------------------------------------------|-------------------------|
| <a href="#">Modules and Name Scoping</a> | <a href="#">page 95</a> |
| <a href="#">Interfaces</a>               | <a href="#">page 97</a> |

|                                      |                          |
|--------------------------------------|--------------------------|
| <a href="#">Valuetypes</a>           | <a href="#">page 113</a> |
| <a href="#">Abstract Interfaces</a>  | <a href="#">page 114</a> |
| <a href="#">IDL Data Types</a>       | <a href="#">page 116</a> |
| <a href="#">Defining Data Types</a>  | <a href="#">page 128</a> |
| <a href="#">Constants</a>            | <a href="#">page 129</a> |
| <a href="#">Constant Expressions</a> | <a href="#">page 132</a> |

---

# Modules and Name Scoping

You create an application's IDL definitions within one or more IDL modules. Each module provides a naming context for the IDL definitions within it.

Modules and interfaces form naming scopes, so identifiers defined inside an interface need to be unique only within that interface. To resolve a name, the IDL compiler conducts its search among the following scopes, in this order:

1. The current interface
2. Base interfaces of the current interface (if any)
3. The scopes that enclose the current interface

In the following example, two interfaces, `Bank` and `Account`, are defined within module `BankDemo`:

```
module BankDemo
{
 interface Bank {
 //...
 };

 interface Account {
 //...
 };
};
```

Within the same module, interfaces can reference each other by name alone. If an interface is referenced from outside its module, its name must be fully scoped with the following syntax:

*module-name::interface-name*

For example, the fully scoped names of interfaces `Bank` and `Account` are `BankDemo::Bank` and `BankDemo::Account`, respectively.

---

## Nesting restrictions

A module cannot be nested inside a module of the same name. Likewise, you cannot directly nest an interface inside a module of the same name. To avoid name ambiguity, you can provide an intervening name scope as follows:

```
module A
{
 module B
 {
 interface A {
 //...
 };
 };
};
```

---

# Interfaces

Interfaces are the fundamental abstraction mechanism of CORBA. An interface defines a type of object, including the operations that the object supports in a distributed enterprise application.

An IDL interface generally describes an object's behavior through operations and attributes:

- Operations of an interface give clients access to an object's behavior. When a client invokes an operation on an object, it sends a message to that object. The ORB transparently dispatches the call to the object, whether it is in the same address space as the client, in another address space on the same machine, or in an address space on a remote machine.
- An IDL attribute is short-hand for a pair of operations that get and, optionally, set values in an object.

For example, the `Account` interface in module `BankDemo` describes the objects that implement bank accounts:

```
module BankDemo
{
 typedef float CashAmount; //Type for representing cash
 typedef string AccountID; //Type for representing account
 ids
 //...
 interface Account {
 readonly attribute AccountID account_id;
 readonly attribute CashAmount balance;

 void
 withdraw (in CashAmount amount);
 raises (InsufficientFunds);

 void
 deposit (in CashAmount amount);
 };
};
```

This interface declares two readonly attributes, `AccountId` and `balance`, which are defined as typedefs of `string` and `float`, respectively. The interface also defines two operations that a client can invoke on this object, `withdraw()` and `deposit()`.

Because an interface does not expose an object's implementation, all members are public. A client can access variables in an object's implementations only through an interface's operations or attributes.

While every CORBA object has exactly one interface, the same interface can be shared by many CORBA objects in a system. CORBA object references specify CORBA objects—that is, interface instances. Each reference denotes exactly one object, which provides the only means by which that object can be accessed for operation invocations.

---

## Interface Contents

An IDL interface can define the following components:

- [Operations](#)
- [Attributes](#)
- [Exceptions](#)
- [Types](#)
- Constants

Of these, operations and attributes must be defined within the scope of an interface; all other components can be defined at a higher scope.

## Operations

IDL operations define the signatures of an object's function, which client invocations on that object must use. The signature of an IDL operation is generally composed of three components:

- Return value data type
- Parameters and their direction
- Exception clause

A operation's return value and parameters can use any data types that IDL supports (see [“Abstract Interfaces” on page 114](#)).

For example, the `Account` interface defines two operations, `withdraw()` and `deposit()`; it also defines the exception `InsufficientFunds`

```
module BankDemo
{
 typedef float CashAmount; //Type for representing cash
 //...
 interface Account {
 exception InsufficientFunds {};

 void
 withdraw (in CashAmount amount)
 raises (InsufficientFunds);

 void
 deposit(in CashAmount amount);
 };
};
```

On each invocation, both operations expect the client to supply an argument for parameter `amount`, and return `void`. Invocations on `withdraw()` can also raise the exception `InsufficientFunds`, if necessary.

### Parameter direction

Each parameter specifies the direction in which its arguments are passed between client and object. Parameter passing modes clarify operation definitions and allow the IDL compiler to map operations accurately to a target programming language. At runtime, Orbix uses parameter passing modes to determine in which direction or directions it must marshal a parameter.

A parameter can take one of three passing mode qualifiers:

**in:** The parameter is initialized only by the client and is passed to the object.

**out:** The parameter is initialized only by the object and returned to the client.

**inout:** The parameter is initialized by the client and passed to the server; the server can modify the value before returning it to the client.

In general, you should avoid using `inout` parameters. Because an `inout` parameter automatically overwrites its initial value with a new value, its usage assumes that the caller has no use for the parameter's original value. Thus, the caller must make a copy of the parameter in order to retain that value. By using two parameters, `in` and `out`, the caller can decide for itself when to discard the parameter.

## One-way operations

By default, IDL operations calls are *synchronous*—that is, a client invokes an operation on an object and blocks until the invoked operation returns. If an operation definition begins with the keyword `oneway`, a client that calls the operation remains unblocked while the object processes the call.

Three constraints apply to a one-way operation:

- The return value must be set to `void`.
- Directions of all parameters must be set to `in`.
- No `raises` clause is allowed.

For example, interface `Account` might contain a one-way operation that sends a notice to an `Account` object:

```
module BankDemo {
 //...
 interface Account {
 oneway void notice(in string text);
 //...
 };
};
```

Orbix cannot guarantee the success of a one-way operation call. Because one-way operations do not support return data to the client, the client cannot ascertain the outcome of its invocation. Orbix only indicates failure of a one-way operation if the call fails before it exits the client's address space; in this case, Orbix raises a system exception.

A client can also issue non-blocking, or asynchronous, invocations. For more information, see [Chapter 12 on page 347](#).

---

## Attributes

An interface's attributes correspond to the variables that an object implements. Attributes indicate which variables in an object are accessible to clients.

Unqualified attributes map to a pair of get and set functions in the implementation language, which let client applications read and write attribute values. An attribute that is qualified with the keyword `readonly` maps only to a get function.

For example, the `Account` interface defines two `readonly` attributes, `AccountId` and `balance`. These attributes represent information about the account that only the object implementation can set; clients are limited to read-only access.

## Exceptions

IDL operations can raise one or more CORBA-defined system exceptions. You can also define your own exceptions and explicitly specify these in an IDL operation. An IDL exception is a data structure that can contain one or more member fields, formatted as follows:

```
exception exception-name {
 [member;]...
};
```

After you define an exception, you can specify it through a `raises` clause in any operation that is defined within the same scope. A `raises` clause can contain multiple comma-delimited exceptions:

```
return-val operation-name([params-list])
 raises(exception-name[,exception-name]);
```

Exceptions that are defined at module scope are accessible to all operations within that module; exceptions that are defined at interface scope are accessible only to operations within that interface.

For example, interface `Account` defines the exception `InsufficientFunds` with a single member of data type `string`. This exception is available to any operation within the interface. The following IDL defines the `withdraw()` operation to raise this exception when the withdrawal fails:

```
module BankDemo
{
 typedef float CashAmount; //Type for representing cash
 //...
 interface Account {
 exception InsufficientFunds {};

 void
 withdraw(in CashAmount amount)
 raises (InsufficientFunds);
 //...
 };
};
```

For more about exception handling, see [Chapter 13 on page 359](#).

---

## Empty Interfaces

IDL allows you to define empty interfaces. This can be useful when you wish to model an abstract base interface that ties together a number of concrete derived interfaces. For example, the CORBA `PortableServer` module defines the abstract `ServantManager` interface, which serves to join the interfaces for two servant manager types, servant activator and servant locator:

```
module PortableServer
{
 interface ServantManager {};

 interface ServantActivator : ServantManager {
 //...
 };

 interface ServantLocator : ServantManager {
 //...
 };
};
```

---

## Inheritance of IDL Interfaces

An IDL interface can inherit from one or more interfaces. All elements of an inherited, or *base interface*, are available to the *derived interface*. An interface specifies the base interfaces from which it inherits as follows:

```
interface new-interface :base-interface[,base-interface]...
{...};
```

For example, the following interfaces, `CheckingAccount` and `SavingsAccount`, inherit from interface `Account` and implicitly include all of its elements:

```
module BankDemo {
 typedef float CashAmount; //Type for representing cash
 interface Account {
 //...
 };

 interface CheckingAccount : Account {
 readonly attribute CashAmount overdraftLimit;
 boolean orderCheckBook ();
 };

 interface SavingsAccount : Account {
 float calculateInterest ();
 };
};
```

An object that implements `CheckingAccount` can accept invocations on any of its own attributes and operations and on any of the elements of interface `Account`. However, the actual implementation of elements in a `CheckingAccount` object can differ from the implementation of corresponding elements in an `Account` object. IDL inheritance only ensures type-compatibility of operations and attributes between base and derived interfaces.

## Multiple inheritance

The following IDL definition expands module `BankDemo` to include interface `PremiumAccount`, which inherits from two interfaces, `CheckingAccount` and `SavingsAccount`:


```
module BankDemo {
 interface Account {
 //...
 };

 interface CheckingAccount : Account {
 //...
 };

 interface SavingsAccount : Account {
 //...
 };

 interface PremiumAccount :
 CheckingAccount, SavingsAccount {
 //...
 };
};
```

Figure 7 shows the inheritance hierarchy for this interface.



**Figure 7:** Multiple inheritance of IDL interfaces

Multiple inheritance can lead to name ambiguity among elements in the base interfaces. The following constraints apply:

- Names of operations and attributes must be unique across all base interfaces.
- If the base interfaces define constants, types, or exceptions of the same name, references to those elements must be fully scoped.

### Inheritance of the object interface

All user-defined interfaces implicitly inherit the predefined interface `Object`. Thus, all `Object` operations can be invoked on any user-defined interface. You can also use `Object` as an attribute or parameter type to indicate that any interface type is valid for the attribute or parameter. For example, the following operation `getAnyObject()` serves as an all-purpose object locator:

```
interface ObjectLocator {
 void getAnyObject (out Object ob);
};
```

**Note:** It is illegal IDL syntax to inherit interface `Object` explicitly.

### Inheritance redefinition

A derived interface can modify the definitions of constants, types, and exceptions that it inherits from a base interface. All other components that are inherited from a base interface cannot be changed. In the following example, interface `CheckingAccount` modifies the definition of exception `InsufficientFunds`, which it inherits from `Account`:

```
module BankDemo
{
 typedef float CashAmount; //Type for representing cash
 //...
 interface Account {
 exception InsufficientFunds {};
 //...
 };
 interface CheckingAccount : Account {
 exception InsufficientFunds {
 CashAmount overchaffLimit;
 };
 };
 //...
};
```

**Note:** While a derived interface definition cannot override base operations or attributes, operation overloading is permitted in interface implementations for those languages such as C++ that support it.

## Forward Declaration of IDL Interfaces

An IDL interface must be declared before another interface can reference it. If two interfaces reference each other, the module must contain a forward declaration for one of them; otherwise, the IDL compiler reports an error. A forward declaration only declares the interface's name; the interface's actual definition is deferred until later in the module.

For example, IDL interface `Bank` defines two operations that return references to `Account` objects—`create_account()` and `find_account()`.

Because interface `Bank` precedes the definition of interface `Account`, `Account` is forward-declared as follows:

```
module BankDemo
{
 typedef float CashAmount; //Type for representing cash
 typedef string AccountId; //Type for representing account
 ids

 //Forward declaration of Account
 interface Account;

 //Bank interface...used to create Accounts
 interface Bank {
 exception AccountAlreadyExists { AccountId account_id; };
 exception AccountNotFound { AccountId account_id; };

 Account
 find_account(in AccountId account_id)
 raises(AccountNotFound);

 Account
 create_account(
 in AccountId account_id,
 in CashAmount initial_balance
) raises (AccountAlreadyExists);
 };

 //Account interface...used to deposit, withdraw , and query
 //available funds.
 interface Account {
 //...
 };
};
```

## Local Interfaces

An interface declaration that contains the keyword `local` defines a *local interface*. An interface declaration that omits this keyword can be referred to as an *unconstrained interface*, to distinguish it from local interfaces. An object that implements a local interface is a *local object*.

Local interfaces differ from unconstrained interfaces in the following ways:

- A local interface can inherit from any interface, whether local or unconstrained. However, an unconstrained interface cannot inherit from a local interface.
- Any non-interface type that uses a local interface is regarded as a *local type*. For example, a struct that contains a local interface member is regarded as a local struct, and is subject to the same localization constraints as a local interface.
- Local types can be declared as parameters, attributes, return types, or exceptions only in a local interface, or as state members of a valuetype.
- Local types cannot be marshaled, and references to local objects cannot be converted to strings through `ORB::object_to_string()`. Attempts to do so throw `CORBA::MARSHAL`.
- Any operation that expects a reference to a remote object cannot be invoked on a local object. For example, you cannot invoke any DII operations or asynchronous methods on a local object; similarly, you cannot invoke pseudo-object operations such as `is_a()` or `validate_connection()`. Attempts to do so throw `CORBA::NO_IMPLEMENT`.
- The ORB does not mediate any invocation on a local object. Thus, local interface implementations are responsible for providing the parameter copy semantics that a client expects.
- Instances of local objects that the OMG defines as supplied by ORB products are exposed either directly or indirectly through `ORB::resolve_initial_references()`.

Local interfaces are implemented by `CORBA::LocalObject` to provide implementations of Object pseudo operations, and other ORB-specific support mechanisms that apply. Because object implementations are language-specific, the `LocalObject` type is only defined by each language mapping.

The `LocalObject` type implements the following Object pseudo-operations to throw an exception of `NO_IMPLEMENT`:

```
is_a()
get_interface()
get_distributed_managers()
get_policy()
get_client_policy()
set_policy_overrides()
get_policy_overrides()
validate_connection()
```

`CORBA::LocalObject` also implements the pseudo-operations shown in [Table 1](#):

**Table 1:** *CORBA::LocalObject pseudo-operation returns*

| Operation                    | Always returns:                                                                   |
|------------------------------|-----------------------------------------------------------------------------------|
| <code>non_existent()</code>  | False                                                                             |
| <code>hash()</code>          | A hash value that is consistent with the object's lifetime                        |
| <code>is_equivalent()</code> | True if the references refer to the same <code>LocalObject</code> implementation. |

---

# Valuetypes

Valuetypes enable programs to pass objects by value across a distributed system. This type is especially useful for encapsulating lightweight data such as linked lists, graphs, and dates.

Valuetypes can be seen as a cross between data types such as `long` and `string` that can be passed by value over the wire as arguments to remote invocations, and objects, which can only be passed by reference. When a program supplies an object reference, the object remains in its original location; subsequent invocations on that object from other address spaces move across the network, rather than the object moving to the site of each request.

Like an interface, a valuetype supports both operations and inheritance from other valuetypes; it also can have data members. When a valuetype is passed as an argument to a remote operation, the receiving address space creates a copy of it. The copied valuetype exists independently of the original; operations that are invoked on one have no effect on the other.

Because a valuetype is always passed by value, its operations can only be invoked locally. Unlike invocations on objects, valuetype invocations are never passed over the wire to a remote valuetype.

Valuetype implementations necessarily vary, depending on the languages used on sending and receiving ends of the transmission, and their respective abilities to marshal and demarshal the valuetype's operations. A receiving process that is written in C++ must provide a class that implements valuetype operations and a factory to create instances of that class. These classes must be either compiled into the application, or made available through a shared library. Conversely, Java applications can marshal enough information on the sender, so the receiver can download the bytecodes for the valuetype operation implementations.

## Abstract Interfaces

An application can use abstract interfaces to determine at runtime whether an object is passed by reference or by value. For example, the following IDL definitions specify that operation `Example::display()` accepts any derivation of abstract interface `Describable`:

```
abstract interface Describable {
 string get_description();
};

interface Example {
 void display(in Describable someObject);
};
```

Given these definitions, you can define two derivations of abstract interface `Describable`, valuetype `Currency` and interface `Account`:

```
interface Account : Describable {
 //body of Account definition not shown
};

valuetype Currency supports Describable {
 //body of Currency definition not shown
};
```

Because the parameter for `display()` is defined as a `Describable` type, invocations on this operation can supply either `Account` objects or `Currency` valuetypes.

All abstract interfaces implicitly inherit from native type `CORBA::AbstractBase`, and map to C++ abstract base classes. Abstract interfaces have several characteristics that differentiate them from interfaces:

- The GIOP encoding of an abstract interface contains a boolean discriminator to indicate whether the adjoining data is an IOR (`TRUE`) or a value (`FALSE`). The demarshalling code can thus determine whether the argument passed to it is an object reference or a value.

- Unlike interfaces, abstract interfaces do not inherit from `CORBA::Object`, in order to allow support for valuetypes. If the runtime argument supplied to an abstract interface type can be narrowed to an object reference type, then `CORBA::Object` operations can be invoked on it.
- Because abstract interfaces can be derived by object references or by value types, copy semantics cannot be guaranteed for value types that are supplied as arguments to its operations.
- Abstract interfaces can only inherit from other abstract interfaces.

## IDL Data Types

In addition to IDL module, interface, valuetype, and exception types, IDL data types can be grouped into the following categories:

- **Built-in types** such as `short`, `long`, and `float`
- **Extended built-in types** such as `long long` and `wstring`
- **Complex data types** such as `enum` and `struct`, and `string`
- **Pseudo object types**

## Built-in Types

Table 2 lists built-in IDL types.

**Table 2:** *Built-in IDL types*

| Data type                        | Size            | Range of values                              |
|----------------------------------|-----------------|----------------------------------------------|
| <code>short</code>               | 16 bits         | $-2^{15} \dots 2^{15}-1$                     |
| <code>unsigned short</code>      | 16 bits         | $0 \dots 2^{16}-1$                           |
| <code>long</code>                | 32 bits         | $-2^{31} \dots 2^{31}-1$                     |
| <code>unsigned long</code>       | 32 bits         | $0 \dots 2^{32}-1$                           |
| <code>float</code>               | 32 bits         | IEEE single-precision floating point numbers |
| <code>double</code>              | 64 bits         | IEEE double-precision floating point numbers |
| <code>char</code>                | 8 bits          | ISO Latin-1                                  |
| <code>string</code>              | variable length | ISO Latin-1, except NUL                      |
| <code>string&lt;bound&gt;</code> | variable length | ISO Latin-1, except NUL                      |
| <code>boolean</code>             | unspecified     | TRUE OR FALSE                                |
| <code>octet</code>               | 8 bits          | 0x0 to 0xff                                  |
| <code>any</code>                 | variable length | Universal container type                     |

### Integer types

IDL supports `short` and `long` integer types, both signed and unsigned. IDL guarantees the range of these types. For example, an unsigned short can hold values between 0-65535. Thus, an unsigned short value always maps to a native type that has at least 16 bits. If the platform does not provide a native 16-bit type, the next larger integer type is used.

### Floating point types

Types `float` and `double` follow IEEE specifications for single- and double-precision floating point values, and on most platforms map to native IEEE floating point types.

**char**


---

Type `char` can hold any value from the ISO Latin-1 character set. Code positions 0-127 are identical to ASCII. Code positions 128-255 are reserved for special characters in various European languages, such as accented vowels.

---

**String types**

Type `string` can hold any character from the ISO Latin-1 character set except `NULL`. IDL prohibits embedded `NULL` characters in strings. Unbounded string lengths are generally constrained only by memory limitations. A bounded string, such as `string< 10>`, can hold only the number of characters specified by the bounds, excluding the terminating `NULL` character. Thus, a `string< 6>` can contain the six-character string `cheese`.

The declaration statement can optionally specify the string's maximum length, thereby determining whether the string is bounded or unbounded:

```
string[< length >] name
```

For example, the following code declares data type `ShortString`, which is a bounded string whose maximum length is 10 characters:

```
typedef string< 10> ShortString;
attribute ShortString shortName; //max length is 10 chars
```

---

**octet**

`Octet` types are guaranteed not to undergo any conversions in transit. This lets you safely transmit binary data between different address spaces. Avoid using type `char` for binary data, inasmuch as characters might be subject to translation during transmission. For example, if client that uses ASCII sends a string to a server that uses EBCDIC, the sender and receiver are liable to have different binary values for the string's characters.

---

**any**

Type `any` allows specification of values that express any IDL type, which is determined at runtime. An `any` logically contains a `TypeCode` and a value that is described by the `TypeCode`. For more information about the `any` data type, see [Chapter 15 on page 393](#).

## Extended Built-in Types

Table 3 lists extended built-in IDL types.

**Table 3:** *Extended built-in IDL types*

| Data type                       | Size            | Range of values                                                                                                                                                                                             |
|---------------------------------|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>long long</code>          | 64 bits         | $-2^{63} \dots 2^{63}-1$                                                                                                                                                                                    |
| <code>unsigned long long</code> | 64 bits         | $0 \dots 2^{64}-1$                                                                                                                                                                                          |
| <code>long double</code>        | 79 bits         | IEEE double-extended floating point number, with an exponent of at least 15 bits in length and signed fraction of at least 64 bits. <code>long double</code> type is currently not supported on Windows NT. |
| <code>wchar</code>              | Unspecified     | Arbitrary codesets                                                                                                                                                                                          |
| <code>wstring</code>            | Variable length | Arbitrary codesets                                                                                                                                                                                          |
| <code>fixed</code>              | Unspecified     | 31 significant digits                                                                                                                                                                                       |

### **long long**

The 64-bit integer types `long long` and `unsigned long long` support numbers that are too large for 32-bit integers. Platform support varies. If you compile IDL that contains one of these types on a platform that does not support it, the compiler issues an error.

### **long double**

Like 64-bit integer types, platform support varies for `long double`, so usage can yield IDL compiler errors.

### **wchar**

Type `wchar` encodes wide characters from any character set. The size of a `wchar` is platform-dependent.

### **wstring**

Type `wstring` is the wide-character equivalent of type `string` (see [page 118](#)). Like `string` types, `wstring` types can be unbounded or bounded. Wide strings can contain any character except `NUL`.

**fixed**

Type `fixed` provides fixed-point arithmetic values with up to 31 significant digits. You specify a `fixed` type with the following format:

```
typedef fixed < digit-size, scale > name
```

*digit-size* specifies the number's length in digits. The maximum value for *digit-size* is 31 and must be greater than *scale*. A fixed type can hold any value up to the maximum value of a `double`.

**Scaling options**

If *scale* is a positive integer, it specifies where to place the decimal point relative to the rightmost digit. For example the following code declares fixed data type `CashAmount` to have a digit size of 8 and a scale of 2:

```
typedef fixed < 10, 2 > CashAmount;
```

Given this typedef, any variable of type `CashAmount` can contain values of up to (+/-)99999999.99.

If *scale* is negative, the decimal point moves to the right *scale* digits, thereby adding trailing zeros to the fixed data type's value. For example, the following code declares fixed data type `bigNum` to have a digit size of 3 and a scale of -4:

```
typedef fixed < 3, -4 > bigNum ;
bigNum myBigNum ;
```

If `myBigNum` has a value of `123`, its numeric value resolves to `1230000`. Definitions of this sort let you store numbers with trailing zeros efficiently.

**Constant fixed types**

Constant fixed types can also be declared in IDL, where *digit-size* and *scale* are automatically calculated from the constant value. For example:

```
module Circle {
 const fixed pi= 3.142857;
};
```

This yields a fixed type with a digit size of 7, and a scale of 6.

Unlike IEEE floating-point values, type `fixed` is not subject to representational errors. IEEE floating point values are liable to represent decimal fractions inaccurately unless the value is a fractional power of 2.

For example, the decimal value 0.1 cannot be represented exactly in IEEE format. Over a series of computations with floating-point values, the cumulative effect of this imprecision can eventually yield inaccurate results. Type `fixed` is especially useful in calculations that cannot tolerate any imprecision, such as computations of monetary values.

---

## Complex Data Types

IDL provides the following complex data types:

- [enum](#)
- [struct](#)
- [union](#)
- multi-dimensional fixed-size [arrays](#)
- [sequence](#)

---

### enum

An enum (enumerated) type lets you assign identifiers to the members of a set of values. For example, you can modify the `BankDemo` IDL with enum type `balanceCurrency`:

```
module BankDemo {
 enum Currency {pound, dollar, yen, franc};

 interface Account {
 readonly attribute CashAmount balance;
 readonly attribute Currency balanceCurrency;
 //...
 };
};
```

In this example, attribute `balanceCurrency` in interface `Account` can take any one of the values `pound`, `dollar`, `yen`, or `franc`.

The actual ordinal values of a `enum` type vary according to the actual language implementation. The CORBA specification only guarantees that the ordinal values of enumerated types monotonically increase from left to right. Thus, in the previous example, `dollar` is greater than `pound`, `yen` is greater than `dollar`, and so on. All enumerators are mapped to a 32-bit type.

**struct**

A `struct` data type lets you package a set of named members of various types. In the following example, `struct CustomerDetails` has several members. Operation `getCustomerDetails()` returns a `struct` of type `CustomerDetails` that contains customer data:

```
module BankDemo {
 struct CustomerDetails {
 string custID;
 string name;
 string phone;
 string address;
 //...
 };

 interface Bank {
 CustomerDetails getCustomerDetails
 (in string custID);
 //...
 };
};
```

A `struct` must include at least one member. Because a `struct` provides a naming scope, member names must be unique only within the enclosing structure.

**union**

A `union` data type lets you define a structure that can contain only one of several alternative members at any given time. A `union` saves space in memory, as the amount of storage required for a `union` is the amount necessary to store its largest member.

You declare a `union` type with the following syntax:

```
union name switch (discriminator) {
 case label1 : element-spec;
 case label2 : element-spec;
 [...]
 case labelN : element-spec;
 [default : element-spec;]
};
```

All IDL unions are *discriminated*. A discriminated union associates a constant expression (*label1..labelN*) with each member. The discriminator's value determines which of the members is active and stores the union's value.

For example, the following code defines the IDL union `Date`, which is discriminated by an `enum` value:

```
enum dateStorage
{ num_eric, stMDDYY, stDDMMYY };

struct DateStructure {
 short Day;
 short Month;
 short Year;
};

union Date switch (dateStorage) {
 case num_eric: long digitalFormat;
 case stMDDYY:
 case stDDMMYY: string stringFormat;
 default: DateStructure structFormat;
};
```

Given this definition, if `Date`'s discriminator value is `num_eric`, then `digitalFormat` member is active; if the discriminator's value is `stMDDYY` or `stDDMMYY`, then member `stringFormat` is active; otherwise, the default member `structFormat` is active.

The following rules apply to `union` types:

- A union's discriminator can be `integer`, `char`, `boolean` or `enum`, or an alias of one of these types; all `case` label expressions must be compatible with this type.
- Because a `union` provides a naming scope, member names must be unique only within the enclosing union.
- Each `union` contains a pair of values: the discriminator value and the active member.
- IDL unions allow multiple case labels for a single member. In the previous example, member `stringFormat` is active when the discriminator is either `stMDDYY` or `stDDMMYY`.

- IDL unions can optionally contain a `default` case label. The corresponding member is active if the discriminator value does not correspond to any other label.

## arrays

IDL supports multi-dimensional fixed-size arrays of any IDL data type, with the following syntax:

```
[typedef] element-type array-name [dimension-spec]...
```

*dimension-spec* must be a non-zero positive constant integer expression. IDL does not allow open arrays. However, you can achieve equivalent functionality with `sequence` types (see page 125).

For example, the following code fragment defines a two-dimensional array of bank accounts within a portfolio:

```
typedef Account portfolio[MAX_ACCT_TYPES][MAX_ACCTS]
```

An array must be named by a `typedef` declaration (see “[Defining Data Types](#)” on page 128) in order to be used as a parameter, an attribute, or a return value. You can omit a `typedef` declaration only for an array that is declared within a structure definition.

Because of differences between implementation languages, IDL does not specify the origin at which arrays are indexed. For example C and C++ array indexes always start at 0, while Pascal uses an origin of 1. Consequently, clients and servers cannot portably exchange array indexes unless they both agree on the origin of array indexes and make adjustments as appropriate for their respective implementation languages. Usually, it is easier to exchange the array element itself instead of its index.

## sequence

IDL supports sequences of any IDL data type with the following syntax:

```
[typedef] sequence < element-type[,max-elements] >
sequence-name
```

An IDL sequence is similar to a one-dimensional array of elements; however, its length varies according to its actual number of elements, so it uses memory more efficiently.

A sequence must be named by a `typedef` declaration (see [“Defining Data Types” on page 128](#)) in order to be used as a parameter, an attribute, or a return value. You can omit a `typedef` declaration only for a sequence that is declared within a structure definition.

A sequence’s element type can be of any type, including another sequence type. This feature is often used to model trees.

The maximum length of a sequence can be fixed (bounded) or unfixed (unbounded):

- Unbounded sequences can hold any number of elements, up to the memory limits of your platform.
- Bounded sequences can hold any number of elements, up to the limit specified by the bound.

The following code shows how to declare bounded and unbounded sequences as members of an IDL struct:

```
structLim fixedAccounts {
 string bankSortCode< 10> ;
 sequence< Account, 50> accounts; //m ax sequence length is 50
};

structUnlim fixedAccounts {
 string bankSortCode< 10> ;
 sequence< Account> accounts; //no m ax sequence length
};
```

---

## Pseudo Object Types

CORBA defines a set of pseudo object types that ORB implementations use when mapping IDL to a programming language. These object types have interfaces defined in IDL but do not have to follow the normal IDL mapping for interfaces and are not generally available in your IDL specifications.

You can use only the following pseudo object types as attribute or operation parameter types in an IDL specification:

```
CORBA::NamedValue
CORBA::TypeCode
```

To use these types in an IDL specification, include the file `orb.idl` in the IDL file as follows:

```
#include <orb.idl>
//...
```

This statement tells the IDL compiler to allow types `NamedValue` and `TypeCode`.

---

## Defining Data Types

With `typedef`, you can define more meaningful or simpler names for existing data types, whether IDL-defined or user-defined. The following IDL defines `typedef` identifier `StandardAccount`, so it can act as an alias for type `Account` in later IDL definitions:

```
module BankDemo {
 interface Account {
 //...
 };

 typedef Account StandardAccount;
};
```

---

# Constants

IDL lets you define constants of all built-in types except type `any`. To define a constant's value, you can either use another constant (or constant expression) or a literal. You can use a constant wherever a literal is permitted.

The following constant types are supported:

- [Integer](#)
- [Floating-point](#)
- [Character and string](#)
- [Wide character and string](#)
- [Boolean](#)
- [Octet](#)
- [Fixed-point](#)
- [Enumeration](#)

---

## Integer

IDL accepts integer literals in decimal, octal, or hexadecimal:

```
const short I1 = -99;
const long I2 = 0123; //Octal123,decim a183
const long long I3 = 0x123; //Hexadecim a1123,decim a1291
const long long I4 = + 0xab; //Hexadecim a1ab,decim a1171
```

Both unary plus and unary minus are legal.

---

## Floating-point

Floating-point literals use the same syntax as C++:

```
const float f1 = 3.1e-9; //Integer part, fraction part,
 //exponent
const double f2 = -3.14; //Integer part and fraction part
const long double f3 = .1 //Fraction part only
const double f4 = 1. //Integer part only
const double f5 = .1E12 //Fraction part and exponent
const double f6 = 2E12 //Integer part and exponent
```

## Character and string

Character constants use the same escape sequences as C++:

```

const char C1 = 'c'; //the character c
const char C2 = '\007'; //ASCII BEL, octal escape
const char C3 = '\x41'; //ASCII A, hex escape
const char C4 = '\n'; //new line
const char C5 = '\t'; //tab
const char C6 = '\v'; //vertical tab
const char C7 = '\b'; //backspace
const char C8 = '\r'; //carriage return
const char C9 = '\f'; //form feed
const char C10 = '\a'; //alert
const char C11 = '\\'; //backslash
const char C12 = '\?'; //question mark
const char C13 = '\'; //single quote
//String constants support the same escape sequences as C++
const string S1 = "Quote: \\"; //string with double quote
const string S2 = "hello world"; //simple string
const string S3 = "hello" "world"; //concatenate
const string S4 = "\xA" "B"; //two characters
//(\xA 'and B '),
//not the single character \xAB

```

## Wide character and string

Wide character and string constants use C++ syntax. Use Universal character codes to represent arbitrary characters. For example:

```

const wchar C = L'X';
const wstring GREETING = L"Hello";
const wchar OMEGA = L'\u03a9';
const wstring OMEGA_STR = L"Omega: \u03A9";

```

**Note:** IDL files themselves always use the ISO Latin-1 code set, they cannot use Unicode or other extended character sets.

## Boolean

Boolean constants use the keywords `FALSE` and `TRUE`. Their use is unnecessary, inasmuch as they create needless aliases:

```

//There is no need to define boolean constants:
const CONTRADICTION = FALSE; //Pointless and confusing
const TAUTOLOGY = TRUE; //Pointless and confusing

```

**Octet**

Octet constants are positive integers in the range 0-255.

```
const octet O1 = 23;
const octet O2 = 0xf0;
```

**Note:** Octet constants were added with CORBA 2.3, so ORBs that are not compliant with this specification might not support them.

**Fixed-point**

For fixed-point constants, you do not explicitly specify the digits and scale. Instead, they are inferred from the initializer. The initializer must end in a or D. For example:

```
//Fixed point constants take digits and scale from the
//initializer:
const fixed val1 = 3D; //fixed< 1,0>
const fixed val2 = 03.14d; //fixed< 3,2>
const fixed val3 = -03000.00D; //fixed< 4,0>
const fixed val4 = 0.03D; //fixed< 3,2>
```

The type of a fixed-point constant is determined after removing leading and trailing zeros. The remaining digits are counted to determine the digits and scale. The decimal point is optional.

**Note:** Currently, there is no way to control the scale of a constant if it ends in trailing zeros.

**Enumeration**

Enumeration constants must be initialized with the scoped or unscoped name of an enumerator that is a member of the type of the enumeration. For example:

```
enum Size { small, medium, large };

const Size DFL_SIZE = medium;
const Size MAX_SIZE = ::large;
```

**Note:** Enumeration constants were added with CORBA 2.3, so ORBs that are not compliant with this specification might not support them.

---

# Constant Expressions

IDL provides a number of [arithmetic](#) and [bitwise](#) operators.

---

## Operator precedence

The precedence for operators follows the rules for C++. You can override the default precedence by adding parentheses.

---

## Arithmetic operators

The arithmetic operators have the usual meaning and apply to integral, floating-point, and fixed-point types (except for %, which requires integral operands). However, these operators do not support mixed-mode arithmetic; you cannot, for example, add an integral value to a floating-point value. The following code contains several examples:

```
//You can use arithmetic expressions to define constants.
const long MIN = -10;
const long MAX = 30;
const long DFLT = (MIN + MAX) / 2;

//Can't use 2 here
const double TWICE_PI = 3.1415926 * 2.0;

//5% discount
const fixed DISCOUNT = 0.05D;
const fixed PRICE = 99.99D;

//Can't use 1 here
const fixed NET_PRICE = PRICE * (1.0D - DISCOUNT);
```

Expressions are evaluated using the type promotion rules of C++. The result is coerced back into the target type. The behavior for overflow is undefined, so do not rely on it. Fixed-point expressions are evaluated internally with 62 bits of precision, and results are truncated to 31 digits.

## Bitwise operators

The bitwise operators only apply to integral types. The right-hand operand must be in the range 0–63. Note that the right-shift operator `>>` is guaranteed to inject zeros on the left, whether the left-hand operand is signed or unsigned:

```
//You can use bitwise operators to define constants.
const long ALL_ONES = -1; //0xffffffff
const long LHW_MASK = ALL_ONES << 16; //0xffff0000
const long RHW_MASK = ALL_ONES >> 16; //0x0000ffff
```

IDL guarantees two's complement binary representation of values.



# Developing Applications with Genies

*The code generation toolkit is packaged with several genies that can help your development effort get off to a fast start.*

Two genies generate code that you can use immediately for application development:

- `app_poa_genie.tcl` reads IDL code and generates C++ source files that you can compile into a working application.
- `app_poa_op.tcl` generates the C++ signatures of specified operations and attributes and writes them to a file. You can use this genie on new or changed interfaces, then update existing source code with the generated signatures.

**Note:** Orbix Mainframe does not support the code generation toolkit and distributed genies.

## In this chapter

This chapter covers the following topics:

[Starting Development Projects](#)

page 137

|                                                                |                          |
|----------------------------------------------------------------|--------------------------|
| <a href="#">Generating Signatures of Individual Operations</a> | <a href="#">page 160</a> |
| <a href="#">Configuration Settings</a>                         | <a href="#">page 161</a> |

---

# Starting Development Projects

The C++ `genie_cpp_poa_genie.tcl` creates a complete, working client and server directly from your IDL interfaces. You can then add application logic to the generated code. This can improve productivity in two ways:

- The outlines of your application—class declarations and operation signatures—are generated for you.
- A working system is available immediately, which you can incrementally modify and test. With the generated makefile, you can build and test modifications right away, thereby eliminating much of the overhead that is usually associated with getting a new project underway.

In a genie-generated application, the client invokes every operation and each attribute's get and set methods, and directs all display to standard output. The server also writes all called operations to standard output.

This client/server application achieves these goals:

- Demonstrates or tests an Orbix client/server application for a particular interface or interfaces.
- Provides a starting point for your application.
- Shows the right way to initialize and pass parameters, and to manage memory for various IDL data types.

## Genie Syntax

`cpp_poa_genie.tcl` uses the following syntax:

```
idgen cpp_poa_genie.tcl component-spec [options] idl-file
```

You must specify an IDL file. You must also specify the application components to generate, either all components at once, or individual components, with one of the arguments in [Table 4](#):

**Table 4:** *Component specifier arguments to `cpp_poa_genie.tcl`*

| Component specifier    | Output                                                                                  |
|------------------------|-----------------------------------------------------------------------------------------|
| <code>-all</code>      | All components: server, servant, client, and makefile ( <a href="#">see page 140</a> ). |
| <code>-servant</code>  | Servant classes to implement the selected interfaces ( <a href="#">see page 144</a> ).  |
| <code>-server</code>   | Server main program ( <a href="#">see page 148</a> )                                    |
| <code>-client</code>   | Client main program ( <a href="#">see page 152</a> ).                                   |
| <code>-makefile</code> | A makefile to compile server and client applications ( <a href="#">see page 153</a> ).  |

Each component specifier can take its own arguments. For more information on these, refer to the discussion on each component later in this chapter.

You can also supply one or more of the optional switches shown in [Table 5](#):

**Table 5:** *Optional switches to `cpp_poa_genie.tcl`*

| Option                            | Description                                                                                                            |
|-----------------------------------|------------------------------------------------------------------------------------------------------------------------|
| <code>-complete/incomplete</code> | Controls the completeness of the code that is generated for the specified components ( <a href="#">see page 154</a> ). |
| <code>-dir</code>                 | Specifies where to generate file output ( <a href="#">see page 158</a> ).                                              |

**Table 5:** *Optional switches to `cpp_poa_genie.tcl`*

| Option                       | Description                                                                                   |
|------------------------------|-----------------------------------------------------------------------------------------------|
| <code>-include</code>        | Specifies to generate code for included files (see <a href="#">page 143</a> ).                |
| <code>-interface-spec</code> | Specifies to generate code only for the specified interfaces (see <a href="#">page 142</a> ). |
| <code>-v/s</code>            | Controls the level of verbosity (see <a href="#">page 158</a> ).                              |

## Specifying Application Components

The `-all` argument generates the files that implement all application components: server, servant, client, and makefile. For example, the following command generates all the files required for an application that is based on `bankdemo.idl`:

```
> idlgen cpp_poa_genie.tcl -all bankdemo.idl

bankdemo.idl:
idlgen: creating BankDem_o_BankIn.plh
idlgen: creating BankDem_o_BankIn.plcxx
idlgen: creating BankDem_o_AccountIn.plh
idlgen: creating BankDem_o_AccountIn.plcxx
idlgen: creating server.cxx
idlgen: creating client.cxx
idlgen: creating call_funcs.h
idlgen: creating call_funcs.cxx
idlgen: creating it_print_funcs.h
idlgen: creating it_print_funcs.cxx
idlgen: creating it_random_funcs.h
idlgen: creating it_random_funcs.cxx
idlgen: creating Makefile
```

Alternatively, you can use `cpp_poa_genie.tcl` to generate one or more application components. For example, the following command specifies to generate only those files that are required to implement a servant:

```
> idlgen cpp_poa_genie.tcl -servant bankdemo.idl

bankdemo.idl:
idlgen: creating BankDem_o_BankIn.plh
idlgen: creating BankDem_o_BankIn.plcxx
idlgen: creating BankDem_o_AccountIn.plh
idlgen: creating BankDem_o_AccountIn.plcxx
idlgen: creating it_print_funcs.h
idlgen: creating it_print_funcs.cxx
idlgen: creating it_random_funcs.h
idlgen: creating it_random_funcs.cxx
```

By generating output for application components selectively, you can control genie processing for each one. For example, the following commands specify different `-dir` options, so that server and servant files are output to one directory, and client files are output to another:

```
> idlgen cpp_poa_genie.tcl -servant - server bankdemo.idl
-dir c:\app\server
> idlgen cpp_poa_genie.tcl -client bankdemo.idl -dir
c:\app\client
```

## Selecting Interfaces

By default, `cpp_poa_genie.tcl` generates code for all interfaces in the specified IDL file. You can specify to generate code for specific interfaces within the file by supplying their fully scoped names. For example, the following command specifies to generate code for the `Bank` interface in `bankdemo.idl`:

```
> idlgen cpp_poa_genie.tcl -all BankDemo::Bank bankdemo.idl
```

You can also use wildcard patterns to specify the interfaces to process. For example, the following command generates code for all interfaces in module `BankDemo`:

```
> idlgen cpp_poa_genie.tcl BankDemo::* bankdemo.idl
```

The following command generates code for all interfaces in `foo.idl` with names that begin with `Foo` or end with `Bar`:

```
> idlgen cpp_poa_genie.tcl foo.idl "Foo*" "*Bar"
```

**Note:** For interfaces defined inside modules, the wildcard is matched against the fully scoped interface name, so `Foo*` matches `FooModule::Y` but not `BarModule::Foo`.

Pattern matching is performed according to the rules of the TCL `string match` command, which is similar to Unix or Windows filename matching.

[Table 6](#) contains some common wildcard patterns:

**Table 6:** *Wildcard pattern matching to interface names*

| Wildcard pattern | Matches...           |
|------------------|----------------------|
| *                | Any string           |
| ?                | Any single character |
| [xyz]            | x, y, or z           |

---

## Including Files

By default, `cpp_poa_genie.tcl` generates code only for the specified IDL files. You can specify also to generate code for all `# include` files by supplying the `-include` option. For example, the following command specifies to generate code from `bankdemo.idl` and any IDL files that are included in it:

```
> idlgen cpp_poa_genie.tcl -all -include bankdemo.idl
```

The default for this option is set in the configuration file through `default_cpp_poa_genie_want_include`.

## Implementing Servants

The `-servant` option generates POA servant classes that implement IDL interfaces. For example, this command generates a class header and implementation code for each interface that appears in IDL file

```
bankdem.o.idl
```

```
idlgen -app_poa_genie.tcl -servant bankdem.o.idl
```

The genie constructs the implementation class name from the scoped name of the interface, replacing double colons (`::`) with an underscore (`_`) and adding a suffix—by default, `_impl`. The default suffix is set in the configuration file through `default_app_impl_class_suffix`.

For example, `BankDem o:Account` is implemented by class `BankDem o_Account_impl`. The generated implementation class contains these components:

- A static `_create()` member method to create a servant.
- A member method to implement each IDL operation for the interface.

The `-servant` option can take one or more arguments, shown in [Table 7](#), that let you control how servant classes are generated:

**Table 7:** *Arguments that control servant generation*

| Argument                                         | Purpose                                                                                                           |
|--------------------------------------------------|-------------------------------------------------------------------------------------------------------------------|
| <code>-tie</code><br><code>-notie</code>         | Choose the inheritance or tie (delegation) method for implementing servants.                                      |
| <code>-inherit</code><br><code>-noinherit</code> | Choose whether implementation classes follow the same inheritance hierarchy as the IDL interfaces they implement. |

**Table 7:** Arguments that control servant generation

| Argument                                           | Purpose                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|----------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>-default_poa_arg</code>                      | <p>Determines the behavior of implicit activation, which uses the default POA associated with a given servant. <code>default_poa</code> can take one of these arguments:</p> <ul style="list-style-type: none"> <li><code>per_servant</code>: Set the correct default POA for each servant.</li> <li><code>exception</code>: Throw an exception on all attempts at implicit activation.</li> </ul> <p>For more information, <a href="#">see page 306</a>.</p> |
| <code>-refcount</code><br><code>-norefcount</code> | Choose whether or not servants are reference counted.                                                                                                                                                                                                                                                                                                                                                                                                         |

The actual content and behavior of member methods is determined by the `-complete` or `-incomplete` flag. For more information, see [“Controlling Code Completeness” on page 154](#).

**-tie/-notie**

A POA servant is either an instance of a class that inherits from a POA skeleton, or an instance of a tie template class that delegates to a separate implementation class. You can choose the desired approach by supplying `-tie` or `-notie` options. The default for this option is set in the configuration file through `default.cpp_poa_genie.want_tie`.

With `-notie`, the genie generates servants that inherit directly from POA skeletons. For example:

```
class BankDem_o_AccountInpl : public virtual POA_BankDem_o_Account
```

The `_create()` method constructs a servant as follows:

```
POA_BankDem_o_Account*
BankDem_o_AccountInpl::_create(PortableServer::POA_ptr the_poa)
{
 return new BankDem_o_AccountInpl(the_poa);
}
```

With `-tie`, the genie generates implementation classes that do not inherit from POA skeletons. The following example uses a `_create` method to create an implementation object (1), and a tie (2) that delegates to it:

```
POA_BankDem o:Account*
BankDem o_AccountIn pl:: create(PortableServer:POA_ptr the_poa)
{
1 BankDem o_AccountIn pl* tied_object =
 new BankDem o_AccountIn pl();
2 POA_BankDem o:Account* the_tie =
 new POA_BankDem o_Account_tie< BankDem o_AccountIn pl> (
 tied_object,
 the_poa
);
 return the_tie;
}
```

---

### **-inherit/-noinherit**

IDL servant implementation classes typically have the same inheritance hierarchy as the interfaces that they implement, but this is not required.

- `-inherit` generates implementation classes with the same inheritance as the corresponding interfaces.
- `-noinherit` generates implementation classes that do not inherit from each other. Instead, each implementation class independently implements all operations for its IDL interface, including operations that are inherited from other IDL interfaces.

The default for this option is set in the configuration file through `defaultcpp_poa_genie_want_inherit`.

---

### **-default\_poa**

In the standard CORBA C++ mapping, each servant class provides a `_this()` method, which generates an object reference and implicitly activates that object with the servant. Implicit activation calls `_default_POA()` on the same servant to determine the POA in which this object is activated. Unless you specify otherwise, `_default_POA()` returns the root POA, which is typically not the POA where you want to activate objects.

The code that `cpp_poa_genie.tcl` generates always overrides `_default_POA()` in a way that prevents implicit activation. Applications generated by this genie can only activate objects explicitly. Two options are available that determine how to override `_default_POA()`:

- `per_servant` (default) Servant constructors and generated `_create()` methods takes a POA parameter. For each servant, `_default_POA()` returns the POA specified when the servant was created.
- `exception`: `_default_POA()` throws a `CORBA::INTERNAL` system exception. This option is useful in a group development environment, in that it allows tests to easily catch any attempts at implicit activation.

For more information about explicit and implicit activation, [see page 305](#).

### **-refcount/-norefcount**

Multi-threaded servers need to reference-count their servants in order to avoid destroying a servant on one thread that is still in use on another. The POA specification provides the standard functions `_add_ref()` and `_remove_ref()` to support reference counting, but by default they do nothing.

- `-refcount` generates servants that inherit from the standard class `PortableServer::RefCountServantBase`, which enables reference counting. For example:

```
class BankDemo_AccountImpl
:public virtual POA_BankDemo::Account,
public virtual PortableServer::RefCountServantBase
```

- `-norefcount` specifies that servants do not inherit from `RefCountServantBase`.

The `-refcount` option is automatically enabled if you use the `-threads` option ([see page 149](#)).

The default for this option is set in the configuration file through `default.cpp_poa_genie_want_refcount`.

**Note:** `-refcount` is invalid with `-tie`. The genie issues a warning if you combine these options. Tie templates as defined in the POA standard do not support reference counting, and the genie cannot change their inheritance. It is recommended that you do not use the tie approach for multi-threaded servers.

## Implementing the Server Mainline

The `-server` option generates a simple server mainline that activates and exports some objects. For example, the following command generates a file called `serverxxx` that contains a `main` program:

```
> idlgen cpp_poa_genie.tcl -server bankdemo.idl
```

The server program performs the following steps:

1. Initializes the ORB and POA.
2. Installs a signal handler to shut down gracefully if the server is killed via SIGTERM on Unix or a CTRL-C event on Windows.
3. For each interface:
  - ◆ Activates a CORBA object of that interface.
  - ◆ Exports a reference either to the naming service or to a file, depending on whether you set the option `-ns` or `-nns`.
4. Catches any exceptions and print a message.

The `-server` option can take one or more arguments, shown in [Table 8](#), that let you modify server behavior:

**Table 8:** *Options affecting the server*

| Command line option                              | Purpose                                                                                                                         |
|--------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------|
| <code>-threads</code><br><code>-nothreads</code> | Choose a single or multi-threaded server. The <code>-threads</code> argument also implies <code>-recount</code> (see page 147). |
| <code>-strategy simple</code>                    | Create servants during start-up.                                                                                                |
| <code>-strategy activator</code>                 | Create servants on demand with a servant activator.                                                                             |
| <code>-strategy locator</code>                   | Create servants per call with a servant locator.                                                                                |
| <code>-strategy default_servant</code>           | For each interface, generate a POA that uses a default servant.                                                                 |

**Table 8:** *Options affecting the server*

| Command line option                    | Purpose                                                                                                                                                                                                                                |
|----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>-ns</code><br><code>-nons</code> | Determines how to export object references: <ul style="list-style-type: none"> <li>• <code>-ns</code> use the naming service to publish object references.</li> <li>• <code>-nons</code> write object references to a file.</li> </ul> |

**-threads/-nothreads**

You can specify the threads policy for all POAs in the server with one of these options:

**-nothreads** sets the `SINGLE_THREAD_MODEL` policy on all POAs in the server, which ensures that all calls to application code are made in the main thread. This policy allows a server to run thread-unsafe code, but might reduce performance because the ORB can dispatch only one operation at a time.

`-threads` sets the `ORB_CTRL_MODEL` policy on all POAs in the server, allowing the ORB to dispatch incoming calls in multiple threads concurrently.

**Note:** If you enable multi-threading, you must ensure that your application code is thread-safe and application data structures are adequately protected by thread-synchronization calls.

The default for this option is set in the configuration file through `default.cpp_poa_genie.want_threads`.

**-strategy Options**

The POA is a flexible tool that lets servers manage objects with different strategies. Some servers can use a combination of strategies for different objects. You can use the genie to generate examples of each strategy, then cut-and-paste the appropriate generated code into your own server.

You set a server's object management strategy through one of the following arguments to the `-strategy` option:

**-strategy simple:** The server creates a POA with a policy of `USE_ACTIVE_OBJECT_MAP_ONLY` (see [page 296](#)). For each interface in the IDL file, the server `main()` creates a servant, activates it with the POA as a CORBA object, and exports an object reference. After the ORB is shut down, `main()` deletes the servants.

This strategy is appropriate for servers that implement a small, fixed set of objects.

**-strategy activator:** The server creates a POA and a servant activator (see “[Servant Activators](#)” on [page 329](#)). For each interface, the server exports an object reference. The object remains inactive until a client first calls on its reference; then, the servant activator is invoked and creates the appropriate servant, which remains in memory to handle future calls on that reference. The servant activator deletes the servants when the POA is destroyed.

This strategy lets the server start receiving requests immediately and defer creation of servants until they are needed. It is useful for servers that normally activate just a few objects out of a large collection on each run, or for servants that take a long time to initialize.

**-strategy locator:** The server creates a POA and a servant locator (see “[Servant Locators](#)” on [page 335](#)). The server exports references, but all objects are initially inactive. For every incoming operation, the POA asks the servant locator to select an appropriate servant. The generated servant locator creates a servant for each incoming operation, and deletes it when the operation is complete.

A servant locator is ideal for managing a cache of servants from a very large collection of objects in a database. You can replace the `preinvoke` and `postinvoke` methods in the generated locator with code that looks for servants in a database cache, loads them into the cache if required, and deletes old servants when the cache is full.

**-strategy default\_servant:** The server creates a POA for each interface, and defines a default servant for each POA to handle incoming requests. A server that manages requests for many objects that all use the same interface should probably have a POA that maps all these requests to the same default servant. For more information about using default servants, see “[Setting a Default Servant](#)” on [page 343](#).

**-ns/-nons**

---

Determines how the server exports object references to the application:

**-ns:** Use the naming service to publish object references. For each interface, the server binds a reference that uses the interface name, in naming context `II_GenieDem o`. For example, for interface `Dem o_Bank`, the genie binds the reference `II_GenieDem oBankDem o_Bank`. If you use this option, the naming service and locator daemon must be running when you start the server.

For more information about the naming service, see [Chapter 18 on page 485](#).

**-nons:** Write stringified object references to a file. For each interface, the server exports a reference to a file named after the interface with the suffix `.ref`—for example `BankDem o_Bank.ref`

The default for this option is set in the configuration file through `default.cpp_poa_genie`.

---

## Implementing a Client

The `-client` option generates client source code in `client.cpp`. For example:

```
> idlgen cpp_poa_genie.tcl -client bank.idl
```

When you run this client, it performs the following actions for each interface:

1. Reads an object reference from the file generated by the server—for example, `BankDem.o_Bank.ref`.
2. If generated with the `-complete` option, for each operation:
  - ◆ Calls the operation and passes random values.
  - ◆ Prints out the results.
3. Catches raised exceptions and prints an appropriate message.

---

## Generating a Makefile

The `-makefile` option generates a makefile that can build the server and client applications. The makefile provides the following targets

- `all`: Compile and link the client and server.
- `clean`: Delete files created during compile and link.
- `clean_all`: Like `clean`, it also deletes all the source files generated by `idlgcn`, including the makefile itself.

To build the client and server, enter `rmake` (Windows) or `make` (UNIX).

---

## Controlling Code Completeness

You can control the extent of the code that is generated for each interface through the `-complete` and `-incomplete` options. These options are valid for server, servant, and client code generation.

The default for this option is set in the configuration file through `default_cpp_poa_genie_want_complete`.

For example, the following commands generate complete servant and client code and incomplete server mainline code:

```
> idlgen cpp_poa_genie.tcl -servant -complete bankdemo.idl
> idlgen cpp_poa_genie.tcl -client -complete bankdemo.idl
> idlgen cpp_poa_genie.tcl -server -incomplete bankdemo.idl
```

Setting the `-complete` option on servant, server, and client components yields a complete application that you can compile and run. The application performs these tasks:

- The client application calls every operation in the server application and passes random values as `in` parameters.
- The server application returns random values for `inout/out` parameters and `return` values.
- Client and server print a message for each operation call, which includes the values passed and returned.

Using the `-complete` option lets you quickly produce a demo or proof-of-concept prototype. It also offers useful models for typical coding tasks, showing how to initialize parameters properly, invoke operations, throw and catch exceptions, and perform memory management.

If you are familiar with calling and parameter passing rules and simply want a starting point for your application, you probably want to use the `-incomplete` option. This option produces minimal code, omitting the bodies of operations, attributes, and client-side invocations.

The sections that follow describe, for each application component, the differences between complete and incomplete code generation. All examples assume the following IDL for interface Account:

```
//IDL:
module BankDemo
{
 //Other interfaces and type definitions omitted...
 interface Account
 {
 exception InsufficientFunds {};
 readonly attribute AccountId account_id;
 readonly attribute CashAmount balance;
 void withdraw (
 in CashAmount amount
) raises (InsufficientFunds);

 void
 deposit(
 in CashAmount amount
);
 };
}
```

## Servant code

Qualifying the `-servant` option with `-incomplete` or `-complete` yields the required source files for each IDL interface. Either option generate the following files for interface Account:

```
BankDemo_Accountimpl.h
BankDemo_Accountimpl.cpp
```

### Incomplete servant

The `-incomplete` option specifies to generate servant class

`BankDemo_Accountimpl`, which implements the `BankDemo::Account` interface. The implementation of each operation and attribute throws a `CORBA::NO_IMPLEMENT` exception.

For example, the following code is generated for the `deposit()` operation:

```
void
BankDemo_Accountimpl::deposit(
 BankDemo::CashAmount amount
) throw (
 CORBA::SystemException
)
{
```

```

 throw CORBA::NO_IMPLEMENT();
 }

```

All essential elements of IDL code are automatically generated, so you can focus on writing the application logic for each IDL operation.

### Complete servant

The `-complete` option specifies to generate several files that provide the functionality required to generate random values for parameter passing, and to print those values:

```

it_print_funcs.h
it_print_funcs.cpp
it_random_funcs.h
it_random_funcs.cpp

```

Member methods are fully implemented to print parameter values and, if required, return a value to the client. For example, the following code is generated for the `deposit()` operation:

```

void
BankDem o_AccountImpl::deposit(
 BankDem o_CashAmount amount)
{
 throw (
 CORBA::SystemException
)
}
{
 //Diagnostics: print the values of "in" and "hout"
 parameters
 cout << "BankDem o_AccountImpl::deposit(): "
 << "talked with..."
 << endl;
 cout << "amount = ";
 IT_print_BankDem o_CashAmount(cout, amount, 3);
 cout << endl;

 //Diagnostics.
 cout << "BankDem o_AccountImpl::deposit(): returning"
 << endl;
}

```

### Client Code

In a completely implemented client, `app_poa_genie.tcl` generates the client source file `call_funcs.cpp`, which contains method calls that invoke on all operation and attributes of each object. Each method assigns random values to the parameters of operations and prints out the values of parameters that

they send, and those that are received back as `out` parameters. Utility methods to assign random values to IDL types are generated in the file `it_random_funcs.cxx`, and utility methods to print the values of IDL types are generated in the file `it_print_funcs.cxx`.

An incomplete client contains no invocations.

Both complete and incomplete clients catch raised exceptions and print appropriate messages.

## General Options

You can supply switches that control `cpp_poa_genie.tcl` genie output:

**-dir:** By default, `cpp_poa_genie.tcl` writes all output files to the current directory. With the `-dir` option, you can explicitly specify where to generate file output.

**-v/-s:** By default, `cpp_poa_genie.tcl` runs in verbose (`-v`) mode. With the `-s` option, you can silence all messaging.

---

## Compiling the Application

To compile a genie-generated application, Orbix must be properly installed on the client and server hosts:

1. Build the application using the makefile.
2. In separate windows, run first the server, then the client applications.

## Generating Signatures of Individual Operations

IDL interfaces sometimes change during development. A new operation might be added to an interface, or the signature of an existing operation might change. When such a change occurs, you must update existing C++ code with the signatures of the new or modified operations. You can avoid much of this work with the `cpp_poa_op.tcl` genie. This genie prints the C++ signatures of specified operations and attributes to a file. You can then paste these operations back into the application source files.

For example, you might add a new operation `close()` to interface `BankDemo::Account`. To generate the new operation, run the `cpp_poa_op.tcl` genie:

```
> idlgen cpp_poa_op.tcl bankdemo.idl "::*:close"
```

```
idlgen: creating tmp
Generating signatures for BankDemo::Account::close
```

As in this example, you can use wildcards to specify the names of operations or attributes. If you do not explicitly specify any operations or attributes, the genie generates signatures for all operations and attributes.

By default, wild cards are matched only against names of operations and attributes in the specified IDL file. If you specify the `-include` option, wildcards are also matched against all operations and attributes in the included IDL files.

By default, `cpp_poa_op.tcl` writes generated operations to file `tmp`. You can specify a different file name with the `-o` command-line option:

```
> idlgen cpp_poa_op.tcl bankdemo.idl -o ops.txt "::*:close"
```

```
bankdemo.idl:
idlgen: creating ops.txt
Generating signatures for BankDemo::Account::close
```

---

# Configuration Settings

The configuration file `idgen.cfg` contains default settings for the C++ genie `app_poa_genie.tcl` at the scope `defaultapp_poa_genie`.

Some other settings are not specific to `app_poa_genie.tcl` but are used by the `std/app_poa_boa_ib.tcl` library, which maps IDL constructs to their C++ equivalents. `app_poa_genie.tcl` uses this library extensively, so these settings affect the output that it generates. They are held in the scope `defaultapp`.

For a full listing of these settings, refer to the *CORBA Code Generation Toolkit Guide*.



# ORB Initialization and Shutdown

*The mechanisms for initializing and shutting down the ORB on a client and a server are the same.*

---

## Overview

The `main()` of both sever and client must perform these steps:

- Initialize the ORB by calling `CORBA::ORB_init()`.
- Shut down and destroy the ORB, by calling `shutdown()` and `destroy()` on the ORB.

Orbix also provides its own `IT_TerminationHandler` class, which enables applications to handle delivery of `CtdC` and similar events in a portable manner. For more information, see [“Termination Handler” on page 280](#).

---

## In this chapter

This chapter contains the following sections:

|                                              |                          |
|----------------------------------------------|--------------------------|
| <a href="#">Initializing the ORB Runtime</a> | <a href="#">page 164</a> |
| <a href="#">Shutting Down the ORB</a>        | <a href="#">page 166</a> |

---

# Initializing the ORB Runtime

---

## Overview

Before an application can start any CORBA-related activity, it must initialize the ORB runtime by calling `ORB_init()`. `ORB_init()` returns an object reference to the ORB object; this, in turn, lets the client obtain references to other CORBA objects, and make other CORBA-related calls.

---

## Calling within main()

It is common practice to set a global variable with the ORB reference, so the ORB object is accessible to most parts of the code. However, you should call `ORB_init()` only after you call `main()` to ensure access to command line arguments. `ORB_init()` scans its arguments parameter for command-line options that start with `-ORB` and removes them. The arguments that remain can be assumed to be application-specific.

---

## Supplying an ORB name

You can supply an ORB name as an argument; this name determines the configuration information that the ORB uses. If you supply null, Orbix uses the ORB identifier as the default ORB name. ORB names and configuration are discussed in the *Application Server Platform Administrator's Guide*.

---

## C++ mapping

`ORB_init()` is defined as follows:

```
namespace CORBA {

// ...
ORB_ptr ORB_init(
 int& argc,
 char** aargv,
 const char* orb_identifier= ""
);
// ...
}
```

`ORB_init()` expects a reference to `argc` and a non-constant pointer to `aargv`. `ORB_init()` scans the passed argument vector for command-line options that start with `-ORB` and removes them.

---

**Registering portable interceptors**

During ORB initialization, portable interceptors are instantiated and registered through an ORB initializer. The client and server applications must register the ORB initializer before calling `ORB_init()`. For more information, see [“Registering Portable Interceptors” on page 684](#).

---

# Shutting Down the ORB

## Overview

For maximum portability and to ensure against resource leaks, a client or server must always shut down and destroy the ORB at the end of `main()`:

- `shutdown()` stops all server processing, deactivates all POA managers, destroys all POAs, and causes the `run()` loop to terminate. `shutdown()` takes a single Boolean argument; if set to true, the call blocks until the shutdown process completes before it returns control to the caller. If set to false, a background thread is created to handle shutdown, and the call returns immediately.
- `destroy()` destroys the ORB object and reclaims all resources associated with it.

## In this section

This section discusses the following topics:

|                                        |                          |
|----------------------------------------|--------------------------|
| <a href="#">Shutting Down a Client</a> | <a href="#">page 167</a> |
| <a href="#">Shutting down a server</a> | <a href="#">page 168</a> |

## Shutting Down a Client

A client is a CORBA application that does not call `CORBA::ORB::run()` and does not process incoming CORBA invocations.

[Example 1](#) shows how a client is shut down:

**Example 1:** *Shutting down a CORBA client*

```

//C++
int main(int argc, char* argv[])
{
 CORBA::ORB_var orb;
 try
 {
 //ORB initialization not shown
 ...
 ...
1 //SHUTDOWN
2 orb->shutdown(1);
 orb->destroy();
 return 0;
 }
 catch (const CORBA::Exception& e)
 {
 cout << "Exception occurred: " << e << endl;
 return 1;
 }
}

```

1. A client calls `shutdown()` with the argument `1(TRUE)`, causing the `shutdown()` operation to remain blocked until ORB shutdown is complete.
2. The last thing the client does is to call `destroy()`. You are required to call `destroy()` for full CORBA compliancy. However, the `destroy()` operation is not required when using working with Orbix.

## Shutting down a server

### Overview

Because servers typically process invocations by calling `CORBA::ORB::run()`, which blocks indefinitely, `CORBA::ORB::shutdown()` cannot be called from the main thread. The following are the main ways of shutting down a server:

- Call `shutdown(0)` from a signal handler.
- Call `shutdown(0)` from a subthread.
- Call `shutdown(0)` in the context of an operation invocation.

### Using a signal handler

[Example 2](#) illustrates shutting down a CORBA server using a signal handler:

#### Example 2: Shutting down a server from a signal handler

```
//C++
CORBA::ORB_var gbbal_orb;

void termination_handler_callback(long sig_type)
{
 if (CORBA::is_nil(gbbal_orb))
 {
 cout << "Shutting down ORB." << endl;
 gbbal_orb->shutdown(0);
 }
 else
 {
 cout << "ORB not initialised, aborting." << endl;
 abort();
 }
}

int main(int argc, char* argv[])
{
 IT_TerminationHandler
 term_termination_handler(termination_handler_callback);

 gbbal_orb = CORBA::ORB_init(argc, argv);
 ...
 ...
 gbbal_orb->run();
 gbbal_orb->destroy();
 return 0;
}
```

In this example, `CORBA::ORB::shutdown()` is called with a `0` (`FALSE`) argument from a signal handler. The `shutdown()` operation is *not* called at the end of `main()`.

**Note:** Pay attention to the value of the flag passed to `shutdown()`. You can easily cause deadlock in a server by calling `shutdown(1)` which forces `shutdown()` to block until the ORB shutdown is complete. In a server, `shutdown(0)`, which returns immediately, is the appropriate form.

See [“Create a Termination Handler Object” on page 75](#) for a detailed description of the shutdown procedure for a server that uses a signal handler.



# Using Policies

*Orbix supports a number of CORBA and proprietary policies that control the behavior of application components.*

Most policies are locality-constrained; that is, they apply only to the server or client on which they are set. Therefore, policies can generally be divided into server-side and client-side policies:

- Server-side policies generally apply to the processing of requests on object implementations. Server-side policies can be set programmatically and in the configuration, and applied to the server's ORB and its POAs.
- client-side policies apply to invocations that are made from the client process on an object reference. Client-side policies can be set programmatically and in the configuration, and applied to the client's ORB, to a thread, and to an object reference.

The procedure for setting policies programmatically is the same for both client and server:

1. Create the `CORBA:Policy` object for the desired policy.
2. Add the `Policy` object to a `PolicyList`.
3. Apply the `PolicyList` to the appropriate target—ORB, POA, thread, or object reference.

---

## In this chapter

This chapter discusses issues that are common to all client and server policies.

|                                                 |                          |
|-------------------------------------------------|--------------------------|
| <a href="#">Setting Orb and Thread Policies</a> | <a href="#">page 175</a> |
| <a href="#">Setting Server-Side Policies</a>    | <a href="#">page 178</a> |
| <a href="#">Setting Client Policies</a>         | <a href="#">page 180</a> |
| <a href="#">Getting Policies</a>                | <a href="#">page 185</a> |

For detailed information about specific policies, refer to the chapters that cover client and POA development: [“Developing a Client” on page 187](#), and [“Managing Server Objects” on page 283](#).

---

# Creating Policy and PolicyList Objects

Two methods are generally available to create policy objects:

- To apply policies to a POA, [use the appropriate policy factory](#) from the `PortableServer:POA` interface.
- Call `ORB::create_policy()` on the ORB.

After you create the required policy objects, you add them to a `PolicyList`. The `PolicyList` is then applied to the desired application component.

---

## Using POA policy factories

The `PortableServer:POA` interface provides factories for creating `CORBA:Policy` objects that apply only to a POA (see [Table 12 on page 290](#)). For example, the following code uses POA factories to create policy objects that specify `PERSISTENT` and `USER_ID` policies for a POA, and adds these policies to a `PolicyList`.

```
CORBA::PolicyList policies;
policies.length (2);

//Use rootPOA to create POA policies
policies[0] = poa-> create_lifespan_policy
(PortableServer:PERSISTENT)
policies[1] = poa-> create_id_assignment_policy
(PortableServer:USER_ID)
```

Orbis also provides several proprietary policies to control POA behavior (see [page 173](#)). These policies require you to call `create_policy()` on the ORB to create `Policy` objects, as described in the next section.

---

## Calling create\_policy()

You call `create_policy()` on the ORB to create `Policy` objects. For example, the following code creates a `PolicyList` that sets a `SyncScope` policy of `SYNC_WITH_SERVER`; you can then use this `PolicyList` to set client policy overrides at the ORB, thread, or object scope:

```
include <omg/Message.h> ;
// ...
CORBA::PolicyList policies(1);
policies.length(1);
CORBA::Any policy_value;
policy_any < < = Messaging::SYNC_WITH_SERVER;

policies[0] = orb->create_policy(
 Messaging::SYNC_SCOPE_POLICY_TYPE, policy_value);
```

---

# Setting Orb and Thread Policies

The `CORBA::PolicyManager` interface provides the operations that a program requires to access and set ORB policies. `CORBA::PolicyCurrent` is an empty interface that simply inherits all `PolicyManager` operations; it provides access to client-side policies at the thread scope.

ORB policies override system defaults, while thread policies override policies set on a system or ORB level. You obtain a `PolicyManager` or `PolicyCurrent` through `resolve_initial_references()`:

- `resolve_initial_references("ORBPolicyManager")` returns the ORB's `PolicyManager`. Both server- and client-side policies can be applied at the ORB level.
- `resolve_initial_references("PolicyCurrent")` returns a thread's `PolicyCurrent`. Only client-side policies can be applied to a thread.

The CORBA module contains the following interface definitions and related definitions to manage ORB and thread policies:

```
module CORBA {
 // ...

 enum SetOverrideType
 {
 SET_OVERRIDE,
 ADD_OVERRIDE
 };

 exception InvalidPolicies
 {
 sequence< unsigned short> indices;
 };
};
```

```

interface PolicyManager {
 PolicyList
 get_policy_overrides(in PolicyTypeSeq ts);

 void
 set_policy_overrides(
 in PolicyList policies,
 in SetOverrideType set_add
) raises (InvalidPolicies);
};

interface PolicyCurrent : PolicyManager, Current
{
};
// ...
}

```

**set\_policy\_overrides()** overrides policies of the same `PolicyType` that are set at a higher scope. The operation takes two arguments:

- A `PolicyList` sequence of `Policy` object references that specify the policy overrides.
- An argument of type `SetOverrideType`:  
`ADD_OVERRIDE` adds these policies to the policies already in effect.  
`SET_OVERRIDE` removes all previous policy overrides and establishes the specified policies as the only override policies in effect at the given scope.

`set_policy_overrides()` returns a new proxy that has the specified policies in effect; the original proxy remains unchanged.

To remove all overrides, supply an empty `PolicyList` and `SET_OVERRIDE` as arguments.

**get\_policy\_overrides()** returns a `PolicyList` of object-level overrides that are in effect for the specified `PolicyTypes`. The operation takes a single argument, a `PolicyTypeSeq` that specifies the `PolicyTypes` to query. If the `PolicyTypeSeq` argument is empty, the operation returns with all overrides for the given scope. If no overrides are in effect for the specified `PolicyTypes`, the operation returns an empty `PolicyList`.

After `get_policy_overrides()` returns a `PolicyList`, you can iterate through the individual `Policy` objects and obtain the actual setting in each one by narrowing it to the appropriate derivation (see [“Getting Policies” on page 185](#)).

---

## Setting Server-Side Policies

Orbix provides a set of default policies that are effective if no policy is explicitly set in the configuration or programmatically. You can explicitly set server policies at three scopes, listed in ascending order of precedence:

1. In the configuration, so they apply to all ORBs that are in the scope of a given policy setting. For a complete list of policies that you can set in the configuration, refer to the *Application Server Platform Administrator's Guide*.
2. On the server's ORB, so they apply to all POAs that derive from that ORB's root POA. The ORB has a `PolicyManager` with operations that let you access and set policies on the server ORB (see [“Setting Orb and Thread Policies” on page 175](#)).
3. On individual POAs, so they apply only to requests that are processed by that POA. Each POA can have its own set of policies (see [“Using POA Policies” on page 294](#)).

You can set policies in any combination at all scopes. If settings are found for the same policy type at more than one scope, the policy at the lowest scope prevails.

Most server-side policies are POA-specific. POA policies are typically attached to a POA when it is created, by supplying a PolicyList object as an argument to `create_POA()`. The following code creates POA `persistentPOA` as a child of the root POA, and attaches a PolicyList to it:

```
//get an object reference to the root POA
CORBA::Object_var obj =
 orb->resolve_initial_references("RootPOA");
PortableServer::POA_var poa = POA::narrow(obj);

//create policy object
CORBA::PolicyList policies;
policies.length(2);

//set policy object with desired policies
policies[0] = poa->create_lifespan_policy
 (PortableServer::PERSISTENT);
policies[1] = poa->create_id_assignment_policy
 (PortableServer::USER_ID);

//create a POA for persistent objects
poa = poa->create_POA("persistentPOA", NULL, policies);
```

In general, you use different sets of policies in order to differentiate among various POAs within the same server process, where each POA is defined in a way that best accommodates the needs of the objects that it processes. So, a server process that contains the POA `persistentPOA` might also contain a POA that supports only transient object references, and only handles requests for callback objects.

For more information about using POA policies, [see page 294](#).

---

## Setting Client Policies

Orbix provides a set of default policies that are effective if no policy is explicitly set in the configuration or programmatically. Client policies can be set at four scopes, listed here in ascending order of precedence:

1. In the configuration, so they apply to all ORBs that are in the scope of a given policy setting. For a complete list of policies that you can set in the configuration, refer to the *Application Server Platform Administrator's Guide*.
2. On the client's ORB, so they apply to all invocations. The ORB has a `PolicyManager` with operations that let you access and set policies on the client ORB (see [“Setting Orb and Thread Policies” on page 175](#)).
3. On a given thread, so they apply only to invocations on that thread. Each client thread has a `PolicyCurrent` with operations that let you access and set policies on that thread (see [page 175](#)).
4. On individual object references, so they apply only to invocations on those objects. Each object reference can have its own set of policies; the `Object` interface provides operations that let you access and set an object reference's quality of service policies (see [“Managing Object Reference Policies” on page 182](#)).

---

## Setting Policies at Different Scopes

You can set policies in any combination at all scopes. If settings are found for the same policy type at more than one scope, the policy at the lowest scope prevails.

For example, the `SyncScope` policy type determines how quickly a client resumes processing after sending one-way requests. The default `SyncScope` policy is `SYNC_NONE`: Orbix clients resume processing immediately after sending one-way requests.

You can set this policy differently on the client's ORB, threads, and individual object references. For example, you might leave the default `SyncScope` policy unchanged at the ORB scope, set a thread to `SYNC_W_IH_SERVER`; and set certain objects within that thread to `SYNC_W_IH_TARGET`. Given these quality of service settings, the client blocks on one-way invocations as follows:

- Outside the thread, the client never blocks.
- Within the thread, the client always blocks until it knows whether the invocations reached the server.
- For all objects within the thread that have `SYNC_W_IH_TARGET` policies, the client blocks until the request is fully processed.

## Managing Object Reference Policies

The `CORBA::Object` interface contains the following operations to manage object policies:

```
interface Object {
 // ...
 Policy
 get_client_policy(in PolicyType type);

 Policy
 get_policy(in PolicyType type);

 PolicyList
 get_policy_overrides(in PolicyTypeSeq ts);

 Object
 set_policy_overrides(
 in PolicyList policies,
 in SetOverrideType set_add
) raises (InvalidPolicies);

 boolean
 validate_connection(out PolicyList inconsistent_policies);
};
```

**get\_client\_policy()** returns the policy override that is in effect for the specified `PolicyType`. This method obtains the effective policy override by checking each scope until it finds a policy setting: first at object scope, then thread scope, and finally ORB scope. If no override is set at any scope, the system default is returned.

**get\_policy()** returns the object's effective policy for the specified `PolicyType`. The effective policy is the intersection of values allowed by the object's effective override—as returned by `get_client_policy()`—and the policy that is set in the object's IOR. If the intersection is empty, the method raises exception `INV_POLICY`. Otherwise, it returns a policy whose value is legally within the intersection. If the IOR has no policy set for the `PolicyType`, the method returns the object-level override.

**get\_policy\_overrides()** returns a `PolicyList` of overrides that are in effect for the specified `PolicyTypes`. The operation takes a single argument, a `PolicyTypeSeq` that specifies the `PolicyTypes` to query. If the `PolicyTypeSeq` argument is empty, the operation returns with all overrides for the given scope. If no overrides are in effect for the specified `PolicyTypes`, the operation returns an empty `PolicyList`.

After `get_policy_overrides()` returns a `PolicyList`, you can iterate through the individual `Policy` objects and obtain the actual setting in each one by narrowing it to the appropriate derivation (see [“Getting Policies” on page 185](#)).

**set\_policy\_overrides()** overrides policies of the same `PolicyType` that are set at a higher scope, and applies them to the new object reference that it returns. The operation takes two arguments:

- A `PolicyList` sequence of `Policy` object references that specify the policy overrides.
- An argument of type `SetOverrideType`:
  - ◆ `ADD_OVERRIDE` adds these policies to the policies already in effect.
  - ◆ `SET_OVERRIDE` removes all previous policy overrides and establishes the specified policies as the only override policies in effect at the given scope.

To remove all overrides, supply an empty `PolicyList` and `SET_OVERRIDE` as arguments.

**validate\_connection()** returns true if the object’s effective policies allow invocations on that object. This method forces rebinding if one of these conditions is true:

- The object reference is not yet bound.
- The object reference is bound but the current policy overrides have changed since the last binding occurred; or the binding is invalid for some other reason.

The method returns false if the object’s effective policies cause invocations to raise the exception `INV_POLICY`. If the current effective policies are incompatible, the output parameter `inconsistent_policies` returns with a `PolicyList` of those policies that are at fault.

If binding fails for a reason that is unrelated to policies, `validate_connections()` raises the appropriate system exception.

A client typically calls `validate_connections()` when its `RebindPolicy` is set to `NO_REBIND`.

# Getting Policies

As shown earlier, `CORBA:PolicyManager`, `CORBA:PolicyCurrent`, and `CORBA:Object` each provide operations that allow programmatic access to the effective policies for an ORB, thread, and object. Accessor operations obtain a `PolicyList` for the given scope. After you get a `PolicyList`, you can iterate over its `Policy` objects. Each `Policy` object has an accessor method that identifies its `PolicyType`. You can then use the `Policy` object's `PolicyType` to narrow to the appropriate type-specific `Policy` derivation—for example, a `SyncScopePolicy` object. Each derived object provides its own accessor method that obtains the policy in effect for that scope.

The Messaging module provides these `PolicyType` definitions:

```
module Messaging
{
 //Messaging Quality of Service

 typedef short RebindMode;

 const RebindMode TRANSPARENT = 0;
 const RebindMode NO_REBIND = 1;
 const RebindMode NO_RECONNECT = 2;

 typedef short SyncScope;

 const SyncScope SYNC_NONE = 0;
 const SyncScope SYNC_W_IH_TRANSPORT = 1;
 const SyncScope SYNC_W_IH_SERVER = 2;
 const SyncScope SYNC_W_IH_TARGET = 3;

 //PolicyType constants

 const CORBA:PolicyType REBIND_POLICY_TYPE = 23;
 const CORBA:PolicyType SYNC_SCOPE_POLICY_TYPE = 24;

 //Locally-Constrained Policy Objects

 //Rebind Policy (default= TRANSPARENT)
 readonly attribute RebindMode rebind_mode;
};
```

```

interface RebindPolicy : CORBA::Policy {
 //Synchronization Policy (default= SYNC_W ITH_TRANSPORT)

 interface SyncScopePolicy : CORBA::Policy {
 readonly attribute SyncScope synchronization;
 };
 ...
}

```

For example, the following code gets the ORB's `SyncScope` policy:

```

#include <omg/Message.h>
...
//get reference to PolicyM anager

CORBA::Object_var object;
object = orb->resolve_initial_references("ORBPolicyM anager");

//narrow
CORBA::PolicyM anager_var policy_m gr =
 CORBA::PolicyM anager::narrow (object);

//set SyncScope policy at ORB scope (not shown)
// ...

//get SyncScope policy at ORB scope
CORBA::PolicyTypeSeq types;
types.length(1);
types[0] = SYNC_SCOPE_POLICY_TYPE;

//get PolicyList from ORB ts PolicyM anager
CORBA::PolicyList_var pList =
 policy_m gr->get_policy_overrides (types);

//evaluate first Policy in PolicyList
Messageing::SyncScopePolicy_var sync_p =
 Messageing::SyncScopePolicy::narrow (pList[0]);

Messageing::SyncScope sync_policy = sync_p->synchronization();

cout << "Effective SyncScope policy at ORB level is "
 << sync_policy << endl;

```

# Developing a Client

*A CORBA client initializes the ORB runtime, handles object references, invokes operations on objects, and handles exceptions that these operations throw.*

---

## In this chapter

This chapter covers the following topics:

|                                                          |
|----------------------------------------------------------|
| <a href="#">Mapping IDL Interfaces to Proxies</a>        |
| <a href="#">Using Object References</a>                  |
| <a href="#">Initializing and Shutting Down the ORB</a>   |
| <a href="#">Invoking Operations and Attributes</a>       |
| <a href="#">Passing Parameters in Client Invocations</a> |
| <a href="#">Client Policies</a>                          |
| <a href="#">Implementing Callback Objects</a>            |

For information about exception handling, see [Chapter 13](#).

---

## Mapping IDL Interfaces to Proxies

When you compile IDL, the compiler maps each IDL interface to a client-side *proxy* class of the same name. Proxy classes implement the client-side call stubs that marshal parameter values and send operation invocations to the correct destination object. When a client invokes on a proxy method that corresponds to an IDL operation, Orbix conveys the call to the corresponding server object, whether remote or local.

The client application accesses proxy methods only through an object reference. When the client brings an object reference into its address space, the client runtime ORB instantiates a proxy to represent the object. In other words, a proxy acts as a local ambassador for the remote object.

For example, interface `Bank::Account` has this IDL definition:

```
module BankDemo
{
 typedef float CashAmount;
 exception InsufficientFunds {};
 // ...
 interface Account{
 void withdraw (in CashAmount amount)
 raises (InsufficientFunds);

 // ...other operations not shown
 };
};
```

Given this IDL, the IDL compiler generates the following proxy class definition for the client implementation:

```

namespace BankDemo
{
 typedef CORBA::Float CashAmount;
 // ...

 class Account : public virtual CORBA::Object
 {
 // ...
 virtual void withdraw (CashAmount amount) = 0;
 }
 // other operations not shown ...
}

```

This proxy class demonstrates several characteristics that are true of all proxy classes:

- Member methods derive their names from the corresponding interface operations—in this case, `withdrawal()`.
- The proxy class inherits from `CORBA::Object`, so the client can access all the inherited functionality of a CORBA object.
- `Account::withdrawal` and all other member methods are defined as pure virtual, so the client code cannot instantiate the `Account` proxy class or any other proxy class. Instead, clients can access the `Account` object only indirectly through object references.

---

## Using Object References

For each IDL interface definition, a POA server can generate and export references to the corresponding object that it implements. To access this object and invoke on its methods, a client must obtain an object reference—generally, from a CORBA naming service. For each generated proxy class, the IDL compiler also generates two other classes: *interface\_var* and *interface\_ptr*, where *interface* is the name of the proxy class. Briefly, *\_ptr* types are unmanaged reference types, while *\_var* types can be characterized as smart pointers.

Both reference types support the indirection operator `->`; when you invoke an operation on a *\_var* or *\_ptr* reference, the corresponding proxy object redirects the C++ call across the network to the appropriate member method of the object's servant.

While *\_ptr* and *\_var* references differ in a number of ways, they both act as handles to the corresponding client proxy. The client code only needs to obtain an object reference and use it to initialize the correct *\_ptr* or *\_var* reference. The underlying proxy code and ORB runtime take all responsibility for ensuring transparent access to the server object.

For example, given the previous IDL, the IDL compiler generates two object reference types to the CORBA object, `Bank::Account Account_ptr` and `Account_var`. You can use either reference type to invoke operations such as `withdrawal()` on the `Bank::Account` object. Thus, the following two invocations are equivalent:

```
// ...
//withdraw_amt is already initialized

//Use a_ptr reference
Account_ptr accp = ...; //get reference...
balance = accp->withdrawal(withdraw_amt);

//Use a_var reference
Account_var accv = ...; //get reference...
balance = accv->withdrawal(withdraw_amt);
```

**Note:** Because `_Ptr` types are not always implemented as actual C++ pointers, you should always use the `_Ptr` definition. Regardless of the underlying mapping, a `_Ptr` type is always guaranteed to behave like a pointer, so it is portable across all platforms and language mappings.


## Counting References

When you initialize a `_var` or `_ptr` reference with an object reference for the first time, the client instantiates a proxy and sets that proxy's reference count to one. Each proxy class has a `_duplicate()` method, which allows a client to create a copy of the target proxy. In practice, this method simply increments the reference count on that proxy and returns a new `_ptr` reference to it. Actual methods for copying `_ptr` and `_var` references differ and are addressed separately in this chapter; conceptually, however, the result is the same.

For example, given an object reference to the `Account` interface, the following client code initializes a `_ptr` reference as follows:

```
Account_ptr accp1 = ...; //get reference somehow
```

This instantiates an `Account` object proxy and automatically sets its reference count to one:




**Figure 8:** Reference count for `Account` proxy is set to one.

The following code copies `accp1` into reference `accp2`, thus incrementing the `Account` proxy's reference count to 2

```
Account_ptr accp2 = Account::_duplicate(accp1);
```

The client now has two initialized `_ptr` references, `accp1` and `accp2`. Both refer to the same proxy, so invocations on either are treated as invocations on the same object.



**Figure 9:** Reference for Account proxy is incremented to 2.

When you release a reference, the reference count of the corresponding proxy is automatically decremented. When the reference count is zero, Orbix deallocates the proxy. You can release references in any order, but you can only release a reference once, and you must not use any reference after it is released.

**Note:** A server object is completely unaware of its corresponding client proxy and its life cycle. Thus, calling `release()` and `_duplicate()` on a proxy reference has no effect on the server object.

## Nil References

Nil references are analogous to C++ null pointers and contain a special value to indicate that the reference points nowhere. Nil references are useful mainly to indicate “not there” or optional semantics. For example, if you have a lookup operation that searches for objects via a key, it can return a nil reference to indicate the “not found” condition instead of raising an exception. Similarly, clients can pass a nil reference to an operation to indicate that no reference was passed for this operation—that is, you can use a nil reference to simulate an optional reference parameter.

You should only use the `CORBA::is_nil()` method to test whether a reference is nil. All other attempts to test for nil have undefined behavior. For example, the following code is not CORBA-compliant and can yield unpredictable results:

```
Object_ptr ref = ...;
if (ref != 0) { //WRONG! Use CORBA::is_nil
 //Use reference...
}
```

You cannot invoke operations on a nil reference. For example, the following code has undefined behavior:

```
Account_ptr accp = Account::nil();
// ...
CORBA::CashAmount bal = accp->balance(); //Crash imminent!
```

---

## Object Reference Operations

Because all object references inherit from `CORBA::Object`, you can invoke its operations on any object reference. `CORBA::Object` is a pseudo-interface with this definition:

```
module CORBA { //IDL
//..
interface Object{
 Object duplicate()
 void release();
 boolean is_nil();
 boolean is_a(in string repository_id);
 boolean non_existent();
 boolean is_equivalent(in Object other_object);
 boolean hash(in unsigned long m_ax);
 // ...
}
};
```

### Mappings

In C++, these operations are mapped to `CORBA::Object` member methods as follows: `is_nil()` is discussed earlier in this chapter ([see page 194](#)).

```
//In namespace CORBA:
class Object {
public:
 static Object_ptr_duplicate(Object_ptr obj);
 void release(Type_ptr);
 Boolean is_nil(Type_ptr p);
 Boolean _is_a(const char * repository_id);
 Boolean non_existent();
 Boolean _is_equivalent(Object_ptr other_obj);
 ULong _hash(ULong m_ax);
 // ...
};
```

`_duplicate()`, and `release()` are discussed later in this chapter ([see page 198](#)).

### Operation descriptions

The following sections describe the remaining operations.

`_is_a()` is similar to `_narrow()` in that it lets you to determine whether an object supports a specific interface. For example:

```
CORBA::Object_ptr obj = ...; //Get a reference

if (CORBA::is_nil(obj) &&
 obj > _is_a("IDL:BankDemo/Account1.0"))
 // It's an Account object...
else
 // Some other type of object...
```

The test for nil in this code example prevents the client program from making a call via a nil object reference.

`_is_a()` lets applications manipulate IDL interfaces without static knowledge of the IDL—that is, without having linked the IDL-generated stubs. Most applications have static knowledge of IDL definitions, so they never need to call `_is_a()`. In this case, you can rely on `_narrow()` to ascertain whether an object supports the desired interface.

`_non_existent()` tests whether a CORBA object exists. `_non_existent()` returns true if an object no longer exists. A return of true denotes that this reference and all copies are no longer viable and should be released.

If `_non_existent()` needs to contact a remote server, the operation is liable to raise system exceptions that have no bearing on the object's existence—for example, the client might be unable to connect to the server.

If you invoke a user-defined operation on a reference to a non-existent object, the ORB raises the `OBJECT_NOT_EXIST` system exception. So, invoking an operation on a reference to a non-existent object is safe, but the client must be prepared to handle errors.

`_is_equivalent()` tests whether two references are identical. If `_is_equivalent()` returns true, you can be sure that both references point to the same object.

A false return does not necessarily indicate that the references denote different objects, only that the internals of the two references differ in some way. The information in references can vary among different ORB implementations. For example, one vendor might enhance performance by adding cached information to references, to speed up connection establishment. Because `_is_equivalent()` tests for absolute identity, it cannot distinguish between vendor-specific and generic information.

**`_hash()`** returns a hash value in the range `0..max-1`. The hash value remains constant for the lifetime of the reference. Because the CORBA specifications offer no hashing algorithm, the same reference on different ORBs can have different hash values.

`_hash()` is guaranteed to be implemented as a local operation—that is, it will not send a message on the wire.

`_hash()` is mainly useful for services such as the transaction service, which must be able to determine efficiently whether a given reference is already a member of a set of references. `_hash()` permits partitioning of a set of references into an arbitrary number of equivalence classes, so set membership testing can be performed in (amortized) constant time. Applications rarely need to call this method.

## Using `_ptr` References

The IDL compiler defines a `_ptr` reference type for each IDL interface. In general, you can think of a `_ptr` reference as a pointer to a proxy instance, with the same semantics and requirements as any C++ pointer.

### Duplicating and releasing references

To make a copy of a `_ptr` reference, invoke the static `_duplicate()` member method on an existing object reference. For example:

```
Account_ptr acc1 = ...; //Get ref from somewhere...
Account_ptr acc2; //acc2 has undefined contents
acc2 = Account::_duplicate(acc1); //Both reference same
Account
```

`_duplicate()` makes an exact copy of a reference. The copy and the original are indistinguishable from each other. As shown earlier (see [“Counting References” on page 192](#)), `_duplicate()` also makes a deep copy of the target reference, so the reference count on the proxy object is incremented. Consequently, you must call `release()` on all duplicated references to destroy them and prevent memory leaks.

To destroy a reference, use the `release` method. For example:

```
Account_ptr accp = ...; //Get reference from somewhere...
// ..Use accp
CORBA::release(accp); //Don't want to use Account anymore
```

`_duplicate()` is type safe. To copy an `Account` reference, supply an `Account` reference argument to `_duplicate()`. Conversely, the `CORBA` namespace contains only one `release()` method, which releases object references of any type.

### Widening and narrowing `_ptr` references

Proxy classes emulate the inheritance hierarchy of the IDL interfaces from which they are generated. Thus, you can widen and narrow `_ptr` references to the corresponding proxies.

### Widening assignments

Object references to proxy instances conform to C++ rules for type compatibility. Thus, you can assign a derived reference to a base reference, or pass a derived reference where a base reference is expected.

For example, the following IDL defines the `CheckingAccount` interface, which inherits from the `Account` interface shown earlier:


```
interface CheckingAccount : Account {
 exception InsufficientFunds {};
 readonly attribute CashAmount overdraftLimit;
 boolean orderCheckBook ();
};
```

Given this inheritance hierarchy, the following widening assignments are legal:

```
CheckingAccount_ptr ck = ...; //Get checking account
reference
Account_ptr accp = ck; //Widening assignment
CORBA::Object_ptr obj1 = ck; //Widening assignment
CORBA::Object_ptr obj2 = accp; //Widening assignment
```

**Note:** Because all proxies inherit from `CORBA::Object`, you can assign any type of object reference to `Object_ptr`, such as `_ptr` references `obj1` and `obj2`.

Ordinary assignments between `_ptr` references have no effect on the reference count. Thus, the assignments shown in the previous code can be characterized as shown in [Figure 10](#):



**Figure 10:** Multiple `_ptr` references to a proxy object can leave the reference count unchanged.

Because the reference count is only 1, calling `release()` on any of these references decrements the proxy reference count to 0, causing Orbix to deallocate the proxy. Thereafter, all references to this proxy are invalid.

### Type-safe narrowing of `_ptr` references

For each interface, the IDL compiler generates a static `_narrow()` method that lets you down-cast a `_ptr` reference at runtime. For example, the following code narrows an `Account` reference to a `CheckingAccount` reference:

```
BankDem o::Account_ptr accp = ..; //get a reference from
 som ewhere
BankDem o::CheckingAccount_ptr ckp =
 BankDem o::CheckingAccount::_narrow(accp);
if (CORBA::is_nil(ckp))
{
 //accp is not of type CheckingAccount
}
else
{
 //accp is a CheckingAccount type, so ckp is a valid
 reference
}
// ...
//release references to Account proxy
CORBA::release(ckp);
CORBA::release(accp);
```

Because `_narrow()` calls `_duplicate()`, it increments the reference count on the `Account` proxy—in this example, to 2. Consequently, the code must release both references.

## Using `_var` References

The IDL compiler defines a `_var` class type for each IDL interface, which lets you instantiate `_var` references in the client code. Each `_var` reference takes ownership of the reference that it is initialized with, and calls `CORBA::release()` when it goes out of scope.

If you initialize a `_var` reference with a `_ptr` reference, you cannot suffer a resource leak because, when it goes out of scope, the `_var` reference automatically decrements the reference count on the proxy.

`_var` references are also useful for gaining exception safety. For example, if you keep a reference you have just obtained as a `_var` reference, you can throw an exception at any time and it does not leak the reference because the C++ run time system calls the `_var`'s destructor as it unwinds the stack

### `_var` class member methods

Given the `Account` interface shown earlier, the IDL compiler generates an `Account_var` class with the following definition:

```
class Account_var{
public:
 Account_var();
 Account_var(Account_ptr&);
 Account_var(const Account_var&);
 ~Account_var();
 Account_var& operator= (Account_ptr&);
 Account_var& operator= (const Account_var&);
 operator Account_ptr& ();
 Account_ptr in() const;
 Account_ptr& in inout();
 Account_ptr& in out();
 Account_ptr_retn();

private:
 Account_ptr; //actual reference stored here
};
```

**Account\_var():** The default constructor initializes the private `_ptr` reference to nil.

**Account\_var(Account\_ptr &):** Constructing a `_var` from a `_ptr` reference passes ownership of the `_ptr` reference to the `_var`. This method leaves the proxy reference count unchanged.

**Account\_var(const Account\_var &):** Copy-constructing a `_var` makes a deep copy by calling `_duplicate()` on the source reference. This method increments the proxy reference count.

**~Account\_var():** The destructor decrements the proxy reference count by calling `release()`.

**Account\_var & operator=(Account\_ptr &) / Account\_var & operator=(const Account\_var &):** Assignment from a pointer passes ownership and leaves the proxy reference count unchanged; assignment from another `Account_var` makes a deep copy and increments the reference count.

**operator Account\_ptr &():** This conversion operator lets you pass a `_var` reference where a `_ptr` reference is expected, so use of `_var` references is transparent for assignment and parameter passing.

**Account\_ptr operator->() const:** The indirection operator permits access to the member methods on the proxy via a `_var` by returning the internal `_ptr` reference.

**Account\_ptr in() const / Account\_ptr & inout() / Account\_ptr & out():**

Explicit conversion operators are provided for compilers that incorrectly apply C++ argument-matching rules.

**Account\_ptr \_retn():** The `_retn()` method removes ownership of a reference from a `_var` without decrementing the reference count. This is useful if a method must allocate and return a `_var` reference, but also throws exceptions.

## Widening and narrowing `_var` References

You can copy-construct and assign from `_var` references, but only if both references are of the same type. For example, the following code is valid:

```
Account_var accv1 = ...; //get object reference
Account_var accv2 (accv1); //Fine, deep copy
accv1 = accv2; //Fine, deep assignment
```

Unlike `_ptr` references, `_var` references have no inheritance relationship, so implicit widening among `_var` references is not allowed. For example, you cannot use a `CheckingAccount_var` to initialize an `Account_var`:

```
CheckingAccount_var ckv = ...; //get object reference
accv1 = ckv; //Compile-time error
Account_var accv3(ckv); //Compile-time error
```

To widen a `_var` reference, you must first call `_duplicate()` on the original `_var`. Although `_duplicate()` expects a `_ptr` reference, a `_var` can be supplied in its place, as with any method that expects a `_ptr` reference. `_duplicate()` returns a `_ptr` reference that can then be implicitly widened.

For example, in the following statement, `_duplicate()` receives a `CheckingAccount_var`:

```
Account_var accv1(CheckingAccount::_duplicate(ckv));
```

`_duplicate()` returns a `CheckingAccount_ptr` that is implicitly widened to an `Account_ptr` as the argument to the `Account_var` constructor. The constructor in turn takes ownership, so the copy made by `_duplicate()` is not leaked.

In the next statement, `_duplicate()` expects an `Account_ptr`:

```
Account_var accv2(Account::_duplicate(ckv));
```

In fact, a `CheckingAccount_var` argument is supplied, which has a conversion operator to `CheckingAccount_ptr`. A `CheckingAccount_ptr` can be passed where an `Account_ptr` is expected, so the compiler finds an argument match. `_duplicate()` makes a copy of the passed reference and returns it as an `Account_ptr`, which is adopted by the `Account_var`, and no leak occurs.

You can also use `_duplicate()` for implicit `_var` widening through assignment, as in these examples:

```
accv1 = CheckingAccount::_duplicate(ckv);
accv2 = Account::_duplicate(ckv);
```

You can freely mix `_ptr` and `_var` references; you only need to remember that when you give a `_ptr` reference to a `_var` reference, the `_var` takes ownership:

```
//Be careful of ownership when mixing_var and_ptr:
{
 CheckingAccount_var ckv = ...; //Get reference...
 Account_ptr accp = ckv; //OK, but ckv still has
 ownership

 //Can use both ckv and accp here...

 CheckingAccount_ptr ckp = ...; //Get reference...
 ckv = ckp; //ckv now owner, accp dangles

 level = accp->balance(); //ERROR -accp dangles
} //ckv automatically releases its reference, ckp dangles!
level = ckp->balance() //ERROR -ckp dangles
```

---

## String Conversions

Object references can be converted to and from strings, which facilitates persistent storage. When a client obtains a stringified reference, it can convert the string back into an active reference and contact the referenced object. The reference remains valid as long as the object remains viable. When the object is destroyed, the reference becomes permanently invalid.

### Operations

The `object_to_string()` and `string_to_object()` operations are defined in C++ as follows:

```
//In < corba/orb.hh> :
namespace CORBA {
 // ...
 class ORB {
 public:
 char* object_to_string(Object_ptr obj);
 Object_ptr string_to_object(const char*);
 // ...
 };
 // ...
}
```

### `object_to_string()`

For example, the following code stringifies an `Account` object reference:

```
BankDemo: Account_ptr accp = ...; //Account reference

//Write reference as a string to stdout
//
try {
 CORBA::String_var str = orb->object_to_string(accp);
 cout << str << endl;
} catch (...) {
 //Deal with error...
}
```

The example puts the return value from `object_to_string` in a `String_var`. This ensures that the string is not leaked. This code prints an IOR (interoperable reference) string whose format is similar to this:

```
DR :
010000002000000049444c3a61636d652e636fd2f4943532f436fe74726fc
```

```
c65723a312e30000100000000000004a000000010102000e0000003139322e3
36382e312e3231300049051b0000003a3e0231310c01000000c7010000234800
008000000000000000001000000600000006000000010000001100
```

The stringified references returned by `object_to_string()` always contain the prefix `DR;` followed by an even number of hexadecimal digits. Stringified references do not contain any unusual characters, such as control characters or embedded newlines, so they are suitable for text I/O.

## string\_to\_object()

To convert a string back into a reference, call `string_to_object()`:

```
//Assume stringified reference is in accv[1]

try {
 CORBA::Object_ptr obj;
 obj = orb->string_to_object(accv[1]);
 if (CORBA::is_nil(obj))
 throw 0; //accv[1] is nil

 BankDemo::Account_ptr accp = BankDemo::Account::_narrow(obj);
 if (CORBA::is_nil(accp))
 throw 0; //Not an Account reference

 //Use accp reference...

 CORBA::release(accp); //Avoid leak
} catch (...) {
 //Deal with error...
}
```

The CORBA specification defines the representation of stringified IOR references, so it is interoperable across all ORBs that support the Internet Inter-ORB Protocol (*IIOP*).

Although the IOR shown earlier looks large, its string representation is misleading. The in-memory representation of references is much more compact. Typically, the incremental memory overhead for each reference in a client can be as little as 30 bytes.

You can also stringify or destringify a nil reference. Nil references look like one of the following strings:

```
DR 00000000000000010000000000000000
DR 01000000010000000000000000000000
```

## Constraints

IOR string references should be used only for these tasks:

- Store and retrieve an IOR string to and from a storage medium such as disk or tape.
- Conversion to an active reference.

It is inadvisable to rely on IOR string references as database keys for the following reasons:

- Actual implementations of IOR strings can vary across different ORBs—for example, vendors can add proprietary information to the string, such as a time stamp. Given these differences, you cannot rely on consistent string representations of any object reference.
- The actual size of IOR strings—between 200 and 600 bytes— makes them prohibitively expensive to use as database keys.

In general, you should not compare one IOR string to another. To compare object references, use `is_equivalent()` (see [page 196](#)).

**Note:** Stringified IOR references are one way to make references to initial objects known to clients. However, distributing strings as e-mail messages or writing them into shared file systems is neither a distributed nor a scalable solution. More typically, applications obtain object references through the naming service (see [Chapter 18 on page 485](#)).

## Using corbaloc URL strings

`string_to_object()` can also take as an argument a corbaloc-formatted URL, and convert it into an object reference. A corbaloc URL denotes objects that can be contacted by IOP or `resolve_initial_references()`.

A corbaloc URL uses one of the following formats:

```
corbaloc:rir/rir-argument
corbaloc:iop-address[,iop-address]...key-string
```

**rir-argument:** A value that is valid for `resolve_initial_references()`, such as `NameService`.

**iop-address:** Identifies a single IOP address with the following format:

```
[iop]:[major-version-number-minor-version-number] host-spec [port-num]
```

IOP version information is optional; if omitted, version 1.0 is assumed. `host-spec` can specify either a DNS-style host name or a numeric IP address; specification of `port-num` is optional.

**key-string:** corresponds to the octet sequence in the object key member of a stringified object reference, or an object's named key that is defined in the implementation repository.

For example, if you register the named key `BankService` for an IOR in the implementation repository, a client can access an object reference with `string_to_object()` as follows:

```
//assume that xyz.com specifies a location domain's host
global_obj-> string_to_object
('boibabc:iiop:xyz.com /BankService');
```

The following code obtains an object reference to the naming service:

```
global_obj-> string_to_object("boibabc:iiop:NamingService");
```

You can define a named key in the implementation repository through the

- `admin named_key create` command. For more information, see the *Application Server Platform Administrator's Guide*.

---

# Initializing and Shutting Down the ORB

Before a client application can start any CORBA-related activity, it must initialize the ORB runtime by calling `ORB_init()`. `ORB_init()` returns an object reference to the ORB object; this, in turn, lets the client obtain references to other CORBA objects, and make other CORBA-related calls.

Procedures for ORB initialization and shutdown are the same for both servers and clients. For detailed information, see [“ORB Initialization and Shutdown” on page 163](#).

## Invoking Operations and Attributes

For each IDL operation in an interface, the IDL compiler generates a method with the name of the operation in the corresponding proxy. It also maps each unqualified attribute to a pair of overloaded methods with the name of the attribute, where one method acts as an accessor and the other acts as a modifier. For `readonly` attributes, the compiler generates only an accessor method.

An IDL attribute definition is functionally equivalent to a pair of set/get operation definitions, with this difference: attribute accessors and modifiers can only raise system exceptions, while user exceptions apply only to operations.

For example, the following IDL defines a single attribute and two operations in interface `Test::Example`:

```
module Test {
 interface Example {
 attribute string name;
 oneway void set_address(in string addr);
 string get_address();
 };
};
```

The IDL compiler maps this definition's members to the following methods in the C++ proxy class `Example`. A client invokes on these methods as if their implementations existed within its own address space:

```
namespace Test {
// ...
class Example : public virtual CORBA::Object
{
public:
// ...
virtual char* name() = 0;
virtual void name(const char* _ivar_name) = 0;
virtual void set_address(const char* addr) = 0;
virtual char* get_address() = 0;
// ...
};
};
```

---

# Passing Parameters in Client Invocations

The C++ mapping has strict rules on passing parameters to operations. Several objectives underlie these rules:

- Avoid data copying.
- Deal with variable-length types, which are allocated by the sender and deallocated by the receiver.
- Map the source code so it is location-transparent; source code does not need to consider whether or not client and server are collocated.

In general, a variable-length parameter is always dynamically allocated, and the receiver of the value is responsible for deallocation. For variable-length `out` parameters and return values, the server allocates the value and the client deallocates it.

For string, reference, and variable-length array `inout` parameters, the client dynamically allocates the value and passes it to the server. The server can either leave the initial value's memory alone or it can deallocate the initial value and allocate a different value to return to the client; either way, responsibility for deallocation of a variable-length `inout` parameter remains with the client.

All other parameters are either fixed-length or `in` parameters. For these, dynamic allocation is unnecessary, and parameters are passed either by value for small types, or by reference for complex types.

## Simple Parameters

For simple fixed-length types, parameters are passed by value if they are `in` parameters or return values, and are passed by reference if they are `inout` or `out` parameters.

For example, the following IDL defines an operation with simple parameters:

```
interface Example {
 long op(
 in long in_p, inout long inout_p, out long out_p
);
};
```

The proxy member method signature is the same as the signature of any other C++ method that passes simple types in these directions:

```
virtual CORBA::Long
op(
 CORBA::Long in_p,
 CORBA::Long& inout_p,
 CORBA::Long& out_p
)= 0;
```

For example, a client can invoke `op` as follows:

```
Example_varev = ...; //Get reference

CORBA::Long inout= 99; //Note initialization
CORBA::Long out; //No initialization needed
CORBA::Long ret_val;

ret_val= ev->op(500, inout, out); //Invoke CORBA operation

cout<< "ret_val: "<< ret_val<< endl;
cout<< "inout: "<< inout<< endl;
cout<< "out: "<< out<< endl;
```

The client passes the constant 500 as the `in` parameter. For the `inout` parameter, the client passes the initial value 99, which the server can change. No initialization is necessary for the `out` parameter and the return value. No dynamic allocation is required; the client can pass variables on the stack, on the heap, or in the data segment (global or static variables).

## Fixed-Length Complex Parameters

For fixed-length complex types such as fixed-length structures, parameters are passed by reference or constant reference and are returned by value.

For example, the following IDL defines an operation with fixed-length complex parameters:

```
struct FLS { //Fixed-Length Structure
 long long_val;
 double double_val;
};

interface Example {
 FLS op(in FLS in_p, inout FLS inout_p, out FLS out_p);
};
```

The corresponding proxy method has the following signature:

```
typedef FLS & FLS_out;
// ...
virtual FLS
op(const FLS & in_p, FLS & inout_p, FLS_out out_p) = 0;
```

Using the generated proxy method in the client is easy, and no dynamic memory allocations are required:

```
Example_varev = ...; //Get reference

FLS in; //Initialize in param
in.long_val = 99;
in.double_val = 33.0;

FLS inout; //Initialize inout param
inout.long_val = 33;
inout.double_val = 11.0;
```

```
FLS out; //Outparam
FLS ret_val; //Return value

ret_val= op(in, inout, out); //Make call

//inout may have been changed, and out and ret_val
//contain the values returned by the server.
```

## Fixed-Length Array Parameters

Fixed-length array parameters follow the same parameter-passing rules as other fixed-length types. However, an array that is passed in C++ degenerates to a pointer to the first element, so the method signature is expressed in terms of pointers to array slices.

For example, the following IDL defines an operation with fixed-length array parameters:

```
typedef long Larr[3];

interface Example {
 Larr op(in Larr in_p, inout Larr inout_p, out Larr out_p);
};
```

The IDL compiler maps this IDL to the following C++ definitions:

```
typedef CORBA::Long Larr[3];
typedef CORBA::Long Larr_slice;
typedef Larr_slice * Larr_out;
// ...
virtual Larr_slice * op(
 const Larr in_p, Larr_slice * inout_p, Larr_out out_p
) = 0;
```

For `in`, `inout`, and `out` parameters, memory is caller-allocated and need not be on the heap; the method receives and, for `inout` and `out` parameters, modifies the array via the passed pointer. For the return value, a pointer must be returned to dynamically allocated memory, simply because there is no other way to return an array in C++. Therefore, the client must deallocate the return value when it is no longer wanted:

```
Example_varev = ...; //Get reference

Larr in = { 1, 2, 3 }; //Initialize in param
Larr inout = { 4, 5, 6 }; //Initialize inout param
Larr out; //out param
Larr_slice * ret_val; //return value
ret_val = ev->op(in, inout, out); //Make call

//Use results...
Larr_free(ret_val); //Must deallocate here!
```

In the previous example, the call to `Larr_free` is required to prevent a memory leak. Alternatively, you can use `_var` types to avoid the need for deallocation. So, you can rewrite the previous example as follows:

```
Example_varev = ...; //Get reference

Larr_in = { 1,2,3 }; //Initialize in param
Larr_inout= { 4,5,6 }; //Initialize inoutparam
Larr_out; //outparam ,note _var type!
Larr_varret_val; //return value

ret_val= ev->op(in, inout, out); //Make call

//Use results...

//No need to dealocate anything here, ret_val takes care of it.
```

`_var` types are well-suited to manage the transfer of memory ownership from sender to receiver because they work transparently for both fixed- and variable-length types.

## String Parameters

The C++ mapping does not encapsulate strings in a class, so string parameters are passed as `char*`. Because strings are variable-length types, the following memory management issues apply:

- `in` strings are passed as `const char*`, so the callee cannot modify the string's value. The passed string need not be allocated on the heap.
- `inout` strings must be allocated on the heap by the caller. The callee receives a C++ reference to the string pointer. This is necessary because the callee might need to reallocate the string if the new value is longer than the initial value. Passing a reference to the callee lets the callee modify the bytes of the string and the string pointer itself. Responsibility for deallocating the string remains with the caller.
- `out` strings are dynamically allocated by the callee. Responsibility for deallocating the string passes to the caller.
- Strings returned as the return value behave like `out` strings: they are allocated by the callee and responsibility for deallocation passes to the caller.

For example, the following IDL defines an operation with string parameters:

```
interface Example {
 string op(
 in string in_p,
 inout string inout_p,
 out string out_p
);
};
```

The IDL compiler maps this interface to the following class, in which string parameters are passed as `char*`:

```
class String_out; // In the CORBA namespace
//...
virtual const char*
op(
 const char* in_p,
 char* & inout_p,
 CORBA::String_out out_p
) = 0;
```

The following example shows how to invoke an operation that passes a string in each possible direction:

```
Example_varev = ...; //Get ref

char* inout= CORBA::string_dup("Hello"); //Initialize
char* out;
char* ret_val;

ret_val= ev->op("Input string", inout, out); //Make call

//Use the strings...

CORBA::string_free(inout); //We retain ownership
CORBA::string_free(out); //Caller passed responsibility
CORBA::string_free(ret_val); //Caller passed responsibility
```

This example illustrates the following points:

- The `in` parameter can be allocated anywhere; the example passes a string literal that is allocated in the data segment.
- The caller must pass a dynamically allocated string as the `inout` parameter, because the callee assumes that it can, if necessary, deallocate that parameter.
- The caller must deallocate the `inout` and `out` parameter and the return value.

The following example shows the same method call as before, but uses `String_var` variables to deallocate memory:

```
Example_varev = ...;

CORBA::String_var inout= CORBA::string_dup("Hello");
CORBA::String_var out;
CORBA::String_var ret_val;

ret_val= ev->op("Input string", inout, out);

//Use the strings...

//No need to deallocate there because the String_var
//variables take ownership.
```

Be careful not to pass a default-constructed `String_var` as an `in` or `inout` parameter:

```
Example_ev ev = ...;

CORBA::String_var in; //Bad: no initialization
CORBA::String_var inout; //Bad: no initialization
CORBA::String_var out;
CORBA::String_var ret_val;

ret_val = ev->op(in, inout, out); //Oops :-|
```

In this example, `in` and `inout` are initialized to the null pointer by the default constructor. However, it is illegal to pass a null pointer across an interface; code that does so is liable to crash or raise an exception.

**Note:** This restriction applies to all types that are passed by pointer, such as arrays and variable-length types. Never pass a null pointer or an uninitialized pointer. Only one exception applies: you can pass a nil reference, even if nil references are implemented as null pointers.

## \_out Types

IDL `out` parameters result in proxy signatures that use C++ `_out` types. `_out` types ensure correct deallocation of previous results for `_var` types. For example, the following IDL defines a single out parameter:

```
interface Person {
 void get_name(out string name);
 // ...
};
```

The IDL compiler generates the following class:

```
class Person {
public:
 void get_name(CORBA::String_out name);
 // ...
};
```

The following code fragment uses the `Person` interface, but leaks memory:

```
char* name;
Person_var person_1 = ...;
Person_var person_2 = ...;

person_1->get_name(name);
cout << "Name of person 1: " << name << endl;

person_2->get_name(name); //Bad news!
cout << "Name of person 2: " << name << endl;

CORBA::string_free(name); //Dealocate
```

Because variable-length `out` parameters are dynamically allocated by the proxy stub, the second call to `get_name()` causes the result of the first `get_name` call to leak.

The following code corrects this problem by deallocating variable-length `out` parameters between invocations:

```
char* name;
Person_var person_1 = ...;
Person_var person_2 = ...;

person_1->get_name(name);
cout << "Name of person 1:" << name << endl;
CORBA::String_free(name); //Much better!

person_2->get_name(name); //No problem
cout << "Name of person 2:" << name << endl;
CORBA::String_free(name); //Dealocate
```

However, if we use `_var` types, no deallocation is required at all:

```
CORBA::String_var name; //Note String_var
Person_var person_1 = ...;
Person_var person_2 = ...;

person_1->get_name(name);
cout << "Name of person 1:" << name << endl;

person_2->get_name(name); //No leak here
cout << "Name of person 2:" << name << endl;

//No need to deallocate name
```

When the name variable is passed to `get_name` a second time, the mapping implementation transparently deallocates the previous string. However, how does the mapping manage to avoid deallocation for pointer types but deallocates the previous value for `_var` types?

The answer lies in the formal parameter type `CORBA::String_out`, which is a class as outlined here:

```
class String_out { // In the CORBA nam espace
public:
 String_out(char* & s):m_ref(s) { m_ref= 0 }
 String_out(String_var& s):m_ref(s.m_ref) {
 string_free(m_ref);
 m_ref= 0;
 }
 //Other member methods here...
private:
 char* & m_ref;
};
```

This implementation of `CORBA::String_out` shows how `char*` out parameters are left alone, but `_var` out parameters are deallocated.

If you pass a `char*` as an out parameter, the compiler looks for a way to convert the `char*` into a `String_out` object. The single-argument constructor for `char*` acts as a user-defined conversion operator, so the compiler finds an argument match by constructing a temporary `String_out` object that is passed to the method. Note that the `char*` constructor is passed a reference to the string, which it binds to the private member variable `m_ref`. The constructor body then assigns zero to the `m_ref` member. `m_ref` is a reference to the passed string, so construction from a `char*` clears (sets to null) the actual argument that is passed to the constructor, without deallocating the previous string.

On the other hand, if you pass a `String_var` as an out parameter, the compiler uses the second constructor to construct the temporary `String_out`. That constructor binds the `m_ref` member variable to the passed `String_var`'s internal pointer and deallocates the current string before setting the passed string pointer to null.

`_out` types are generated for all complex types, such as strings, sequences, and structures. If a complex type has fixed length, then the generated `_out` type is simply an alias for a reference to the actual type (see “[Fixed-Length Complex Parameters](#)” on page 213 for an example).

**Note:** You can ignore most of the implementation details for `_out` types. It is only important to know that they serve to prevent memory leaks when you pass a `_var` as an out parameter.

## Variable-Length Complex Parameters

The parameter-passing rules for variable-length complex types differ from those for fixed-length complex types. In particular, for `out` parameters and return values, the caller is responsible for deallocating the value.

For example, the following IDL defines an operation with variable-length complex parameters:

```
struct VLS { //Variable-Length Structure
 long long_val;
 string string_val;
};

interface Example {
 VLS op(in VLS in_p, inout VLS inout_p, out VLS out_p);
};
```

The IDL compiler maps this IDL to the following C++ definitions:

```
class VLS_out;
// ...
virtual VLS *
op(const VLS & in_p, VLS & inout_p, VLS_out out_p) = 0;
```

The following code calls the `op()` operation:

```
Example_varev = ...; //Get reference

VLS in; //initialize in param
in.long_val = 99;
in.string_val = CORBA::string_dup("Ninety-nine");

VLS inout; //initialize inout param
inout.long_val = 86;
inout.string_val = CORBA::string_dup("Eighty-six");

VLS * out; //Note *pointer* to out param
VLS * ret_val; //Note *pointer* to return value

ret_val = op(in, inout, out); //Make call
```

```
//Use values...

delete out; //Make sure nothing is leaked
delete ret_val; //Ditto...
```

As with fixed-length complex types, `in` and `inout` parameters can be ordinary stack variables. However, both the `out` parameter and the return value are dynamically allocated by the call. You are responsible for deallocating these values when you no longer require them.

You can also use `_var` types to take care of the memory-management chores for you, as in this modified version of the previous code:

```
Example_varev = ...; //Get reference

VLS in; //Initialize in param
in.lng_val= 99;
in.string_val= CORBA::string_dup("Ninety-nine");

VLS inout; //Initialize inout param
inout.lng_val= 86;
inout.string_val= CORBA::string_dup("Eighty-six");

VLS_varout; //Note _var type
VLS_varret_val; //Note _var type

ret_val= op(in, inout, out); //Make call

//Use values...

//No need to deallocate anything here
```

**Note:** Type `Any` is passed using the same rules—that is, `out` parameters and return values are dynamically allocated by the stub and must be deallocated by the caller. Of course, you can use `CORBA::Any_var` to achieve automatic deallocation.

## Variable-Length Array Parameters

Variable-length arrays are passed as parameters in the same way as fixed-length arrays, except for `out` parameters: these are passed as a reference to a pointer. As for strings, the generated `_out` class takes care of deallocating values from a previous invocation held in `_var` types.

For example, the following IDL defines an operation with variable-length string array parameters:

```
typedef string Sarr[3];

interface Example {
 Sarr op(in Sarr in_p, inout Sarr inout_p, out Sarr out_p);
};
```

The IDL compiler maps this IDL to the following C++ definitions:

```
typedef CORBA::String_mgr Sarr[3];
typedef CORBA::String_Mgr Sarr_slice;
class Sarr_out;
// ...
virtual Sarr_slice * op(
 const Sarr in_p, Sarr_slice * inout_p, Sarr_out out_p
) = 0;
```

The following code calls the `op()` operation:

```
Example_varev = ...; //Get reference

Sarr in;
in[0] = CORBA::string_dup("Björne");
in[1] = CORBA::string_dup("Stan");
in[2] = CORBA::string_dup("Andrew");

Sarr inout;
inout[0] = CORBA::string_dup("Dennis");
inout[1] = CORBA::string_dup("Ken");
inout[2] = CORBA::string_dup("Brian");

Sarr_slice * out; //Pointer to array slice
Sarr_slice * ret_val; //Pointer to array slice
```

```
ret_val= ev-> op(in, inout, out); //Make call

//Use values...

Sarr_free(out); //Deallocate to avoid leak
Sarr_free(ret_val); //Ditto...
```

As always, you can rewrite the code to use `_var` types, and so prevent memory leaks:

```
Example_var ev = ...; //Get reference

Sarr in;
in[0]= CORBA::string_dup("B June");
in[1]= CORBA::string_dup("Stan");
in[2]= CORBA::string_dup("Andrew ");

Sarr inout;
inout[0]= CORBA::string_dup("Dennis");
inout[1]= CORBA::string_dup("Ken");
inout[2]= CORBA::string_dup("Brian");

Sarr var out; //Note _var type
Sarr var ret_val; //Note _var type

ret_val= ev-> op(in, inout, out); //Make call

//Use values...

//No need to free anything here
```

## Object Reference Parameters

You pass object references as parameters as you do strings. For `inout` reference, the caller must pass a C++ reference to a `_ptr` reference. For an `out` parameter and return values, the caller is responsible for deallocation. For example, the following IDL defines an operation with object reference parameters:

```
interface Example {
 string greeting();
 Example op(
 in Example in_p,
 inout Example inout_p,
 out Example out_p
);
};
```

The IDL compiler maps this IDL to the following C++ definitions:

```
class Example_out;
// ...
virtual Example_ptr op(
 Example_ptr in_p, Example_ptr& inout_p, Example_out out_p
) = 0;
```

The following code calls the `op()` operation:

```
Example_var ev = ...;
Example_var in = ...; // Initialize in param
Example_var inout = ...; // Initialize inout param
Example_ptr out; // Note _ptr reference
Example_ptr& inout_val; // Note _ptr reference

ret_val = ev->op(in, inout, out);

// Use references...

CORBA::release(out); // Deallocate
CORBA::release(ret_val); // Ditto...
```

Note that the code explicitly releases the references returned as the `out` parameter and the return value.

You can also rewrite this code to use `_var` references in order to avoid memory leaks:

```
Example_var ev = ...;
Example_var in = ...; // initialize in param
Example_var inout = ...; // initialize inout param
Example_var out; // Note _var reference
Example_var ret_val; // Note _var reference

ret_val = ev->op(in, inout, out);

// Use references...

// No need to deallocate here
```

## Parameter-Passing Rules: Summary

The following sections summarize the parameter-passing rules for the C++ mapping.

**Never pass null or uninitialized pointers as in or inout parameters.** As shown earlier (see page 219), it is illegal to pass null pointers or uninitialized pointers as `inout` or `in` parameters. The most likely outcome of ignoring this rule is a core dump.

Nil object references are exempt from this rule, so it is safe to pass a nil reference as a parameter.

**Do not ignore variable-length return values.** Ignoring return values can leak memory. For example, the following interface defines operation `do_something()` to return a string value:

```
// interface Example {
// string do_something();
//};
```

The following client call on `do_something()` erroneously ignores its return value:

```
Example_varev = ...; //Get reference
ev->do_something(); //Memory leak!
```

Be careful never to ignore the return, because the memory that the stub allocates to the return value can never be reclaimed.

**Allocate string and reference inout parameters on the heap and deallocate them after the call.** String and reference `inout` parameters must be allocated on the heap; ownership of the memory remains with the caller.

**Deallocate variable-length return values and out parameters.**

Variable-length types passed as return values or `out` parameters are passed by pointer and are dynamically allocated by the stub. You must deallocate these values to avoid memory leaks.

**Use `_var` types for complex inout and out parameters and return values.**

Always use a `_var` type when a value must be heap-allocated. This includes any complex or variable-length `inout` or `out` parameter or return value. After you have assigned a parameter to a `_var` type, you don't have to worry about deallocating memory.

For example, the following interface defines three operations:

```
//Some sample IDL to show how _var types make life easier.
interface Example {
 string get_string();
 void modify_string(inout string s);
 void put_string(in string s);
};
```

Because `_var` types convert correctly to pass in any direction, the following code does exactly the right things:

```
//_var automates memory management.
{
 Example ev = ...; //Get reference
 CORBA::String_var s; //Parameter

 s = ev->get_string(); //Get value
 ev->modify_string(s); //Change it
 ev->put_string(s); //Put it somewhere
}
//Everything is deallocated here
```

Table 9 summarizes parameter-passing rules. It does not show that `out` parameters are passed as `_out` types. Instead, it shows the corresponding alias for fixed-length types, or the type of constructor argument for the `_out` type for variable-length types.

**Table 9:** *Parameter passing for low-level mapping*

| IDL Type       | in                       | inout                | out                  | Return Value   |
|----------------|--------------------------|----------------------|----------------------|----------------|
| <i>simple</i>  | <i>simple</i>            | <i>simple &amp;</i>  | <i>simple &amp;</i>  | <i>simple</i>  |
| <i>enum</i>    | <i>enum</i>              | <i>enum &amp;</i>    | <i>enum &amp;</i>    | <i>enum</i>    |
| <i>fixed</i>   | <i>const Fixed &amp;</i> | <i>Fixed &amp;</i>   | <i>Fixed &amp;</i>   | <i>Fixed</i>   |
| <i>string</i>  | <i>const char*</i>       | <i>char* &amp;</i>   | <i>char* &amp;</i>   | <i>char*</i>   |
| <i>wstring</i> | <i>const W Char*</i>     | <i>W Char* &amp;</i> | <i>W Char* &amp;</i> | <i>W Char*</i> |
| <i>any</i>     | <i>const Any &amp;</i>   | <i>Any &amp;</i>     | <i>Any* &amp;</i>    | <i>Any*</i>    |

**Table 9:** *Parameter passing for low-level mapping*

| IDL Type                 | in                     | inout                | out                    | Return Value         |
|--------------------------|------------------------|----------------------|------------------------|----------------------|
| <i>objref</i>            | <i>objref_ptr</i>      | <i>objref_ptr</i> &  | <i>objref_ptr</i> &    | <i>objref_ptr</i>    |
| <i>sequence</i>          | <i>constsequence</i> & | <i>sequence</i> &    | <i>sequence</i> * &    | <i>sequence</i> *    |
| <i>struct</i> , fixed    | <i>const struct</i> &  | <i>struct</i> &      | <i>struct</i> &        | <i>struct</i>        |
| <i>union</i> , fixed     | <i>const union</i> &   | <i>union</i> &       | <i>union</i> &         | <i>union</i>         |
| <i>array</i> , fixed     | <i>const array</i>     | <i>array_slice</i> * | <i>array_slice</i> *   | <i>array_slice</i> * |
| <i>struct</i> , variable | <i>const struct</i> &  | <i>struct</i> &      | <i>struct</i> * &      | <i>struct</i> *      |
| <i>union</i> , variable  | <i>const union</i> &   | <i>union</i> &       | <i>union</i> * &       | <i>union</i> *       |
| <i>array</i> , variable  | <i>const array</i>     | <i>array_slice</i> * | <i>array_slice</i> * & | <i>array_slice</i> * |

As Table 9 shows, the parameter type varies for both `out` parameters and return values, depending on whether a complex structure, union, or array is variable length or fixed length. Table 10 shows the considerably simpler parameter-passing rules for `_var` types:

**Table 10:** *Parameter passing with `_var` types*

| IDL Type        | in                         | inout/out              | Return Value        |
|-----------------|----------------------------|------------------------|---------------------|
| <i>string</i>   | <i>constString_var</i> &   | <i>String_var</i> &    | <i>String_var</i>   |
| <i>wstring</i>  | <i>constW String_var</i> & | <i>W String_var</i> &  | <i>W String_var</i> |
| <i>any</i>      | <i>constAny_var</i> &      | <i>Any_var</i> &       | <i>Any_var</i>      |
| <i>objref</i>   | <i>constobjref_var</i> &   | <i>objref_var</i> &    | <i>objref_var</i>   |
| <i>sequence</i> | <i>constsequence_var</i> & | <i>ssequence_var</i> & | <i>sequence_var</i> |
| <i>struct</i>   | <i>conststruct_var</i> &   | <i>struct_var</i> &    | <i>struct_var</i>   |
| <i>union</i>    | <i>constunion_var</i> &    | <i>union_var</i> &     | <i>union_var</i>    |
| <i>array</i>    | <i>constarray_var</i> &    | <i>array_var</i> &     | <i>array_var</i>    |

`_var` types are carefully crafted so that parameter passing is uniform, regardless of the underlying type. This aspect of `_var` types, together with their automatic deallocation behavior, makes them most useful for parameter passing.

---

# Client Policies

Orbis supports a number of quality of service policies, which can give a client programmatic control over request processing:

- [RebindPolicy](#) specifies whether the ORB transparently reopens closed connections and rebinds forwarded objects.
- [SyncScopePolicy](#) determines how quickly a client resumes processing after sending one-way requests.
- [Timeout policies](#) offer different degrees of control over the length of time that an outstanding request remains viable.

You can set quality of service policies at three scopes, in descending order of precedence:

1. On individual objects, so they apply only to invocations on those objects.
2. On a given thread, so they apply only to invocations on that thread
3. On the client ORB, so they apply to all invocations.

You can set policies in any combination at all three scopes; the *effective* policy is determined on each invocation. If settings are found for the same policy type at more than one scope, the policy at the lowest scope prevails.

For detailed information about setting these and other policies on a client, see [“Setting Client Policies” on page 180](#).

**Note:** Because all policy types and their settings are defined in the Messaging module, client code that sets quality of service policies must include `com.ibm.messaging.hh.`

---

## RebindPolicy

A client's `RebindPolicy` determines whether the ORB can transparently reconnect and rebind. A client's rebind policy is set by a `RebindMode` constant, which describes the level of transparent binding that can occur when the ORB tries to carry out a remote request:

**TRANSPARENT** The default policy: the ORB silently reopens closed connections and rebinds forwarded objects.

**NO\_REBIND** The ORB silently reopens closed connections; it disallows rebinding of forwarded objects if client-visible policies have changed since the original binding. Objects can be explicitly rebound by calling `CORBA::Object::validate_connection()` on them.

**NO\_RECONNECT** The ORB disallows reopening of closed connections and rebinding of forwarded objects. Objects can be explicitly rebound by calling `CORBA::Object::validate_connection()` on them.

**Note:** Currently, Orbix requires rebinding on reconnection. Therefore, `NO_REBIND` and `NO_RECONNECT` policies have the same effect.

---

## SyncScopePolicy

A client's `SyncScopePolicy` determines how quickly it resumes processing after sending one-way requests. You specify this behavior with one of these `SyncScope` constants:

**SYNC\_NONE** The default policy: Orbix clients resume processing immediately after sending one-way requests, without knowing whether the request was processed, or whether it was even sent over the wire.

**SYNC\_WITH\_TRANSPORT** The client resumes processing after a transport accepts the request. This policy is especially helpful when used with store-and-forward transports. In that case, this policy offers clients assurance of a high degree of probable delivery.

**SYNC\_WITH\_SERVER** The client resumes processing after the request finds a server object to process it—that is, the server ORB sends a `NO_EXCEPTION` reply. If the request must be forwarded, the client continues to block until location forwarding is complete.

**SYNC\_WITH\_TARGET** The client resumes processing after the request processing is complete. This behavior is equivalent to a synchronous (two-way) operation. With this policy in effect, a client has absolute assurance that its request has found a target and been acted on. The object transaction service (OTS) requires this policy for any operation that participates in a transaction.

**Note:** This policy only applies to GIOP 1.2 (and higher) requests.

## Timeout Policies

A responsive client must be able to specify timeouts in order to abort invocations. Orbix supports several standard OMG timeout policies, as specified in the Messaging module; it also provides proprietary policies in the `II_CORBA` module that offer more fine-grained control. Table 11 shows which policies are supported in each category:

**Table 11:** *Timeout Policies*

|                              |                                                                                                                                                                                                                                                                                  |
|------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OMG Timeout Policies         | <a href="#">RelativeRoundtripTimeoutPolicy</a><br><a href="#">ReplyEndTimePolicy</a><br><a href="#">RelativeRequestTimeoutPolicy</a><br><a href="#">RequestEndTimePolicy</a>                                                                                                     |
| Proprietary Timeout Policies | <a href="#">BindingEstablishmentPolicy</a><br><a href="#">RelativeBindingExclusiveRoundtripTimeoutPolicy</a><br><a href="#">RelativeBindingExclusiveRequestTimeoutPolicy</a><br><a href="#">RelativeConnectionCreationTimeoutPolicy</a><br><a href="#">InvocationRetryPolicy</a> |

If a request's timeout expires before the request can complete, the client receives the system exception `CORBA::TIMEOUT`.

**Note:** When using these policies, be careful that their settings are consistent with each other. For example, the `RelativeRoundtripTimeoutPolicy` specifies the maximum amount of time allowed for round-trip execution of a request.

Orbix also provides its own policies, which let you control specific segments of request execution—for example, `BindingEstablishmentPolicy` lets you set the maximum time to establish bindings.

It is possible to set the maximum binding time to be greater than the maximum allowed for roundtrip request execution. Although these settings are inconsistent, no warning is issued; and Orbix silently adheres to the more restrictive policy.

### Setting absolute and relative times

Two policies, `RequestEndTimePolicy` and `ReplyEndTimePolicy`, set absolute deadlines for request and reply delivery, respectively, through the `TimeBase::UTC` type. Other policies set times that are relative to a specified

event—for example, `RelativeRoundtripTimeoutPolicy` limits how much time is allowed to deliver a request and its reply, starting from the request invocation.

The Orbix libraries include helper class `IT_UtcT`, which provides ease-of-use operators and methods for working with the types defined in the `TimeBase` module. For example, you can use `IT_UtcT::current()` and `IT_UtcT::operator+()` to obtain an absolute time that is relative to the current time. You can specify absolute times in long epoch (15 Oct 1582 to ~30000AD) Universal Time Coordinated (UTC), or relative times in 100 nano-seconds units using the OMG Time Service's `TimeBase::UtcT` type. You can also convert times to short epoch (Jan 1 1970 to ~2038) UTC in millisecond units. All times created have zero displacement from GMT. For more information, refer to the *CORBA Programmer's Reference*.

## Policies

**RelativeRoundtripTimeoutPolicy** specifies how much time is allowed to deliver a request and its reply. Set this policy's value in 100-nanosecond units. No default is set for this policy; if it is not set, a request has unlimited time to complete.

The timeout countdown begins with the request invocation, and includes the following activities:

- Marshalling in/inout parameters
- Any delay in transparently establishing a binding

If the request times out before the client receives the last fragment of reply data, the request is cancelled via a GIOP `CancelRequest` message and all received reply data is discarded.

For example, the following code sets a `RelativeRoundtripTimeoutPolicy` override on the ORB PolicyManager, setting a four-second limit on the time allowed to deliver a request and receive the reply:

```

TimeBase::TimeT relative_expiry = 4L * 100000000L; //4 seconds
try{
 CORBA::Any relative_roundtrip_timeout_value;
 relative_roundtrip_timeout_value <= relative_expiry;
 CORBA::PolicyList policies(1);
 policies.length(1);
 policies[0] = orb->create_policy(
 Messaging::RELATIVE_RT_TIMEOUT_POLICY_TYPE,
 relative_roundtrip_timeout_value
);
 policy_manager->set_policy_overrides(
 policies,
 CORBA::ADD_OVERRIDE
);
}
catch (CORBA::PolicyError& pe){
 return 1;
}
catch (CORBA::InvalidPolicies& ip){
 return 1;
}
catch (CORBA::SystemException& se){
 return 1;
}

```

**ReplyEndTimePolicy** sets an absolute deadline for receipt of a reply. This policy is otherwise identical to `RelativeRoundtripTimeoutPolicy`. Set this policy's value with a `TimeBase::UTCT` type (see [“Setting absolute and relative times” on page 236](#)).

No default is set for this policy; if it is not set, a request has unlimited time to complete.

**RelativeRequestTimeoutPolicy** specifies how much time is allowed to deliver a request. Request delivery is considered complete when the last fragment of the GIOP request is sent over the wire to the target object. The timeout-specified period includes any delay in establishing a binding. This policy type is useful to a client that only needs to limit request delivery time. Set this policy's value in 100-nanosecond units.

No default is set for this policy; if it is not set, request delivery has unlimited time to complete.

For example, the following code sets a `RelativeRequestTimeoutPolicy` override on the ORB PolicyManager, setting a three-second limit on the time allowed to deliver a request:

```

TimeBase::TimeT relative_expiry = 3L * 1000000L; // 3 seconds
try{
 CORBA::Any relative_request_timeout_value;
 relative_request_timeout_value <= relative_expiry;
 CORBA::PolicyList policies(1);
 policies.length(1);
 policies[0] = orb->create_policy(
 Messaging::RELATIVE_REQ_TIMEOUT_POLICY_TYPE,
 relative_request_timeout_value
);
 policy_manager->set_policy_overrides(
 policies,
 CORBA::ADD_OVERRIDE
);
}
catch (CORBA::PolicyError& pe){
 return 1;
}
catch (CORBA::InvalidPolicies& ip){
 return 1;
}
catch (CORBA::SystemException& se){
 return 1;
}
}

```

**RequestEndTimePolicy** sets an absolute deadline for request delivery. This policy is otherwise identical to `RelativeRequestTimeoutPolicy`. Set this policy's value with a `TimeBase::TimeT` type (see [“Setting absolute and relative times” on page 236](#)).

No default is set for this policy; if it is not set, request delivery has unlimited time to complete.

**BindingEstablishmentPolicy** limits the amount of effort Orbix puts into establishing a binding. The policy equally affects transparent binding (which results from invoking on an unbound object reference), and explicit binding (which results from calling `Object::validate_connection()`).

A client's `BindingEstablishmentPolicy` is determined by the members of its `BindingEstablishmentPolicyValue`, which is defined as follows:

```
struct BindingEstablishmentPolicyValue
{
 TimeBase::TimeT relative_expiry;
 unsigned short max_binding_iterations;
 unsigned short max_forwards;
 TimeBase::TimeT initial_iteration_delay;
 float backoff_ratio;
};
```

- `relative_expiry` limits the amount of time allowed to establish a binding. Set this member in 100-nanosecond units. The default value is infinity.
- `max_binding_iterations` limits the number of times the client tries to establish a binding. Set to -1 to specify unlimited retries. The default value is 5.

**Note:** If location forwarding requires that a new binding be established for a forwarded IOR, only one iteration is allowed to bind the new IOR. If the first binding attempt fails, the client reverts to the previous IOR. This allows a load balancing forwarding agent to redirect the client to another, more responsive server.

- `max_forwards` limits the number of forward tries that are allowed during binding establishment. Set to -1 to specify unlimited forward tries. The default value is 20.
- `initial_iteration_delay` sets the amount of time, in 100-nanosecond units, between the first and second tries to establish a binding. The default value is 0.1 seconds.
- `backoff_ratio` lets you specify the degree to which delays between binding retries increase from one retry to the next. The successive delays between retries form a geometric progression:

```
0,
initial_iteration_delay x backoff_ratio0,
initial_iteration_delay x backoff_ratio1,
initial_iteration_delay x backoff_ratio2,
...
initial_iteration_delay x backoff_ratio(max_binding_iterations - 2)
```

The default value is 2.

For example, the following code sets an `BindingEstablishmentPolicy` override on an object reference:

```
try{
 CORBA:Anybind_est_value;

 IT_CORBA:BindingEstablishmentPolicyValue val;
 val.re_expire = (TimeBase::TimeT)30 * 10000000; //30s
 val.max_rebinds = (CORBA::UShort)5; //5 binding tries
 val.max_forwards = (CORBA::UShort)20; //20 forwards
 val.initial_iteration_delay
 = (TimeBase::TimeT)1000000; //0.1s delay
 val.backoff_ratio = (CORBA::Float)2.0; //back-off
 ratio

 bind_est_value <= val;

 CORBA::PolicyList policies(1);
 policies.length(1);
 policies[0] = orb->create_policy(
 IT_CORBA::BINDING_ESTABLISHMENT_POLICY_D,
 bind_est_value
);

 CORBA::Object_var obj = slave->_set_policy_overrides(
 policies,
 CORBA::ADD_OVERRIDE
);

 lots_of_retries_slave = ClientPolicy::Slave::narrow(obj);
}
catch (CORBA::PolicyError& pe){
 return 1;
}
catch (CORBA::InvalidPolicies& ip){
 return 1;
}
catch (CORBA::SystemException& se){
 return 1;
}
```

**RelativeBindingExclusiveRoundtripTimeoutPolicy** limits the amount of time allowed to deliver a request and receive its reply, exclusive of binding attempts. The countdown begins immediately after a binding is obtained for the invocation. This policy's value is set in 100-nanosecond units.

**RelativeBindingExclusiveRequestTimeoutPolicy** limits the amount of time allowed to deliver a request, exclusive of binding attempts. Request delivery is considered complete when the last fragment of the GIOP request is sent over the wire to the target object. This policy's value is set in 100-nanosecond units.

**RelativeConnectionCreationTimeoutPolicy** specifies how much time is allowed to resolve each address in an IOR, within each binding iteration. Defaults to 8 seconds.

An IOR can have several `TAG_INTERNET_DP` (IIOP transport) profiles, each with one or more addresses, while each address can resolve via DNS to multiple IP addresses. Furthermore, each IOR can specify multiple transports, each with its own set of profiles.

This policy applies to each IP address within an IOR. Each attempt to resolve an IP address is regarded as a separate attempt to create a connection. The policy's value is set in 100-nanosecond units.

**InvocationRetryPolicy** applies to invocations that receive the following exceptions:

- A `TRANSIENT` exception with a completion status of `COMPLETED_NO` triggers a transparent reinvocation.
- A `COMM_FAILURE` exception with a completion status of `COMPLETED_NO` triggers a transparent rebind attempt.

A client's `InvocationRetryPolicy` is determined by the members of its `InvocationRetryPolicyValue`, which is defined as follows:

```
struct InvocationRetryPolicyValue
{
 unsigned short max_retries;
 unsigned short max_rebinds;
 unsigned short max_forwards;
 TimeBase::Time_t initial_retry_delay;
 float backoff_ratio;
};
```

- `max_retries` limits the number of transparent reinvocation that are attempted on receipt of a `TRANSPARENT` exception. The default value is 5.
- `max_rebinds` limits the number of transparent rebinds that are attempted on receipt of a `COMM_FAILURE` exception. The default value is 5.

**Note:** This setting is valid only if the effective `RebindPolicy` is `TRANSPARENT`; otherwise, no rebinding occurs.

- `max_forwards` limits the number of forward tries that are allowed for a given invocation. Set to -1 to specify unlimited forward tries. The default value is 20.
- `initial_retry_delay` sets the amount of time, in 100-nanosecond units, between the first and second retries. The default value is 0.1 seconds.

**Note:** The delay between the initial invocation and first retry is always 0.

This setting only affects the delay between transparent invocation retries; it has no affect on rebind or forwarding attempts.

- `backoff_ratio` lets you specify the degree to which delays between invocation retries increase from one retry to the next. The successive delays between retries form a geometric progression:

```
0,
initial_iteration_delay x backoff_ratio0,
initial_iteration_delay x backoff_ratio1,
initial_iteration_delay x backoff_ratio2,
...,
initial_iteration_delay x backoff_ratio(max_retries - 2)
```

The default value is 2.

For example, the following code sets an `InvocationRetryPolicy` override on an object reference:

```

try{
 CORBA:Any bts_of_retries_value;

 IT_CORBA::InvocationRetryPolicyValue val;
 valm ax_retries = (CORBA::UShort)10000; //10000 retries
 valm ax_rebinds = (CORBA::UShort)5; //5 rebinds
 valm ax_forwards = (CORBA::UShort)20; //20 forwards
 val initial_retry_delay
 = (TimeBase::Time)1000000; //0.1s delay
 val backoff_ratio = (CORBA::Float)2.0; //back-off
 ratio

 bts_of_retries_value <<= val;

 CORBA::PolicyList policies(1);
 policies.length(1);
 policies[0] = orb->create_policy(
 IT_CORBA::INVOCATION_RETRY_POLICY_D,
 bts_of_retries_value
);

 CORBA::Object_var obj = slave->_set_policy_overrides(
 policies,
 CORBA::ADD_OVERRIDE
);

 bts_of_retries_slave = ClientPolicy::Slave::_narrow(obj);
}

catch (CORBA::PolicyError& pe){
 return 1;
}
catch (CORBA::InvalidPolicies& ip){
 return 1;
}
catch (CORBA::SystemException& se){
 return 1;
}
}

```

---

# Implementing Callback Objects

Many CORBA applications implement callback objects on a client so that a server can notify the client of some event. You implement a callback object on a client exactly as you do on a server, by activating it in a client-side POA (see [“Activating CORBA Objects” on page 257](#)). This POA’s LifeSpanPolicy should be set to `TRANSIENT`. Thus, all object references that the POA exports are valid only as long as the POA is running. This ensures that a late server callback is not misdirected to another client after the original client shuts down.

It is often appropriate to use a client’s root POA for callback objects, inasmuch as it always exports transient object references. If you do so, make sure that your callback code is thread-safe; otherwise, you must create a POA with policies of `SINGLE_THREAD_MODEL` and `TRANSIENT`.



# Developing a Server

*This chapter explains how to develop a server that implements servants for CORBA objects.*

---

## Server tasks

A CORBA server performs these tasks:

- Uses a POA to map CORBA objects to servants, and to process client requests on those objects.
- Implements CORBA objects as POA servants.
- Creates and exports object references for these servants.
- Manages memory for POA servants and object references.
- Initializes and shuts down the runtime ORB.
- Passes parameters to server-side operations.

For an overview of server code requirements, see [“Enhancing Server Functionality” on page 74](#). Although throwing exceptions is an important aspect of server programming, it is covered separately in [Chapter 13](#).

For information on ORB initialization and shutdown, see [“ORB Initialization and Shutdown” on page 163](#).

---

## In this chapter

This chapter contains the following sections:

|                                               |
|-----------------------------------------------|
| <a href="#">POAs, Skeletons, and Servants</a> |
|-----------------------------------------------|

|                                        |
|----------------------------------------|
| Mapping Interfaces to Skeleton Classes |
| Creating a Servant Class               |
| Implementing Operations                |
| Activating CORBA Objects               |
| Handling Output Parameters             |
| Counting Servant References            |
| Delegating Servant Implementations     |
| Implementation Inheritance             |
| Interface Inheritance                  |
| Multiple Inheritance                   |
| Explicit Event Handling                |
| Termination Handler                    |
| Compiling and Linking                  |

---

# POAs, Skeletons, and Servants

CORBA objects exist in server applications. Objects are implemented, or *incarnated*, by language-specific *servants*. Objects and their servants are connected by the portable object adapter (POA). The POA provides the server-side runtime support that connects server application code to the networking layer of the ORB.

---

## POA tasks

A POA has these responsibilities:

- Create and destroy object references.
- Convert client requests into appropriate calls to application code.
- Synchronize access to objects.
- Cleanly start up and shut down applications.

For detailed information about the POA, see [Chapter 9](#).

---

## POA skeleton class

For each IDL interface, the IDL compiler generates a `POA_` skeleton class that you compile into the server application. Skeleton classes are abstract base classes. You implement skeleton classes in the server application code with servant classes, which define the behavior of the pure virtual methods that they inherit. Through a servant's inherited connection to a skeleton class, ORB runtime connects that servant back to the CORBA object that it incarnates.

---


## TIE class

The IDL compiler can also generate a TIE class, which lets you implement CORBA objects with classes that are unrelated (by inheritance) to skeleton classes. For more information, see [“Delegating Servant Implementations” on page 274](#).

**Note:** The `POA_` prefix only applies to the outermost naming scope of an IDL construct. So, if an interface is nested in a module, only the outermost module gets the `POA_` prefix; constructs nested inside the module do not have the prefix.

**Server request handling**

Figure 11 shows how a CORBA server handles an incoming client request, and the stages by which it dispatches that request to the appropriate servant. The server's ORB runtime directs an incoming request to the POA where the object was created. Depending on the POA's state, the request is either processed or blocked. A POA manager can block requests by rejecting them outright and raising an exception in the client, or by queueing them for later processing.



**Figure 11:** The server-side ORB conveys client requests to the POA via its manager, and the POA dispatches the request to the appropriate servant.

---

# Mapping Interfaces to Skeleton Classes

When the ORB receives a request on a CORBA object, the POA maps that request to an instance of the corresponding servant class and invokes the appropriate method. All operations are represented as virtual member methods, so dynamic binding ensures that the proper method in your derived servant class is invoked.

For example, interface `Account` is defined as follows:

```
module BankDemo
{
 typedef float CashAmount; //type represents cash
 typedef string AccountId; //Type represents account IDs
 // ...
 interface Account
 {
 exception InsufficientFunds {};

 readonly attribute AccountId account_id;
 readonly attribute CashAmount balance;

 void
 withdraw (in CashAmount amount)
 raises (InsufficientFunds);

 void
 deposit (in CashAmount amount);
 };
}
```

The IDL compiler maps the `Account` interface to skeleton class `POA_BankDem o:Account`. For purposes of simplification, only methods that map directly to IDL operations and attribute are shown:

```

namespace POA_BankDem o
{
 class Account :
 virtual public PortableServer::ServantBase
 {
 virtual :BankDem o:AccountId
 account_id() IT_THROW _DECL((CORBA::System Exception)) = 0;

 virtual :BankDem o:CashAmount
 balance() IT_THROW _DECL((CORBA::System Exception)) = 0;

 virtual void
 withdraw (
 :BankDem o:CashAmount amount
) IT_THROW _DECL((CORBA::System Exception,
 BankDem o:Account:InsufficientFunds)) = 0;

 virtual void
 deposit(
 :BankDem o:CashAmount amount
) IT_THROW _DECL((CORBA::System Exception)) = 0;
 };
}

```

The following points are worth noting about the skeleton class:

- `POA_BankDem o:Account` inherits from `PortableServer::ServantBase`. All skeleton classes inherit from the `ServantBase` class for two reasons:
  - ◆ `ServantBase` provides functionality that is common to all servants.
  - ◆ Servants can be passed generically—you can pass a servant for any type of object as a pointer or reference to `ServantBase`.
- The names of the skeleton class and the corresponding client-side proxy class are different. In this case, the fully scoped name of the skeleton class is `POA_BankDem o:Account`, while the proxy class name is `BankDem o:Account`.

This differentiation is important if client and server are linked into the same program, because it avoids name clashes for multiply defined symbols. It also preserves location transparency because it guarantees

that collocated calls are always dispatched by an intervening proxy object, and are never dispatched as a direct virtual method call from client to servant. So, if the server decides to delete an object and a collocated client attempts to make a call on the deleted object, the proxy raises an `OBJECT_NOT_EXIST` exception instead of attempting to access deallocated memory and causing the program to crash.

- The skeleton class defines methods that correspond to the interface operations and attributes.
- Methods are all defined as pure virtual, so you cannot instantiate a skeleton class. Instead, you must derive from the skeleton a concrete servant class that implements the pure virtual methods that it inherits.
- Each method has an exception specification. Orbix generates exception specifications only for skeleton classes. In this example, the methods throw system exceptions and, in the case of `withdraw()`, the user exception `InsufficientFunds`.
- The `throw` clause prevents methods from throwing illegal exceptions. For example, if `deposit()` throws an exception other than `CORBA::SystemException`, the C++ run time calls the `unexpected` method (which, by default, aborts the process).
- Apart from the exception specification, the signature of each skeleton class method is the same as the corresponding proxy class method. Identical signatures preserve location transparency. If the server and client are collocated, the proxy can delegate calls directly to the skeleton without translating or copying data. It also simplifies client and server application development in that one set of parameter passing rules apply to both.

## Creating a Servant Class

Each servant class inherits from a skeleton class. The following code defines servant class `AccountImpl`, which derives from skeleton class `POA_BankDemo::Account`. Unlike the skeleton class methods, the `AccountImpl` methods that map to IDL operations and attributes are not pure virtual, so a server can instantiate `AccountImpl` as a servant.

```
include "BankDemoS.hh" //Generated server-side header

class AccountImpl : public POA_BankDemo::Account {
public:
 //Inherited IDL operations

 virtual BankDemo::AccountId
 account_id() IT_THROW_DECL((CORBA::System Exception));

 virtual BankDemo::CashAmount
 balance() IT_THROW_DECL((CORBA::System Exception));

 virtual void
 withdraw (
 BankDemo::CashAmount amount
) IT_THROW_DECL((CORBA::System Exception,
 BankDemo::Account::InsufficientFunds));

 virtual void
 deposit(
 BankDemo::CashAmount amount
) IT_THROW_DECL((CORBA::System Exception));

 //other members here ...

private:
 //Prevent copying and assignment of servants
 AccountImpl(const AccountImpl &);
 void operator= (const AccountImpl &);
};
```

### Servant class requirements

The following requirements and recommendations apply to servant class definitions:

- The code must include the generated server header file—in this case, `BankDem.cs.h`.
- `AccountImpl` inherits from `POA_BankDem o:Account` through virtual inheritance. If, as in this case, the servant class inherits from only one source, it is unimportant to specify virtual inheritance. However, a servant class that inherits from multiple skeleton classes should always use virtual inheritance to prevent errors.
- The choice of name for servant classes is purely a matter of convention. The examples here and elsewhere apply the `Impl` suffix to the original interface name, as in `AccountImpl`. It is always good practice to have a naming convention and use it consistently in your code.
- The copy constructor and assignment operator for the servant class are private to prevent copying and assignment of servant instances. Servants should not be copied or assigned; only one servant should incarnate any given CORBA object; otherwise, it is unclear which servant should handle requests for that object. It is always good practice to hide a servant's copy constructor and assignment operator.

The preceding `AccountImpl` class is a complete and functional servant class. It only remains to implement the pure virtual methods that are inherited from the skeleton. You can also add other member variables and methods, public and private, that can help implement a servant. For example, it is typical to add a constructor and destructor, and private member variables to hold the state of the object while the servant is in memory.

## Implementing Operations

Most work in developing a servant consists of implementing each inherited pure virtual method. Because the application code controls the body of each operation, it largely determines the application's overall behavior. The following code outlines an implementation of the `withdraw()` method:

```
void
AccountIn pl:withdraw (
 BankDem o:CashAm ountam ount
)IT_THROW _DECL((
 CORBA::System Exception,
 BankDem o:Account:InsufficientFunds
))
{
 // ...database connection (via PSS) code omitted here

 //get a PSS reference to corresponding database object
 IT_PSS_RefVar< BankDem oStore_AccountBaseRef> ref=
 my_state(accounts_home_objin());

 BankDem o:CashAm ountnew_balance = ref-> balance()-am ount;

 if (new_balance < 0.0F)
 {
 cout<< "throwing InsufficientFunds"<< endl;
 throw BankDem o:Account:InsufficientFunds();
 }

 ref-> balance(new_balance);
 // ...

 cout<< "withdrew $"<< am ount<< endl;
}
```

---

# Activating CORBA Objects

In order to enable clients to invoke on CORBA operations, a server must create and export object references. These object references must point back to a CORBA object that is active through its incarnation by a C++ or Java servant.

Activation of a CORBA object is a two-step process:

1. Instantiate the CORBA object's servant. Instantiating a servant does not by itself activate the CORBA object. The ORB runtime remains unaware of the existence of the servant and the corresponding CORBA object.
2. Register the servant and the object's ID in a POA.

---

## **this()**

The simplest way to activate a CORBA object is by calling `_this()` on the servant. The IDL compiler generates a `_this()` method for each servant skeleton class. `_this()` performs two separate tasks:

- Checks the POA to determine whether the servant is registered with an existing object. If not, `_this()` creates an object from the servant's interface, registers a unique ID for this object in the POA's active object map, and maps this object ID to the servant's address.
- Generates and returns an object reference that includes the object's ID and POA identifier.

In other words, the object is implicitly activated in order to return an object reference.

---

## **servant\_to\_reference()**

You can also implicitly activate an object by calling `servant_to_reference()` on the desired POA. This requires you to narrow to the appropriate object; however, there can be no ambiguity concerning the POA in which the object is active, as can happen through using `_this()` (see [page 306](#)).

---

**Explicit activation methods**

Alternatively, you can explicitly activate a CORBA object: call `activate_object()` or `activate_object_with_id()` on the POA. You can then obtain an object reference by calling `_this()` on the servant. Because the servant is already registered in the POA with an object ID, the method simply returns an object reference.

The ability to activate an object implicitly or explicitly depends on a POA's activation policy. For more information on this topic, see [“Using POA Policies” on page 294](#).

**Note:** The object reference returned by `_this()` is independent of the servant itself; you must eventually call `release()` on the object or hold it in a `_var` reference in order to avoid resource leaks. Releasing the object reference has no effect on the corresponding servant.

---

# Handling Output Parameters

---

## Server-side rules

Server-side rules for passing output (`inout`) parameters and return values to the client complement client-side rules. For example, if the client is expected to deallocate a variable-length return value, the server must allocate that value.

In general, these rules apply:

- If the type to pass is variable-length, the server dynamically allocates the value and the client deallocates it.
- String, reference, and variable-length array types are dynamically allocated and deallocated by the client. Strings and references can be reallocated by the server.

Other types are passed by value or reference.

The following sections show the server-side rules for passing output parameters and return values of various IDL types.

## Simple Parameters

Simple IDL types such as `short` or `long` are passed by value. For example, the following IDL defines operation `Example::op()`, which passes three `long` parameters:

```
interface Example {
 long
 op(in long in_p, inout long inout_p, out long out_p);
};
```

The corresponding servant class contains this signature for `op()`:

```
virtual CORBA::Long
op(
 CORBA::Long in_p,
 CORBA::Long & inout_p,
 CORBA::Long_out out_p
) throw (CORBA::SystemException);
```

### Implementation example

This example has the same mapping as the client, where `CORBA::Long_out` type is simply an alias for `CORBA::Long &`. You might implement this operation as follows:

```
CORBA::Long
ExampleImpl::op(
 CORBA::Long in_p, CORBA::Long & inout_p, CORBA::Long_out out_p
) throw (CORBA::SystemException)
{
 inout_p = 2 * inout_p; //Change inout_p.
 out_p = in_p * in_p; //Set out_p
 return in_p / 2; //Return in_p
}
```

The method simply sets output parameters and return values; the changes are automatically propagated back to the client.

## Fixed-Length Complex Parameters

Fixed-length complex parameters are passed by value or by reference. For example, the following IDL defines a fixed-length structure that operation `Example::op()` uses in its return value and parameters:

```
struct FLS { //Fixed-Length Structure
 long long_val;
 double double_val;
};

interface Example {
 FLS op(in FLS in_p, inout FLS inout_p, out FLS out_p);
};
```

The corresponding servant class contains this signature for `op()`:

```
typedef FLS & FLS_out;
// ...
virtual FLS
op(const FLS & in_p, FLS & inout_p, FLS_out out_p)
throw (CORBA::SystemException);
```

### Implementation example

The following code implements the servant operation. No memory management issues arise; the method simply assigns the values of output parameters and the return value:

```
FLS
ExampleInpl::op(const FLS & in_p, FLS & inout_p, FLS_out out_p)
throw (CORBA::SystemException)
{
 cout << in_p.long_val << endl; //Use in_p
 cout << in_p.double_val << endl; //Use in_p
 cout << inout_p.double_val << endl; //Use inout_p
}
```

```
//Change inout_p
inout_p.double_val= inout_p.long_val* in_p.double_val;

out_p.long_val= 99; //Initialize out_p
out_p.double_val= 3.14;

FIS ret_val= { 42, 42.0 }; //Initialize return value
return ret_val;
}
```

## Fixed-Length Array Parameters

Fixed-length arrays are passed as pointers to array slices. The return value is dynamically allocated. For example, the following IDL defines a fixed-length array that operation `Example::op()` uses in its return value and parameters:

```
typedef long Larr[3];

interface Example {
 Larr op(in Larr in_p, inout Larr inout_p, out Larr out_p);
};
```

The corresponding servant class contains this signature for `op()`:

```
typedef CORBA::Long Larr[3];
typedef CORBA::Long Larr_slice;
typedef Larr_slice * Larr_out;
// ...
virtual Larr_slice *
op(const Larr in_p, Larr_slice * inout_p, Larr_out out_p)
throw (CORBA::SystemException);
```

### Implementation example

In the following implementation, the generated `Larr_alloc()` method dynamically allocates the return value:

```
Larr_slice *
ExampleImpl::
op(const Larr in_p, Larr_slice * inout_p, Larr_out out_p)
throw (CORBA::SystemException)
{
 int len = sizeof(in_p) / sizeof(*in_p);

 //Use incoming values of in_p and inout_p...

 //Modify inout_p
 inout_p[1] = 12345;
```

```
// initialize out_p
for (int i = 0; i < len; i++)
 out_p[i] = i * i;

// Return value must be dynamically allocated
Larr_slice * ret_val = new Larr_alloc();
for (int i = 0; i < len; i++)
 ret_val[i] = i * i * i;

return ret_val;
}
```

---

## String Parameters

String-type output parameters and return values must be dynamically allocated. For example, the following IDL defines a fixed-length array that operation `Example:op()` uses in its return value and parameters:

```
interface Example {
 string op(
 in string in_p,
 inout string inout_p,
 out string out_p
);
};
```

The corresponding servant class contains this signature for `op()`:

```
virtual const char*
op(
 const char* in_p,
 char* & inout_p,
 CORBA::String_out out_p
) throw (CORBA::SystemException);
```

### Memory requirements

The server is constrained by the same memory requirements as the client:

- Strings are initialized as usual.
- `inout` strings are dynamically allocated and initialized by the client. The servant can change an `inout` string by modifying the bytes of the `inout` string in place, or shorten the `inout` string in place by writing a terminating NUL byte into the string. To return an `inout` string that is longer than the initial value, the servant must deallocate the original copy and allocate a longer string.
- `out` strings must be dynamically allocated.
- Return value strings must be dynamically allocated.

### Implementation example

The following code implements the servant operation:

```

const char*
Example::
op(
 const char* in_p,
 char* & inout_p,
 CORBA::String_out out_p
) throw (CORBA::System Exception)
{

 cout << in_p << endl; //Show in_p
 cout << inout_p << endl; //Show inout_p

 //Modify inout_p in place:
 //
 char* p = inout_p;
 while (*p != '\0')
 toupper(*p++);

 //OR make a string shorter by writing a terminating NUL:
 //
 *inout_p = '\0'; //Set to empty string.

 //OR deallocate the initial string and allocate a new one:
 //

 CORBA::string_free(inout_p);
 inout_p = CORBA::string_dup("New string value");

 //out strings must be dynamically allocated.
 //
 out_p = CORBA::string_dup("I am an output parameter");

 //Return value strings must be dynamically allocated.
 //
 char* ret_val
 = CORBA::string_dup("In Xanadu did Kubla Khan...");

 return ret_val;
}

```

## Variable-Length Complex Parameters

out parameters and return values of variable-length complex types must be dynamically allocated; in and inout parameters are passed by reference.

For example, the following IDL defines a variable-length structure that operation `Example::op()` uses in its return value and parameters:

```
struct VLS { //Variable-length structure
 long long_val;
 string string_val;
};

interface Example {
 VLS op(in VLS in_p, inout VLS inout_p, out VLS out_p);
};
```

The corresponding servant class contains this signature for `op()`:

```
class VLS_out { /* ... */};
// ...
virtual VLS *
op(const VLS & in_p, VLS & inout_p, VLS_out out_p)
throw (CORBA::SystemException);
```

### Implementation example

The following code implements the servant operation:

```
VLS *
ExampleImpl::
op(const VLS & in_p, VLS & inout_p, VLS_out out_p)
throw (CORBA::SystemException)
{
 cout << in_p.string_val << endl; //Use in_p
 cout << inout_p.long_val << endl; //Use inout_p
 inout_p.long_val = 99; //Modify inout_p
 out_p = new VLS; //Allocate outparam
 out_p->long_val = 1; //Initialize...
 out_p->string_val = CORBA::string_dup("One");
```

```
VLS *ret_val= new VLS; //Allocate return value
ret_val->long_val= 2; //initialize...
ret_val->string_val= CORBA::string_dup("Two");

return ret_val;
}
```

## Variable-Length Array Parameters

Like fixed-length arrays, variable-length arrays are passed as pointers to array slices. `out` parameters and the return value must be dynamically allocated.

For example, the following IDL defines a variable-length array that operation `Example::op()` uses in its return value and parameters:

```
typedef string Sarr[3];

interface Example {
 Sarr op(in Sarr in_p, inout Sarr inout_p, out Sarr out_p);
};
```

The corresponding servant class contains this signature for `op()`:

```
typedef CORBA::String_m grSarr[3];
typedef CORBA::String_M grSarr_slice;
class Sarr_out { /* ... */};
// ...
virtual Sarr_slice * op(
 const Sarr in_p, Sarr_slice * inout_p, Sarr_out out_p
) throw (CORBA::SystemException);
```

### Implementation example

The following code implements the servant operation. As with all nested strings, string elements behave like a `string_var`, so assignments make deep copies or, if a pointer is assigned, take ownership:

```
typedef CORBA::String_m grSarr[3];
typedef CORBA::String_M grSarr_slice;
class Sarr_out;
// ...

Sarr_slice *
ExampleImpl::
op(
 const Sarr in_p, Sarr_slice * inout_p, Sarr_out out_p
) throw (CORBA::SystemException)
```

```
{
 cout << in_p[1] << endl; //Use in_p
 cout << inout_p[0] << endl; //Use inout_p
 inout_p[1] = in_p[0]; //Modify inout_p

 out_p = Sarr_alloc(); //Allocate outparam
 out_p[0] = CORBA::string_dup("In Xanadu did Kubla Khan");
 out_p[1] = CORBA::string_dup("A stately pleasure-dome
 out_p[2] = CORBA::string_dup("decree:W here Alph...");

 //Allocate return value and initialize...
 //
 Sarr_slice *ret_val = Sarr_alloc();
 ret_val[0] = out_p[0];
 ret_val[1] = inout_p[1];
 ret_val[2] = in_p[2];

 return ret_val; //Poor Coleridge...
}
```

---

## Object Reference Parameters

Object references are passed as `_ptr` references. The following memory management rules apply to object reference parameters:

- `in` parameters are initialized by the caller and must not be released; the caller retains ownership of the `in` parameter.
- `inout` parameters are initialized by the caller. To change the value of an `inout` parameter, you must call `release()` on the original value and use `_duplicate()` to obtain the new value.
- `out` parameters and return values must be allocated by `_duplicate()` or `_this()`, which calls `_duplicate()` implicitly.

For example, the following IDL defines interface `Example`; operation `Example::op()` specifies this interface for its return value and parameters:

```
interface Example {
 string greeting();
 Example op(
 in Example in_p,
 inout Example inout_p,
 out Example out_p
);
};
```

The corresponding servant class contains this signature for `op()`:

```
class Example_out { /* ... */ };
// ...
virtual Example_ptr op(
 Example_ptr in_p, Example_ptr& inout_p, Example_out out_p
) throw (CORBA::SystemException);
```

### Implementation example

The following implementation dynamically allocates the new value of `inout_p` after releasing the previous value. The return value is dynamically allocated because `_this()` calls `_duplicate()` implicitly.

As shown in this example, you should always test for `nil` before making a call on a passed `in` or `inout` reference. Otherwise, your servant is liable to make a call on a `nil` reference and cause a core dump.

```

Example_ptr
Example_ptr::
op(
 Example_ptr in_p, Example_ptr& inout_p, Example_ptr out_p
) throw (CORBA::SystemException)
{
 //Use in_p.
 //
 if (CORBA::is_nil(in_p)) {
 CORBA::String_var s = in_p->greeting();
 cout << s << endl;
 }

 //Use inout_p.
 //
 if (CORBA::is_nil(inout_p)) {
 CORBA::String_var s = inout_p->greeting();
 cout << s << endl;
 }

 //Modify inout_p to be the same as in_p.
 //
 CORBA::release(inout_p); //First deallocate,
 inout_p = Example_ptr::duplicate(in_p); //then assign.

 //Set return value.
 //
 return *_this(); //Return reference to self.
}

```

**Note:** This example is unrealistic in returning a reference to self, because in order to invoke the operation, the caller must hold a reference to this object already.

---

# Counting Servant References

Multi-threaded servers need to reference-count their servants in order to avoid destroying a servant on one thread that is still in use on another. In general, you should enable reference counting for servants that are activated in a POA with a policy of `ORB_CTRL_MODEL`.

## Enabling reference counting

The POA specification provides the standard methods `_add_ref()` and `_remove_ref()` to support reference counting, but by default they do nothing. You can enable reference counting by inheriting the standard class `PortableServer::RefCountServantBase` in servant implementations. For example:

```
class BankDem o_AccountImpl
:public virtual POA_BankDem o::Account,
public virtual PortableServer::RefCountServantBase
```

## Implicit reference counting

With reference counting enabled, the POA calls `_add_ref()` when it holds a pointer to a servant in any thread, and calls `_remove_ref()` when it is finished with that servant. POA methods that return servants to user code call `_add_ref()` before they deliver the servant, so the same code should call `_remove_ref()` on the result when it is finished.

## Explicit reference counting

In your own code, you should call `_add_ref()` for each additional pointer to a servant, and `_remove_ref()` when you are done with that pointer (rather than delete it). Doing so ensures that the servant is deleted when no pointers are held to that servant either in your own code or in the POA. Reference counting is ignored by tie-based servants. Tie templates, as defined in the POA standard, do not support reference counting. Therefore, it is not recommended that you use the tie approach for multi-threaded servers.

---

# Delegating Servant Implementations

Previous examples show how Orbix uses inheritance to associate servant classes and their implementations with IDL interfaces. By inheriting from IDL-derived skeleton classes, servants establish their connection to the corresponding IDL interfaces, and thereby make themselves available to client requests.

Alternatively, you can explicitly associate, or *tie* a servant and its operations to the appropriate IDL interface through tie template classes. The tie approach lets you implement CORBA objects with classes that are unrelated (by inheritance) to skeleton classes.

In most cases, inheritance and tie approaches are functionally equivalent; only programming style preferences determine whether to favor one approach over the other. For more on the comparative merits of each approach, see [“Tie versus inheritance” on page 275](#).

## Creating tie-based servants

Tie-based servants rely on two components:

- A *tie object* implements the CORBA object; however, unlike the inherited approach, the class that it instantiates does not inherit from any of the IDL-generated base skeleton classes.
- A *tie servant* instantiates a tie template class, which the IDL compiler generates when you run it with the `-XTIE` switch. The POA regards a tie servant as the actual servant of an object. Thus, all POA operations on a servant such as `activate_object()` take the tie servant as an argument. The tie servant receives client invocations and forwards them to the tie object.

To create a tie servant and associate it with a tie object:

- 
- 1 Instantiate the tie object
- 
- 2 Pass the tie object's address to the tie object constructor with this syntax:

```
tie-template-class<impl-class> tie-servant(tied-object);
```

**Example**

For example, given an IDL specification that includes interface `BankDem o::Bank`, the IDL compiler can generate tie template class `POA_BankDem o::Bank_tie`. This class supplies a number of operations that enable its tie servant to control the tie object.

Given implementation class `BankImpl`, you can instantiate a tie object and create tie servant `bank_srv_tie` for it as follows:

```
// instantiate tie object and create its tie servant
POA_BankDem o::Bank_tie< BankImpl> bank_srv_tie(new BankImpl);
```

Given this tie servant, you can use it to create an object reference:

```
// create an object reference for bank servant
bank_varbankref = bank_srv_tie_this();
```

When the POA receives client invocations on the `bankref` object, it relays them to tie servant `bank_srv_tie`, which delegates them to the bank tie object for processing.

**Removing tie objects and servants**

You remove a tie servant from memory like any other servant—for example, with `PortableServer::POA::deactivate_object()`. If the tie servant's tie object implements only a single object, the tie object is also removed.

**Tie versus inheritance**


The tie approach can be useful where implementations must inherit from an existing class framework, as often occurs with OODB systems. In this case, you can create object implementations only with the tie approach. Otherwise, the tie approach has several drawbacks:

- Because the tie approach requires two C++ instances for each CORBA object, it uses up more resources.
- Tie-based servants ignore reference counting; therefore, you should not use the tie approach for multi-threaded servers.
- The tie approach adds an unnecessary layer of complexity to application code.

In general, unless you have a compelling reason to use the tie approach, you should favor the inheritance approach in your code.

## Implementation Inheritance

IDL inheritance does not constrain your options for implementing servant classes. In [Figure 12](#), shaded classes represent the skeleton abstract base classes generated by the IDL compiler; non-shaded classes represent the servant classes that you provide




**Figure 12:** A servant class can inherit base class implementations.

`CheckingAccountIn.pl` inherits from `AccountIn.pl`, so `CheckingAccountIn.pl` needs only to implement the two pure virtual methods that it inherits from `CheckingAccount`: `overrideInIt()` and `orderCheckBook()`. Functions in base interface `Account` such as `balance()` are already implemented in and inherited from `AccountIn.pl`.

# Interface Inheritance

You can choose not to derive `CheckingAccountImpl()` from `AccountImpl()`. If all methods in `POA_BankDemo::CheckingAccount` are defined as pure virtual, then `CheckingAccountImpl` must implement the methods that it inherits from `POA_BankDemo::Account`, as well as those inherited from `POA_BankDemo::CheckingAccount`, as shown in [Figure 13](#)




**Figure 13:** A servant class can implement operations of all base skeleton classes.

Interface inheritance facilitates encapsulation. With interface inheritance, the derived class servant is independent of the base class servant. This might be desirable if you plan to split a single server into two servers: one that implements base objects and another that implements derived objects. This model also serves any application design that requires all base classes to be abstract, while it retains interface inheritance.

## Multiple Inheritance

Implementation and interface inheritance extend to multiple inheritance. In [Figure 14](#), solid arrows indicate inheritance that is mandated by the C++ mapping. The dotted arrows indicate that the servants allow either implementation or interface inheritance.

Given this hierarchy, it is also possible to leave `POA_BankDem o::Account` without an implementation, inasmuch as it is an IDL abstract base class. In this case, `CheckingAccountImpl` and `SavingsAccountImpl` must provide the required virtual method implementations.



**Figure 14:** Inheritance options among servant and base skeleton classes.

---

# Explicit Event Handling

When you call `ORB::run()`, the ORB gets the thread of control to dispatch events. This is acceptable for a server that only processes CORBA requests. However, if your process must also support a GUI or uses another networking stack, you also must be able to monitor incoming events that are not CORBA client requests.

The ORB interface methods `work_pending()` and `perform_work()` let you poll the ORB's event loop for incoming requests:

- `work_pending()` returns true if the ORB's event loop has at least one request ready to process.
- `perform_work()` processes one or more requests before it completes and returns the thread of control to the application code. The amount of work processed by this call depends on the threading policies and the number of queued requests; however, `perform_work()` guarantees to return periodically so you can handle events from other sources.

---

# Termination Handler

Orbix provides its own `IT_TerminationHandler` class, which enables server applications to handle delivery of `Ctrl-C` and similar events in a portable manner. On UNIX, the termination handler handles the following signals:

```
SIGINT
SIGTERM
SIGQUIT
```

On Windows, the termination handler is just a wrapper around `SetConsoleCtrlHandler`, which handles delivery of the following control events:

```
CTRL_C_EVENT
CTRL_BREAK_EVENT
CTRL_SHUTDOWN_EVENT
CTRL_LOGOFF_EVENT
CTRL_CLOSE_EVENT
```

You can create only one termination handler object in a program.

---

## Example

In the following example, the main routine creates a termination handler object on the stack. On POSIX platforms, it is critical to create this object in the main thread before creation of any other thread, especially before calling `ORBinit()`. The `IT_TerminationHandler` destructor deregisters the callback, in order to avoid calling it during static destruction.

```
static void
termination_handler_callback(
 long signal
)
{
 int
main(int argc, char** argv)
{
 IT_TerminationHandler
 termination_handler(termination_handler_callback);
}
```

```
cout << "Processing shutdown signal" << signal << endl;
if (CORBA::is_nil(orb))
{
 cout >> "ORB shutdown ..." << flush;
 orb->shutdown(II_FALSE);
 cout << "done." << endl;
}
}
```

---

## Compiling and Linking

Server compile and link requirements are almost the same as the client, except that it also requires the server-side skeleton code, which has the format `idl-nameS.cxx`—for example, `BankDemOS.cxx`. You also must link with the `poa` library, which contains the server-side run-time support for the POA.

Details for compiling and linking a server differ among platforms. For more information about platform-specific compiler flags and libraries, refer to the demo makefiles in your Orbix distribution.

# Managing Server Objects

*A portable object adapter, or POA, maps CORBA objects to language-specific implementations, or servants, in a server process. All interaction with server objects takes place via the POA.*

A POA identifies objects through their object IDs, which are encapsulated within the object requests that it receives. Orbix views an object as *active* when its object ID is mapped to a servant; the servant is viewed as *incarnating* that object. By abstracting an object's identity from its implementation, a POA enables a server to be portable among different implementations.

---

**In this chapter**


This chapter shows how to create and manage a POA within a server process, covering the following topics:

|                                             |                          |
|---------------------------------------------|--------------------------|
| <a href="#">Mapping Objects to Servants</a> | <a href="#">page 285</a> |
| <a href="#">Creating a POA</a>              | <a href="#">page 287</a> |
| <a href="#">Using POA Policies</a>          | <a href="#">page 294</a> |
| <a href="#">Explicit Object Activation</a>  | <a href="#">page 305</a> |
| <a href="#">Implicit Object Activation</a>  | <a href="#">page 306</a> |

|                                               |                          |
|-----------------------------------------------|--------------------------|
| <a href="#">Managing Request Flow</a>         | <a href="#">page 311</a> |
| <a href="#">Work Queues</a>                   | <a href="#">page 313</a> |
| <a href="#">Controlling POA Proxification</a> | <a href="#">page 323</a> |

# Mapping Objects to Servants

Figure 15 shows how a POA manages the relationship between CORBA objects and servants, within the context of a client request. A client references an object or invokes a request on it through an interoperable object reference (IOR). This IOR encapsulates the information required to find the object, including its server address, POA, and object ID—in this case, A. On receiving the request, the POA uses the object's ID to find its servant. It then dispatches the requested operation to the servant via the server skeleton code, which extracts the operation's parameters and passes the operation as a language-specific call to the servant.



**Figure 15:** A portable object adapter (POA) maps abstract objects to their concrete implementations (servants)

Depending on a POA's policies, a servant can be allowed to incarnate only one object; or it can incarnate multiple objects. During an object's lifetime, it can be activated multiple times by successive servant incarnations.

---

### Mapping options

A POA can map between objects and servants in several ways:

- An *active object map* retains object-servant mappings throughout the lifetime of its POA, or until an object is explicitly deactivated. Before a POA is activated, it can anticipate incoming requests by mapping known objects to servants, and thus facilitate request processing.
- A *servant manager* maps objects to servants on demand, either on the initial object request, or on every request. Servant managers can enhance control over servant instantiation, and help avoid or reduce the overhead incurred by a static object-servant mapping.
- A single *default servant* can be used to handle all object requests. A POA that uses a default servant incurs the same overhead no matter how many objects it processes.

Depending on its policies, a POA can use just one object-mapping method, or several methods in combination. For more information, see [“Enabling the Active Object Map” on page 295](#).

---

## Creating a POA

All server processes in a location domain use the same root POA, which you obtain by calling `resolve_initial_references("POA")`. The root POA has predefined policies which cannot be changed (see [page 293](#)). Within each server process, the root POA can spawn one or more child POAs. Each child POA provides a unique namespace; and each can have its own set of policies, which determine how the POA implements and manages object-servant mapping. Further, each POA can have its own POA manager and servant manager.

---

### Using multiple POAs

A number of objectives can justify the use of multiple POAs within the same server. These include:

- *Partition the server into logical or functional groups of servants.* You can associate each group with a POA whose policies conform with the group's requirements. For example, a server that manages Customer and Account servants can provide a different POA for each set of servants.

You can also group servants according to common processing requirements. For example, a POA can be configured to generate object references that are valid only during the lifespan of that POA, or across all instantiations of that POA and its server. POAs thus offer built-in support for differentiating between persistent and transient objects.

- *Independently control request processing for sets of objects.* A POA manager's state determines whether a POA is active or inactive; it also determines whether an active POA accepts incoming requests for processing, or defers them to a queue (see ["Processing Object Requests" on page 296](#)). By associating POAs with different managers, you can gain finer control over object request flow.
- *Choose the method of object-servant binding that best serves a given POA.* For example, a POA that processes many objects can map all of them to the same default servant, incurring the same overhead no matter how many objects it processes.

**Procedure for creating a POA**

---

Creating a POA consists of these steps:

1. Set the POA policies.  
Before you create a POA, establish its desired behavior through a CORBA PolicyList, which you attach to the new POA on its creation. Any policies that are explicitly set override a new POA's default policies (refer to [Table 12 on page 290](#)).
2. Create the POA by calling `create_POA()` on an existing POA.
3. If the POA has a policy of `USE_SERVANT_MANAGER`, register its servant manager by calling `set_servant_manager()` on the POA.
4. Enable the POA to receive client requests by calling `activate()` on its POA manager.

---

## Setting POA Policies

A new POA's policies are set when it is created. You can explicitly set a POA's policies through a CORBA PolicyList object, which is a sequence of Policy objects.

### Creating Policy objects

The `PortableServer:POA` interface provides factories to create CORBA Policy object types (see [Table 12 on page 290](#)). If a Policy object type is proprietary to Orbix, you must create the Policy object by calling `create_policy()` on the ORB (see [“Setting proprietary policies for a POA” on page 291](#)). In all cases, you attach the PolicyList object to the new POA. All policies that are not explicitly set in the PolicyList are set to their defaults.

For example, the following code creates policy objects of `PERSISTENT` and `USER_ID`:

```
CORBA::PolicyList policies;
policies.length (2);
policies[0] = poa-> create_lifespan_policy
(PortableServer:PERSISTENT)
policies[1] = poa-> create_id_assignment_policy
(PortableServer:USER_ID)
```

With the `PERSISTENT` policy, a POA can create object references that remain valid across successive instantiations of this POA and its server process. The `USER_ID` policy requires the application to autoassign all object IDs for a POA.

### Attaching policies to a POA

After you create a PolicyList object, you attach it to a new POA by supplying it as an argument to `create_POA()`. The following code creates POA `persistentPOA` as a child of the root POA, and attaches to it the PolicyList object just shown:

```
//get an object reference to the rootPOA
CORBA::Object_var obj =
 orb-> resolve_initial_references("RootPOA");
PortableServer::POA_var poa = POA::_narrow(obj);
```

```

//create policy object
CORBA::PolicyList policies;
policies.length (2);

//set policy object with desired policies
policies[0] = poa-> create_lifespan_policy
(PortableServer:PERSISTENT)
policies[1] = poa-> create_id_assignment_policy
(PortableServer:USER_ID)

//create a POA for persistent objects
poa = poa-> create_POA("persistentPOA",NULL,policies);

```

In general, POA policies let you differentiate among various POAs within the same server process, where each POA is defined in a way that best accommodates the needs of the objects that it processes. For example, a server process that contains the POA `persistentPOA` might also contain a POA that supports only transient object references, and only handles requests for callback objects.

**Note:** Orbix automatically removes policy objects when they are no longer referenced by any POA.

## POA Policy factories

The `PortableServer:POA` interface contains factory methods for creating CORBA Policy objects:

**Table 12:** POA policy factories and argument options

| POA policy factories                             | Policy options                                                                    |
|--------------------------------------------------|-----------------------------------------------------------------------------------|
| <code>create_id_assignment_policy()</code>       | <code>SYSTEM_ID</code> (default)<br><code>USER_ID</code>                          |
| <code>create_id_uniqueness_policy()</code>       | <code>UNIQUE_ID</code> (default)<br><code>MULTIPLE_ID</code>                      |
| <code>create_implicit_activation_policy()</code> | <code>NO_IMPLICIT_ACTIVATION</code> (default)<br><code>IMPLICIT_ACTIVATION</code> |
| <code>create_lifespan_policy()</code>            | <code>TRANSIENT</code> (default)<br><code>PERSISTENT</code>                       |

Table 12: POA policy factories and argument options

| POA policy factories                            | Policy options                                                                                                                     |
|-------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------|
| <code>create_request_processing_policy()</code> | <code>USE_ACTIVE_OBJECT_MAP_ONLY</code> ( <i>default</i> )<br><code>USE_DEFAULT_SERVANT</code><br><code>USE_SERVANT_MANAGER</code> |
| <code>create_servant_retention_policy()</code>  | <code>RETAIN</code> ( <i>default</i> )<br><code>NON_RETAIN</code>                                                                  |
| <code>create_thread_policy()</code>             | <code>ORB_CTRL_MODEL</code> ( <i>default</i> )<br><code>SINGLE_THREAD_MODEL</code>                                                 |

For specific information about these methods, refer to their descriptions in the *CORBA Programmer's Reference*.

### Setting proprietary policies for a POA

Orbix provides several proprietary policies to control POA behavior. To set these policies, call `create_policy()` on the ORB to create Policy objects with the desired policy value, and add these objects to the POA's `PolicyList`. For example, Orbix provides policies that determine how a POA handles incoming requests for any object as it undergoes deactivation. You can specify a `DISCARD` policy for a POA so it discards all incoming requests for deactivating objects:

```

CORBA::PolicyList policies;
policies.length (1);
CORBA::Any obj_deactivation_policy_value;
obj_deactivation_policy_value <<= IT_PortableServer::DISCARD;

policies[0] = orb->create_policy(
 (IT_PortableServer::OBJECT_DEACTIVATION_POLICY_ID,
 obj_deactivation_policy_value);

```

### Orbix-proprietary policies

You can attach the following Orbix-proprietary Policy objects to a POA's `PolicyList`:

**ObjectDeactivationPolicy** controls how the POA handles requests that are directed at deactivating objects. This policy is valid only for a POA that uses a servant activator to control object activation. For more information, see [“Setting deactivation policies” on page 333](#).

**PersistenceModePolicy** can specify a policy of `DIRECT_PERSISTENCE`, so that the POA uses a well-known address in the IORs that it generates for persistent objects. This policy is valid only for a POA that has a `PERSISTENT` lifespan policy. For more information, see [“Direct persistence” on page 298](#).

**WellKnownAddressingPolicy** sets transport configuration data—for example, address information for persistent objects that use a well-known address, or IIOp buffer sizes. For more information, see [“Direct persistence” on page 298](#).

**DispatchWorkQueuePolicy** specifies the work queue used to process requests for a POA whose threading policy is set to `ORB_CTRL_MODEL`. All requests for the POA are dispatched in a thread controlled by the specified work queue. For more information, see [“Work Queues” on page 313](#).

**WorkQueuePolicy** specifies the work queue used by network transports to read requests for the POA. For more information, see [“Work Queues” on page 313](#).

**InterdictionPolicy** disables the proxification of the POA when using the Iona firewall proxy service. A POA with this policy set to `DISABLE` will never be proxified. For more information, see [“Controlling POA Proxification” on page 323](#).

---

## Root POA Policies

The root POA has the following policy settings, which cannot be changed:

| <b>Policy</b>       | <b>Default setting</b>     |
|---------------------|----------------------------|
| Id Assignment       | SYSTEM_ID                  |
| Id Uniqueness       | UNIQUE_ID                  |
| Implicit Activation | IMPLICIT_ACTIVATION        |
| Lifespan            | TRANSIENT                  |
| Request Processing  | USE_ACTIVE_OBJECT_MAP_ONLY |
| Servant Retention   | RETAIN                     |
| Thread              | ORB_CTRL_MODEL             |

---

# Using POA Policies

**Overview**

---

A POA's policies play an important role in determining how the POA implements and manages objects and processes client requests. While the root POA has a set of predefined policies that cannot be changed, any POA that you create can have its policies explicitly set.

---

**In this section**

The following sections describe POA policies and setting options:

|                                                            |                          |
|------------------------------------------------------------|--------------------------|
| <a href="#">Enabling the Active Object Map</a>             | <a href="#">page 295</a> |
| <a href="#">Processing Object Requests</a>                 | <a href="#">page 296</a> |
| <a href="#">Setting Object Lifespan</a>                    | <a href="#">page 298</a> |
| <a href="#">Assigning Object IDs</a>                       | <a href="#">page 301</a> |
| <a href="#">Activating Objects with Dedicated Servants</a> | <a href="#">page 302</a> |
| <a href="#">Activating Objects</a>                         | <a href="#">page 303</a> |
| <a href="#">Setting Threading Support</a>                  | <a href="#">page 304</a> |

---

## Enabling the Active Object Map

A POA's servant retention policy determines whether it uses an active object map to maintain servant-object associations. Depending on its request processing policy (see page 296), a POA can rely exclusively on an active object map to map object IDs to servants, or it can use an active object map together with a servant manager and/or default servant. A POA that lacks an active object map must use either a servant manager or a default servant to map between objects and servants.

You specify a POA's servant retention policy by calling `create_servant_retention_policy()` with one of these arguments:

**RETAIN:** The POA retains active servants in its active object map.

**NON\_RETAIN:** The POA has no active object map. For each request, the POA relies on the servant manager or default servant to map between an object and its servant; all mapping information is destroyed when request processing returns. Thus, a `NON_RETAIN` policy also requires that the POA have a request processing policy of `USE_DEFAULT_SERVANT` or `USE_SERVANT_MANAGER` (see “Processing Object Requests” on page 296).

### Servant manager and servant retention policy

---

If a POA has a policy of `USE_SERVANT_MANAGER`, its servant retention policy determines whether it uses a servant activator or servant locator as its servant manager. A `RETAIN` policy requires the use of a servant activator; a `NON_RETAIN` policy requires the use of a servant locator. For more information about servant managers, see [Chapter 11](#).

---

## Processing Object Requests

A POA's request processing policy determines how it locates a servant for object requests. Four options are available:

- Maintain a permanent map, or *active object map*, between object IDs and servants and rely exclusively on that map to process all object requests.
- Activate servants on demand for object requests.
- Locate a servant for each new object request.
- Map object requests to a single default servant.

For example, if the application processes many lightweight requests for the same object type, the server should probably have a POA that maps all these requests to the same default servant. At the same time, another POA in the same server might be dedicated to a few objects that each use different servants. In this case, requests can probably be processed more efficiently if the POA is enabled for permanent object-servant mapping.

You set a POA's request processing policy by calling `create_request_processing_policy()` and supplying one of these arguments:

- `USE_ACTIVE_OBJECT_MAP_ONLY`
- `USE_SERVANT_MANAGER`
- `USE_DEFAULT_SERVANT`

**USE\_ACTIVE\_OBJECT\_MAP\_ONLY:** All object IDs must be mapped to a servant in the active object map; otherwise, Orbix returns an exception of `OBJECT_NOT_EXIST` to the client.

During POA initialization and anytime thereafter, the active object map is populated with all object-servant mappings that are required during the POA's lifetime. The active object map maintains object-servant mappings until the POA shuts down, or an object is explicitly deactivated through `deactivate_object()`.

Typically, a POA can rely exclusively on an active object map when it processes requests for a small number of objects.

This policy requires POA to have a servant retention policy of `RETAIN`. (see [“Enabling the Active Object Map” on page 295](#)).

**USE\_SERVANT\_MANAGER:** The POA's servant manager finds a servant for the requested object. Depending on its servant retention policy, the POA can implement one of two servant manager types, either a *servant activator* or a *servant locator*:

- A servant activator can be registered with a POA that has a `RETAIN` policy. The servant activator incarnates servants for inactive objects on receiving an initial request for them. The active object map retains mappings between objects and their servants; it handles all subsequent requests for this object.
- If the POA has a policy of `NON_RETAIN` (the POA has no active object map), a servant locator must find a servant for an object on each request; otherwise, an `OBJ_ADAPTER` exception is returned when clients invoke requests.

`USE_SERVANT_MANAGER` requires the application to register a servant manager with the POA by calling `set_servant_manager()`.

For more information about servant managers, see [Chapter 11](#).

**USE\_DEFAULT\_SERVANT:** The POA dispatches requests to the default servant when it cannot otherwise find a servant for the requested object. This can occur because the object's ID is not in the active object map, or the POA's servant retention policy is set to `NON_RETAIN`.

Set this policy for a POA that needs to process many objects that are instantiated from the same class, and thus can be implemented by the same servant.

This policy requires the application to register the POA's default servant by calling `set_servant()` on the POA; it also requires the POA's ID uniqueness policy to be set to `MULTIPLE_ID`, so multiple objects can use the default servant.

---

## Setting Object Lifespan

A POA creates object references through calls to `create_reference()` or `create_reference_with_id()`. The POA's lifespan policy determines whether these object references are persistent—that is, whether they outlive the process in which they were created. A persistent object reference is one that a client can successfully reissue over successive instantiations of the target server and POA.

You specify a POA's lifespan policy by calling `create_lifespan_policy()` with one of these arguments

**TRANSIENT:** (default policy) Object references do not outlive the POA in which they are created. After a transient object's POA is destroyed, attempts to use this reference yield the exception

`CORBA::OBJECT_NOT_EXIST`

**PERSISTENT:** Object references can outlive the POA in which they are created.

---

### Transient object references

When a POA creates an object reference, it encapsulates it within an IOR. If the POA has a `TRANSIENT` policy, the IOR contains the server process's current location—its host address and port. Consequently, that object reference is valid only as long as the server process remains alive. If the server process dies, the object reference becomes invalid.

---

### Persistent object references

If the POA has a `PERSISTENT` policy, the IOR contains the address of the location domain's implementation repository, which maps all servers and their POAs to their current locations. Given a request for a persistent object, the location daemon uses the object's "virtual" address first, and looks up the server process's actual location via the implementation repository.

---

### Direct persistence

Occasionally, you might want to generate persistent object references that avoid the overhead of using the location daemon. In this case, Orbix provides the proprietary policy of `DIRECT_PERSISTENCE`. A POA with policies of `PERSISTENT` and `DIRECT_PERSISTENCE` generates IORs that contain a well-known address list for the server process.

A POA that uses direct persistence must also indicate where the configuration sets the well-known address list to be embedded in object references. In order to do this, two requirements apply:

- The configuration must contain a well-known address configuration variable, with this syntax:
 

```
prefix:transport addr_list= [address-spec [, ...]
```
- The POA must have a `WELL_KNOWN_ADDRESSING_POLICY` whose value is set to `prefix`.

For example, you might create a well-known address configuration variable in name scope `MyConfigApp` as follows:

```
MyConfigApp {
 ...
 wka:top addr_list= ["host.com:1075"];
 ...
}
```

Given this configuration, a POA is created in the ORB `MyConfigApp` can have its `PolicyList` set so it generates object references that use direct persistence, as follows:

```
CORBA::PolicyList policies;
policies.length (4);
CORBA::Any persistence_mode_policy_value;
CORBA::Any well_known_addressing_policy_value;

persistence_mode_policy_value
 <<= IT_PortableServer::DIRECT_PERSISTENCE;
well_known_addressing_policy_value <<=
 CORBA::Any::from_string("wka", IT_TRUE);

policies[0] = poa->create_lifespan_policy
 (PortableServer::PERSISTENT);
policies[1] = poa->create_id_assignment_policy
 (PortableServer::USER_ID);
policies[2] = oib->create_policy(
 (IT_PortableServer::PERSISTENCE_MODE_POLICY_D,
 persistence_mode_policy_value);
policies[3] = oib->create_policy(
 IT_CORBA::WELL_KNOWN_ADDRESSING_POLICY_D,
 well_known_addressing_policy_value);
```

**Object lifespan and ID assignment**

---

A POA's lifespan and ID assignment policies have dependencies upon one another.

`TRANSIENT` and `SYSTEM_ID` are the default settings for a new POA, because system-assigned IDs are sufficient for transient object references. The application does not need tight control over the POA's ID because the POA's object reference is only valid for the POA's current incarnation.

However, `PERSISTENT` and `USER_ID` policies are usually set together, because applications require explicit control over the object IDs of its persistent object references. When using persistent object references the POA's name is part of the information used to resolve an object's IOR. For this reason, there is a possibility of conflicts when using multiple POA's with the same name and a lifespan policy of `PERSISTENT`. This is particularly true when using indirect persistent IORs.

---

## Assigning Object IDs

The ID assignment policy determines whether object IDs are generated by the POA or the application. Specify the POA's ID assignment policy by calling `create_id_assignment_policy()` with one of these arguments:

**SYSTEM\_ID:** The POA generates and assigns IDs to its objects. Typically, a POA with a `SYSTEM_ID` policy manages objects that are active for only a short period of time, and so do not need to outlive their server process. In this case, the POA also has an object lifespan policy of `TRANSIENT`. Note, however, that system-generated IDs in a persistent POA are unique across all instantiations of that POA.

**USER\_ID:** The application assigns object IDs to objects in this POA. The application must ensure that all user-assigned IDs are unique across all instantiations of the same POA.

`USER_ID` is usually assigned to a POA that has an object lifespan policy of `PERSISTENT`—that is, it generates object references whose validity can span multiple instantiations of a POA or server process, so the application requires explicit control over object IDs.

---

## Activating Objects with Dedicated Servants

A POA's ID uniqueness policy determines whether it allows a servant to incarnate more than one object. You specify a POA's ID uniqueness policy by calling `create_id_uniqueness_policy()` with one of these arguments:

**UNIQUE\_ID:** Each servant in the POA can be associated with only one object ID.

**MULTIPLE\_ID:** Any servant in the POA can be associated with multiple object IDs.

**Note:** If the same servant is used by different POAs, that servant conforms to the uniqueness policy of each POA. Thus, it is possible for the same servant to be associated with multiple objects in one POA, and be restricted to one object in another.

---

## Activating Objects

A POA's activation policy determines whether objects are explicitly or implicitly associated with servants. If a POA is enabled for explicit activation, you activate an object by calling `activate_object()` or `activate_object_with_id()` on the POA. A POA that supports implicit activation allows the server application to call the `_this()` function on a servant to create an active object (see [“Implicit Object Activation” on page 306](#)).

The activation policy determines whether the POA supports implicit activation of servants.

Specify the POA's activation policy by supplying one of these arguments:

**NO\_IMPLICIT\_ACTIVATION:** (default) The POA only supports explicit activation of servants.

**IMPLICIT\_ACTIVATION:** The POA supports implicit activation of servants. This policy requires that the POA's object ID assignment policy be set to `SYSTEM_ID`, and its servant retention policy be set to `RETAIN`.

For more information, see [“Implicit Object Activation” on page 306](#).

---

## Setting Threading Support

Specify the POA's thread policy by supplying one of these arguments:

**ORB\_CTRL\_MODEL:** The ORB is responsible for assigning requests for an ORB-controlled POA to threads. In a multi-threaded environment, concurrent requests can be delivered using multiple threads.

**SINGLE\_THREAD\_MODEL:** Requests for a single-threaded POA are processed sequentially. In a multi-threaded environment, all calls by a single-threaded POA to implementation code (servants and servant managers) are made in a manner that is safe for code that does not account for multi-threading.

Multiple single-threaded POAs might need to cooperate to ensure that calls are safe when they share implementation code such as a servant manager.

---

### Default work queues

Orbitx maintains for each ORB two default work queues, one manual and the other automatic. Depending on its thread policy, a POA that lacks its own work queue uses one of the default work queues to process requests:

- A POA with a threading policy of `SINGLE_THREAD_MODEL` uses the manual work queue. To remove requests from the manual work queue, you must call either `ORB::perform_work()` or `ORB::run()` within the main thread.
- A POA with a threading policy of `ORB_CTRL_MODEL` uses the automatic work queue. Requests are automatically removed from this work queue; however, because `ORB::run()` blocks until the ORB shuts down, an application can call this method to detect when shutdown is complete.

Both threading policies assume that the ORB and the application are using compatible threading synchronization. All uses of the POA within the server must conform to its threading policy.

For information about creating a POA workqueue, [see page 313](#).

---

## Explicit Object Activation

If the POA has an activation policy of `NO_IMPLICIT_ACTIVATION`, the server must call either `activate_object()` or `activate_object_with_id()` on the POA to activate objects. Either of these calls registers an object in the POA with either a user-supplied or system-generated object ID, and maps that object to the specified servant.

After you explicitly activate an object, you can obtain its object reference in two ways:

- Use the object's ID to call `id_to_reference()` on the POA where the object was activated. `id_to_reference()` uses the object's ID to obtain the information needed to compose an object reference, and returns that reference to the caller.
- Call `_this()` on the servant. Because the servant is already registered in the POA with an object ID, the function composes an object reference from the available information and returns that reference to the caller.

---

# Implicit Object Activation

A server activates an object implicitly by calling `_this()` on the servant designated to incarnate that object. `_this()` is valid only if the POA that maintains these objects has policies of `RETAIN`, `SYSTEM_ID`, and `IMPLICIT_ACTIVATION`; otherwise, it raises a `WrongPolicy` exception. Thus, implicit activation is generally a good option for a POA that maintains a relatively small number of transient objects.

---

## Calling `_this()`

`_this()` performs two separate tasks:

- Checks the POA to determine whether the servant is registered with an existing object. If it is not, `_this()` creates an object from the servant's interface, registers a new ID for this object in the POA's active object map, and maps this object ID to the servant.
- Generates and returns an object reference.

In other words, the object is implicitly activated in order to return an object reference.

You can call `_this()` on a servant in two ways:

- [Within an operation](#) that is invoked on the servant's object.
- [Outside an operation](#).

---

## Calling `_this()` Inside an Operation

If called inside an operation, `_this()` returns a reference to the object on which the operation was invoked. Thus, a servant can always obtain a reference to the object that it incarnates—for example, in order to register the object as a callback with another object.

The following interface defines the `get_self()` operation, whose implementation returns a reference to the same interface:

```
interface Whatever {
 Whatever get_self();
};
```

You might implement this operation as follows:

```
Whatever_ptr
Whatever::in_ptr::get_self() throw (CORBA::SystemException)
{
 return _this(); //Return reference to self
}
```

## Calling `_this()` Outside an Operation

You can activate an object and obtain a reference to it by calling `_this()` on a servant. This object reference must include information that it obtains from the POA in which the object is registered: the fully qualified POA name, protocol information, and the object ID that is registered in the POA's active object map. `_this()` determines which POA to use by calling `_default_POA()` on the servant.

`_default_POA()` is inherited from the `ServantBase` class:

```
class ServantBase {
public:
 virtual POA_ptr _default_POA();
 // ...
};
```

### Servant inheritance of `_default_POA()` implementation

All skeleton classes and the servants that implement them derive from `ServantBase`, and therefore inherit its implementation of `_default_POA()`. The inherited `_default_POA()` always returns the root POA. Thus, calling `_this()` on a servant that does not override `_default_POA()` returns a transient object reference that points back to the root POA. All invocations on that object are processed by the root POA.

As seen earlier, an application typically creates its own POAs to manage objects and client requests. For example, to create and export persistent object references, you must create a POA with a `PERSISTENT` lifespan policy and use it to generate the desired object references. If this is the case, you must be sure that the servants that incarnate those objects also override `_default_POA()`; otherwise, calling `_this()` on those servants returns transient object references whose mappings to servants are handled by the root POA.

**Note:** To avoid ambiguity concerning the POA in which an object is implicitly activated, call `servant_to_reference()` on the desired POA instead of `_this()`. While using `servant_to_reference()` requires you to narrow to the appropriate object, the extra code is worth the extra degree of clarity that you achieve.

## Overriding `_default_POA()`

To ensure that `_this()` uses the right POA to generate object references, an application's servants must override the default POA. You can do this three ways:

**Override `_default_POA()` to throw a system exception.** For example, `_default_POA()` can return system exception `CORBA::INTERNAL`. This prevents use of `_this()` to generate any object references for that servant.

By overriding `_default_POA()` to throw an exception, you ensure that attempts to use `_this()` yield an immediate error instead of a subtly incorrect behavior that must be debugged later. Instead, you must create object references with calls to either `create_reference()` or `create_reference_with_id()` (see page 344), then explicitly map objects to servants—for example, through a servant manager, or via the active object map by calling `activate_object_with_id()`.

Disabling `_default_POA()` also prevents you from calling `_this()` to obtain an existing object reference for a servant. To obtain the reference, you must call `servant_to_reference()`.

**Override `_default_POA()` in each servant to return the correct POA.** Calls to `_this()` are guaranteed to use the correct POA. This approach also raises a `WrongPolicy` exception if the POA that you set for a servant has invalid policies for implicit activation, such as `USER_D`.

This approach requires the application to maintain a reference for the servant's POA. If all servants use the same POA, you can set the reference in a global variable or a static private member. However, if a server uses unique POAs for different groups of servants, each servant must carry the overhead of an additional (non-static) data member.

**Override `_default_POA()` in a common base class.** Servant classes that need to override `_default_POA()` can inherit from a common base class that contains an override definition. This approach to overriding `_default_POA()` has two advantages:

- You only need to write the overriding definition of `_default_POA()` once.
- If you define a servant class that inherits from multiple servant classes, you avoid inheriting conflicting definitions of the `_default_POA()` method.

**Example**

Orbix's `qpp_poa_genie.tclgenie` generates servant code that overrides `_default_POA()` in the common base class `IT_ServantBaseOverrides`. This class overrides `_default_POA()` as follows:

**Example 3:** *Overriding `_default_POA()` in a common base class*

```

/File: it_servant_base_overrides.h
...
class IT_ServantBaseOverrides :
1 public virtual PortableServer::ServantBase
 {
 public:
2 IT_ServantBaseOverrides(
 PortableServer::POA_ptr
);

 virtual
 ~IT_ServantBaseOverrides();

3 virtual PortableServer::POA_ptr
 _default_POA();

 private:
4 PortableServer::POA_var m_poa;
 ...
 };

```

The code executes as follows:

1. `IT_ServantBaseOverrides` inherits from `PortableServer::ServantBase`, which is the base class for all servant classes.
2. The constructor is passed a reference to a POA object, which it stores in private member variable `m_poa`.
3. `IT_ServantBaseOverrides::_default_POA()` overrides the definition inherited from `PortableServer::ServantBase`. It returns a copy of the POA reference stored in `m_poa`.
4. The `m_poa` private member is used to store the POA reference.

For more information about using the `IT_ServantBaseOverrides` class, [see page 59](#).

## Managing Request Flow

Each POA is associated with a `POAManager` object that determines whether the POA can accept and process object requests. When you create a POA, you specify its manager by supplying it as an argument to `create_POA()`. This manager remains associated with the POA throughout its life span.

`create_POA()` can specify either an existing POA manager, or `NULL` to create a `POAManager` object. You can obtain the `POAManager` object of a given POA by calling `get_POAManager()` on it. By creating POA managers and using existing ones, you can group POAs under different managers according to their request processing needs. Any POA in the POA hierarchy can be associated with a given manager; the same manager can be used to manage POAs in different branches.

### POA manager states

A POA manager can be in four different states. The `POAManager` interface provides four operations to change the state of a POA manager, as shown in [Table 13](#).

**Table 13:** *POA manager states and interface operations*

| State   | Operation                    | Description                                                                                                                                                                                                            |
|---------|------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Active  | <code>activate()</code>      | Incoming requests are accepted for processing. When a POA manager is created, it is initially in a holding state. Until you call <code>activate()</code> on a POA's manager, all requests sent to that POA are queued. |
| Holding | <code>hold_requests()</code> | All incoming requests are queued. If the queue fills to capacity, incoming requests are returned with an exception of <code>TRANSIENT</code> .                                                                         |

**Table 13:** POA manager states and interface operations

| State      | Operation                       | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|------------|---------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Discarding | <code>discard_requests()</code> | All incoming requests are refused and a system exception of <code>TRANSIENT</code> is raised to clients so they can reissue their requests. A POA manager is typically in a discarding state when the application detects that an object or the POA in general cannot keep pace with incoming requests. A POA manager should be in a discarding state only temporarily. On resolution of the problem that required this call, the application should restore the POA manager to its active state with <code>activate()</code> . |
| Inactive   | <code>deactivate()</code>       | The POA manager is shutting down and destroying all POAs that are associated with it. Incoming requests are rejected with the exception <code>CORBA::OBJ_ADAPTER</code> .                                                                                                                                                                                                                                                                                                                                                       |

**Holding state**

The POA manager of the root POA is initially in a holding state, as is a new POA manager. Until you call `activate()` on a POA's manager, all requests sent to that POA are queued. `activate()` can also reactivate a POA manager that has reverted to a holding state (due to a `hold_requests()` call) or is in a discarding state (due to a `discard_requests()` call).

If a new POA is associated with an existing active POA manager, it is unnecessary to call `activate()`. However, it is generally a good idea to put a POA manager in a holding state before creating a new POA with it.

The queue for a POA manager that is in a holding state has limited capacity, so this state should be maintained for a short time only. Otherwise, the queue is liable to fill to capacity with pending requests. When this happens, all subsequent requests return to the client with a `TRANSIENT` exception.

---

# Work Queues

---

## Overview

Orbit provides two proprietary policies, which allow you to associate a `WorkQueue` with a POA and thereby control the flow of incoming requests for that POA:

**DispatchWorkQueuePolicy** associates a work queue with an `ORB_CTRL_MODEL` POA. All work items for the POA are processed by the work queue in a thread owned by the work queue.

**WorkQueuePolicy** associates a work queue with any POA. The specified work queue will be used by the underlying network transports for reading requests from the POA.

---

## Interface

A work queue has the following interface definition:

```
//DL
interface WorkQueue
{
 readonly attribute long max_size;
 readonly attribute unsigned long count;

 boolean enqueue(in WorkItem work, in long timeout);

 boolean enqueue_immediate(in WorkItem work);

 boolean is_full();

 boolean is_empty();

 boolean activate();

 boolean deactivate();

 boolean owns_current_thread();

 void flush();
};
```

## WorkQueue types

---

You can implement your own `WorkQueue` interface, or use IONA-supplied `WorkQueue` factories to create one of two `WorkQueue` types:

- [ManualWorkQueue](#)
- [AutomaticWorkQueue](#)

---

## ManualWorkQueue

---

### Overview

A `ManualWorkQueue` is a work queue that holds incoming requests until they are explicitly dequeued. It allows the developer full control over how requests are processed by the POA.

---

### IDL

The interface is defined as follows:

```

\\IDL
interface ManualWorkQueue : WorkQueue
{
 boolean dequeue(out WorkItem work, in long timeout);

 boolean do_work(in long number_of_jobs, in long timeout);

 void shutdown(in boolean processing_jobs);
};

```

---

### Creating

You create a `ManualWorkQueueFactory` by calling `resolve_initial_references("IT_ManualWorkQueueFactory")`. The `ManualWorkQueueFactory` has the following interface:

```

interface ManualWorkQueueFactory
{
 ManualWorkQueue create_work_queue(in long max_size);
};

```

`create_work_queue` takes the following argument:

**max\_size** is the maximum number of work items that the queue can hold. If the queue becomes full, the transport considers the server to be overloaded and tries to gracefully close down connections to reduce the load.

---

### How requests are processed

Applications that use a `ManualWorkQueue` must periodically call `dequeue()` or `do_work()` to ensure that requests are processed. The developer is in full control of time between calls and if the events are processed by multiple

threads or in a single thread. If the developer chooses a multithreaded processing method, they are responsible for ensuring that the code is thread safe.

A false return value from either `do_work()` or `dequeue()` indicates that the timeout for the request has expired or that the queue has shut down.

---

# AutomaticWorkQueue

---

## Overview

An `AutomaticWorkQueue` is a work queue that feeds a thread pool. Automatic work queues process requests in the same way that the standard ORB does; however, it does allow the developer to assign a customized thread pool to a particular POA. Also, the developer can implement several automatic work queues to process different types of requests at different priorities.

---

## IDL

The interface is defined as follows:

```
//IDL
interface AutomaticWorkQueue : WorkQueue
{
 readonly attribute unsigned long threads_total;
 readonly attribute unsigned long threads_working;

 attribute long high_watermark;
 attribute long low_watermark;

 void shutdown(in boolean process_remaining_jobs);
};
```

## Creating

You create an `AutomaticWorkQueue` through the `AutomaticWorkQueueFactory`, obtained by calling `resolve_initial_references("T_AutomaticWorkQueue")`. The `AutomaticWorkQueueFactory` has the following interface:

```
interface AutomaticWorkQueueFactory
{
 AutomaticWorkQueue create_work_queue(
 in long max_size,
 in unsigned long initial_thread_count,
 in long high_water_mark,
 in long low_water_mark);

 AutomaticWorkQueue create_work_queue_with_thread_stack_size(
 in long max_size,
 in unsigned long initial_thread_count,
 in long high_water_mark,
 in long low_water_mark,
 in long thread_stack_size);
};
```

`create_work_queue()` takes these arguments:

**max\_size** is the maximum number of work items that the queue can hold. To specify an unlimited queue size, supply a value of `-1`.

**initial\_thread\_count** is the initial number of threads in the thread pool; the ORB automatically creates and starts these threads when the workqueue is created.

**high\_water\_mark** specifies the maximum number of threads that can be created to process work queue items. To specify an unlimited number of threads, supply a value of `-1`.

**low\_water\_mark** lets the ORB remove idle threads from the thread pool, down to the value of `low_water_mark`. The number of available threads is never less than this value.

If you wish to have greater control of the size of the work queue's thread stack, use `create_work_queue_with_thread_stack()`. It adds one argument, `thread_stack_size`, to the end of the argument list. This argument specifies the size of the workqueue's thread stack.

## How requests are processed

---

Applications that use an `AutomaticWorkQueue` do not need to explicitly dequeue work items; instead, work items are automatically dequeued and processed by threads in the thread pool.

If all threads are busy and the number of threads is less than `high_water_mark`, the ORB can start additional threads to process items in the work queue, up to the value of `high_water_mark`. If the number of threads is equal to `high_water_mark` and all are busy, and the work queue is filled to capacity, the transport considers the server to be overloaded and tries to gracefully close down connections to reduce the load.

## Using a WorkQueue

### Creating the WorkQueue

To create a POA with a `WorkQueue` policy, follow these steps:

1. Create a work queue factory by calling `resolve_initial_references()` with the desired factory type by supplying an argument of `IT_AutomaticWorkQueueFactory` OR `IT_ManualWorkQueueFactory`.
2. Set work queue parameters.
3. Create the work queue by calling `create_work_queue()` on the work queue factory.
4. Insert the work queue into an `Any`.
5. Add a work queue policy object to a POA's `PolicyList`.

[Example 4](#) illustrates these steps:

#### Example 4: Creating a POA with a WorkQueue policy

```

1 //get an automatic work queue factory
CORBA::Object obj_var_obj =
 resolve_initial_references("IT_AutomaticWorkQueueFactory");
IT_WorkQueue:AutomaticWorkQueueFactory_var wqf =
 AutomaticWorkQueueFactory::narrow (obj);

2 //set work queue parameters
CORBA::Long max_size = 20;
CORBA::Long init_thread_count = 1;
CORBA::Long high_water_mark = 20;
CORBA::Long low_water_mark = 2;

3 //create work queue
IT_AutomaticWorkQueue_var wq = wqf->create_work_queue(max_size,
 init_thread_count, high_water_mark, low_water_mark);

4 //insert the work queue into an any
CORBA::Any work_queue_policy_val;
work_queue_policy_val << wq;

//create PolicyList
CORBA::PolicyList policies;
policies.length(1);

```

**Example 4:** *Creating a POA with a WorkQueue policy*

```

5 //add work queue policy object to POA's PolicyList
 policies[0] = orb->create_policy(
 II_PortableServer::DISPATCH_WORKQUEUE_POLICY_D,
 work_queue_policy_val);

```

**Processing events in a manual work queue**

When using a manual work queue, the developer must implement the loop which removes requests from the queue.

**Example 5** demonstrates one way to remove requests from a manual work queue. The code loops indefinitely and continuously polls the queue for requests. When there are requests on the queue, they are removed from the queue using the `dequeue()` method and then they processed with the `execute()` method of the `WorkItem` object returned from `dequeue()`.

**Example 5:** *Removing requests from a work queue.*

```

WorkQueue:WorkItem work_item ;

while (1)
{
 if (wq->is_empty())
 {
 //Since there are no requests to process
 //the object can sleep, or do whatever other work
 //the developer needs done.

 }
 else
 {
 manual_work_queue->dequeue(work_item, 5000);
 work_item->execute();
 //no need to explicitly destroy as execute deletes the
 //work item once completed.
 }
}

```

Alternatively, you remove requests from the queue using the `do_work()` method. The difference is that using `do_work()` you can process several requests at one time.

**Processing events in an automatic work queue**

Automatic work queues handle request processing under the covers. Therefore, the developer does not need to implement any request handling logic.

---

# Controlling POA Proxification

---

## Overview

The Iona firewall proxy service, if it is activated, default behavior is to proxyify all POAs. This can consume resources and degrade performance of a system if a large number of POAs are placed behind the firewall proxy service. In many instances only specific POAs will need to face outside the firewall. Using the `IntedictionPolicy` you can control if a specific POA is proxified.

---

## Policy

The `IntedictionPolicy` controls the behavior of the firewall proxy service plug-in, if it is loaded. The policy has two settings:

|                      |                                                                                                                                                                                                                                                                                                 |
|----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>ENABLE</code>  | This is the default behavior of the firewall proxy service plug-in. A POA with its <code>IntedictionPolicy</code> set to <code>ENABLE</code> will be proxified.                                                                                                                                 |
| <code>DISABLE</code> | This setting tells the firewall proxy service plug-in to not proxyify the POA. A POA with its <code>IntedictionPolicy</code> set to <code>DISABLE</code> will not use the firewall proxy service and requests made on objects under its control will come directly from the requesting clients. |

---

## Example

The following code samples demonstrate how to set the `IntedictionPolicy` on a POA. In the examples, the policy is set to `DISABLE`.

**C++**

```
include < orbix/fps.hh>

//Create a PREVENT interdiction policy.
CORBA::Any interdiction;
interdiction < = IT_FPS::DISABLE;

CORBA::PolicyList policies(1);
policies.length(1);
policies[0] =
 m_orb-> create_policy(IT_FPS::INTERDICTION_POLICY_D,
 interdiction);

//Create and return new POA.
return m_poa-> create_POA("no_fps_poa",0,policies);
```

# Managing Servants

*A POA that needs to manage a large number of objects can be configured to incarnate servants only as they are needed. Alternatively, a POA can use a single servant to service all requests.*

A POA's default request processing policy is `USE_ACTIVE_OBJECT_MAP_ONLY`. During POA initialization, the active object map must be populated with all object-servant mappings that are required during the POA's lifetime. The active object map maintains object-servant mappings until the POA shuts down, or an object is explicitly deactivated.

For example, you might implement the `BankDemo:Account` interface so that at startup, a server instantiates a servant for each account and activates all the account objects. Thus, a servant is always available for any client invocation on that account—for example, `balance()` or `withdraw()`.

## Drawbacks of active object map usage

---

Given the potential for many thousands of accounts, and the likelihood that account information changes—accounts are closed down, new accounts are created—the drawbacks of this static approach become obvious:

- Code duplication: For each account, the same code for servant creation and activation must be repeated, increasing the potential for errors.
- Inflexibility: For each change in account information, you must modify and recompile the server code, then stop and restart server processes.

- Startup time: The time required to create and activate a large number of servants prolongs server startup and delays its readiness to process client requests.
- Memory usage: An excessive amount of memory might be required to maintain all servants continuously.

This scenario makes it clear that you should usually configure a POA to rely exclusively on an active object map only when it maintains a small number of objects.

**Policies for managing many objects**

If a POA is required to maintain a large number of objects, you should set its request processing policy to one of the following:

- `USE_SERVANT_MANAGER` specifies that servants are instantiated on demand.
- `USE_DEFAULT_SERVANT` specifies a default servant that handles requests for any objects that are not registered in the active object map, or for all requests in general.

This chapter shows how to implement both policies.

**In this chapter**

This chapter contains the following sections:

|                                           |                          |
|-------------------------------------------|--------------------------|
| <a href="#">Using Servant Managers</a>    | <a href="#">page 327</a> |
| <a href="#">Using a Default Servant</a>   | <a href="#">page 340</a> |
| <a href="#">Creating Inactive Objects</a> | <a href="#">page 344</a> |

---

# Using Servant Managers

---

## Servant manager types

A POA whose request processing policy is set to `USE_SERVANT_MANAGER` supplies servants on demand for object requests. The POA depends on a servant manager to map objects to servants. Depending on its servant retention policy, the POA can implement one of two servant manager types, either a *servant activator* or *servant locator*:

- A servant activator is registered with a POA that has a `RETAIN` policy. The servant activator supplies a servant for an inactive object on receiving an initial request for it. The active object map retains the mapping between the object and its servant until the object is deactivated.
- A servant locator is registered with a POA that has a policy of `NON_RETAIN`. The servant locator supplies a servant for an inactive object each time the object is requested. In the absence of an active object map, the servant locator must deactivate the object and delete the servant from memory after the request returns.

Because a servant activator depends on the active object map to maintain the servants that it supplies, its usefulness is generally limited to minimizing an application's startup time. In almost all cases, you should use a servant locator for applications that must dynamically manage large numbers of objects.

---

## Registering a servant manager

An application registers its servant manager—whether activator or locator—with the POA by calling `set_servant_manager()` on it; otherwise, an `OBJ_ADAPTER` exception is returned to the client on attempts to invoke on one of its objects.

The following sections show how to implement the `BankDemo::Account` interface with a servant activator and a servant locator. Both servant manager types activate account objects with instantiations of servant class `SingleAccountImpl`, which inherits from skeleton class `POA_BankDemo::Account`

```

class SingleAccountImpl:
public POA_BankDem o::Account
{
public:
SingleAccountImpl(
const char* account_id,
AccountDatabase& account_db
);

~SingleAccountImpl();

void withdraw(BankDem o::CashAccount amount) throw (
CORBA::SystemException,
BankDem o::Account::InsufficientFunds);

void deposit(BankDem o::CashAccount amount) throw (
CORBA::SystemException);

char* account_id() throw (CORBA::SystemException);


BankDem o::CashAccount balance()
throw (CORBA::SystemException);

private:
CORBA::String_var m_account_id;
BankDem o::CashAccount m_balance;
AccountDatabase& m_account_db;
};

```

## Servant Activators

A POA with policies of `USE_SERVANT_MANAGER` and `RETAIN` uses a servant activator as its servant manager. The POA directs the first request for an inactive object to the servant activator. If the servant activator returns a servant, the POA associates it with the requested object in the active object map and thereby activates the object. Subsequent requests for the object are routed directly to its servant.



**Figure 16:** On the first request on an object, the servant activator returns a servant to the POA, which establishes the mapping in its active object map.

Servant activators are generally useful when a server can hold all its servants in memory at once, but the servants are slow to initialize, or they are not all needed each time the server runs. In both cases, you can expedite server startup by deferring servant activation until it is actually needed.

## ServantActivator interface

The `PortableServer::ServantActivator` interface is defined as follows:

```
interface ServantActivator : ServantManager
{
 Servant
 incarnate(
 in ObjectID oid,
 in POA adapter
 raises (ForwardRequest);

 void
 etherealize(
 in ObjectID oid,
 in POA adapter,
 in Servant serv,
 in boolean cleanup_in_progress,
 in boolean remaining_activations
);
};
```

A POA can call two methods on its servant activator:

- `incarnate()` is called by the POA when it receives a request for an inactive object, and should return an appropriate servant for the requested object.
- `etherealize()` is called by the POA when an object is deactivated or the POA shuts down. In either case, it allows the application to clean up resources that the servant uses.

## Implementing a servant activator

You can define a servant activator as follows:

### Example 6: Servant activator class definition

```
include < om/gPortableServerS.hh>
include "account_db.h"

class AccountServantActivatorImpl :
 public PortableServer::ServantActivator,
 public CORBA::LocalObject
{
public:
 AccountServantActivatorImpl(AccountDatabase& account_db);

 PortableServer::Servant incarnate(
 const PortableServer::ObjectID & oid,
 PortableServer::POA_ptr adapter
) throw (CORBA::SystemException,
 PortableServer::ForwardRequest);

 void etherealize(
 const PortableServer::ObjectID & oid,
 PortableServer::POA_ptr adapter,
 PortableServer::Servant serv,
 CORBA::Boolean cleanup_in_progress,
 CORBA::Boolean remaining_activations
) throw (CORBA::SystemException);
};
```

In this example, the servant activator's constructor takes a single argument, an AccountDatabase object, to enable interaction between Account objects and persistent account data..

## Activating objects

`incarnate()` instantiates a servant for a requested object and returns the servant to the POA. The POA registers the servant with the object's ID, thereby activating the object and making it available to process requests on it.

In the implementation shown in [Example 7](#), `incarnate()` performs these tasks:

1. Takes the object ID of a request for a `BankDemo::Account` object, and the POA that relayed the request.

- Instantiates an `SingleAccountImpl` servant, passing account information to the servant's constructor, and returns the servant to the POA.

**Example 7:** *Servant activator implementation*

```

//servant activator constructor
AccountServantActivatorImpl::AccountServantActivatorImpl(
 AccountDatabase& account_db) : m_account_db(account_db)
{ // ... }

PortableServer::Servant

1 AccountServantActivatorImpl::incarnate(
 const PortableServer::ObjectID & oid,
 PortableServer::POA_ptr adapter
) throw (CORBA::SystemException, PortableServer::ForwardRequest)
{
 CORBA::String_var account_id =
 PortableServer::ObjectID_to_string(oid);

2 return new SingleAccountImpl(account_id, m_account_db);
}

```

## Deactivating objects

The POA calls `deactivate()` when an object deactivates, either because the object is destroyed or as part of general cleanup when the POA itself deactivates or is destroyed.

The following implementation of `deactivate()` checks the `remaining_activations` parameter to ensure that the servant does not incarnate another object before it deletes the servant. Implementations can

also check the `cleanup_in_progress` parameter to determine whether etherealization results from POA deactivation or destruction; this lets you differentiate between this and other reasons to etherealize a servant.

**Example 8:** *Implementation of `etherealize()` method*

```
void
AccountServantActivator::pl::etherealize(
 const PortableServer::ObjectId & oid,
 PortableServer::POA_ptr poa,
 PortableServer::Servant servant,
 CORBA::Boolean cleanup_in_progress,
 CORBA::Boolean remaining_activations
) throw ((CORBA::SystemException))
{
 if (remaining_activations == 0)
 delete serv;
}
```

## Setting deactivation policies

By default, a POA that uses a servant activator lets an object deactivate (and its servant to etherealize) only after all pending requests on that object return. You can modify the way the POA handles incoming requests for a deactivating object by creating an Orbix-proprietary `ObjectDeactivationPolicy` object and attaching it to the POA's `PolicyList` (see [“Setting proprietary policies for a POA” on page 291](#)).

Three settings are valid for this Policy object:

**DELIVER:** (default) The object deactivates only after processing all pending requests, including any requests that arrive while the object is deactivating. This behavior complies with CORBA specifications.

**DISCARD:** The POA rejects incoming requests with an exception of `TRANSIENT`. Clients should be able to reissue discarded requests.

**HOLD:** Requests block until the object deactivates. A POA with a `HOLD` policy maintains all requests until the object reactivates. However, this policy can cause deadlock if the object calls back into itself.

**Setting a POA's servant activator**

The following example shows how you can establish a POA's servant activator in two steps:

```
...
AccountDatabase account_database = new AccountDatabase();
1 // instantiate servant activator
AccountServantActivator in_pl_activator_in_pl(account_database);
2 // Associate the activator with the accounts POA
acct_poa-> set_servant_manager(&activator_in_pl);
```


1. Instantiate the servant activator.
2. Call `set_servant_manager()` on the target POA and supply the servant activator.

## Servant Locators

A server that needs to manage a large number of objects might only require short-term access to them. For example, the operations that are likely to be invoked on most customer bank accounts—such as withdrawals and deposits—are usually infrequent and of short duration. Thus, it is unnecessary to keep account objects active beyond the lifetime of any given request. A POA that services requests like this can use a servant locator, which activates an object for each request, and deactivates it after the request returns.

### Required policies

A POA with policies of `USE_SERVANT_MANAGER` and `NON_RETAIN` uses a servant locator as its servant manager. Because the POA lacks an active object map, it directs each object request to the servant locator, which returns a servant to the POA in order to process the request. The POA calls the request operation on the servant; when the operation returns, the POA deactivates the object and returns control to the servant locator. From the POA's perspective, the servant is active only while the request is being processed.



**Figure 17:** The POA directs each object request to the servant locator, which returns a servant to the POA to process the request.

## Controlling servant lifespan

An application that uses a servant locator has full control over servant creation and deletion, independently of object activation and deactivation. Your application can assert this control in a number of ways. For example:

- *Servant caching*: A servant locator can manage a cache of servants for applications that have a large number of objects. Because the locator is called for each operation, it can determine which objects are requested most recently or frequently and retain and remove servants accordingly.
- *Application-specific object map*: A servant locator can implement its own object-servant mapping algorithm. For example, a POA's active object map requires a unique servant for each interface. With a servant locator, an application can implement an object map as a simple fixed table that maps multiple objects with different interfaces to the same servant. Objects can be directed to the appropriate servant through an identifier that is embedded in their object IDs. For each incoming request, the servant locator extracts the identifier from the object ID and directs the request to the appropriate servant.

## ServantLocator interface

The `PortableServer.ServantLocator` interface is defined as follows:

```
interface ServantLocator : ServantManager
{
 native Cookie;
 Servant
 preinvoke(
 in ObjectID oid,
 in POA adapter,
 in CORBA::Identifier operation,
 out Cookie the_cookie
 raises (ForwardRequest);

 void
 postinvoke(
 in ObjectID oid,
 in POA adapter,
 in CORBA::Identifier operation,
 in Cookie the_cookie,
 in Servant the_servant
);
};
```

A servant locator processes each object request with a pair of methods, `preinvoke()` and `postinvoke()`:

- `preinvoke()` is called on a POA's servant locator when the POA receives a request for an object. `preinvoke()` returns an appropriate servant for the requested object.
- `postinvoke()` is called on a POA's servant locator to dispose of the servant when processing of the object request is complete. The `postinvoke()` implementation can either delete the servant, or cache it for later reuse.

## Implementing a servant locator

The following code defines a servant locator that handles account objects:

### Example 9: Servant locator class definition

```
class AccountServantLocatorIn pl :
 public PortableServer::ServantLocator,
 public CORBA::LocalObject
{
 public:
 AccountServantLocatorIn pl(AccountDatabase& account_db);

public:
 PortableServer::Servant preinvoke(
 const PortableServer::Object& id,
 PortableServer::POA_ptr poa,
 const char* operation,
 PortableServer::Cookie & cookie)
 throw (CORBA::SystemException);

 void postinvoke (
 const PortableServer::Object& id,
 PortableServer::POA_ptr poa,
 const char* operation,
 PortableServer::Cookie & cookie,
 PortableServer::Servant the_servant)
 throw (CORBA::SystemException);
};
```

Each request is guaranteed a pair of `preinvoke()` and `postinvoke()` calls. This can be especially useful for applications with database transactions. For example, a database server can use a servant locator to direct concurrent operations to the same servant; each database transaction is opened and closed within the `preinvoke()` and `postinvoke()` operations.

The signatures of `preinvoke()` and `postinvoke()` are differentiated from those of `invoke()` and `incarnate()` by two parameters, `the_cookie` and `operation`:

**the\_cookie** lets you explicitly map data between `preinvoke()` and its corresponding `postinvoke()` call. This can be useful in a multi-threaded environment and in transactions where it is important to ensure that a pair of `preinvoke()` and `postinvoke()` calls operate on the same servant. For example, each `preinvoke()` call can set its `the_cookie` parameter to data that identifies its servant; the `postinvoke()` code can then compare that data to its `the_servant` parameter.

**operation** contains the name of the operation that is invoked on the CORBA object, and thus provides the context of the servant's instantiation. The servant can use this to differentiate between different operations and execute the appropriate code.

### Incarnating objects with a servant locator

The following implementation of `preinvoke()` is functionally identical to the `incarnate()` implementation shown in [Example 7](#).

#### Example 10: Implementation of `preinvoke()` method

```
PortableServer::Servant
MyAcctLocator::preinvoke(
 const PortableServer::ObjectID & id,
 PortableServer::POA_ptr poa,
 const char* operation,
 PortableServer::Cookie & cookie)
throw (CORBA::SystemException)
{
 CORBA::String_var str =
 PortableServer::ObjectID_to_string(id);

 // look up account ID in accounts database,
 // make sure it exists
 CORBA::Long acctId = acct_lookup(str);

 if (acctId == -1)
 throw CORBA::OBJECT_NOT_EXIST ();

 return new SingleAccountImpl(str);
}
```

## Etherealizing objects with a servant locator

The following implementation of `postinvoke()` is similar to the `etherealize()` implementation shown in [Example 8](#), with one significant difference: because each servant is bound to a single request, `postinvoke()` has no remaining activations to check.

### Example 11: Implementation of `postinvoke()` method

```
PortableServer::Servant
MyAcctLocator::postinvoke(
 const PortableServer::ObjectID &id,
 PortableServer::POA_ptr poa,
 const char *operation,
 PortableServer::Cookie &cookie,
 PortableServer::Servant the_servant)
throw (CORBA::SystemException)
{
 delete servant;
}
```

## Setting a POA's servant locator

You establish a POA's servant locator in two steps, as shown in the following example:

```
1 AccountServantLocatorImpl bcator_impl(account_database);
2 //Associate the bcator with the accounts POA
acct_poa-> set_servant_manager(&bcator_impl);
```

1. Instantiate the servant locator.
2. Call `set_servant_manager()` on the target POA and supply the servant locator.

## Using a Default Servant

If a number of objects share the same interface, a server can most efficiently handle requests on them through a POA that provides a single default servant. This servant processes all requests on a set of objects. A POA with a request processing policy of `USE_DEFAULT_SERVANT` dispatches requests to the default servant when it cannot otherwise find a servant for the requested object. This can occur because the object's ID is not in the active object map, or the POA's servant retention policy is set to `NON_RETAIN`.

For example, all customer account objects in the bank server share the same `BankDemo:Account` interface. Instead of instantiating a new servant for each customer account object as in previous examples, it might be more efficient to create a single servant that processes requests on all accounts.

### Obtaining the current object

A default servant must be able to differentiate the objects that it is serving. The `PortableServer:Current` interface offers this capability:

```
module PortableServer
{
 interface Current : CORBA::Current
 {
 exception NoContext{};
 POA get_POA () raises (NoContext);
 ObjectID get_object_id() raises (NoContext);
 };
 ...
}
```

You can call a `PortableServer:Current` operation only in the context of request processing. Thus, each `Bank:Account` operation such as `deposit()` or `balance()` can call `PortableServer:Current:get_object_id()` to obtain the current object's account ID number.

### Implementing a default servant

To implement a default servant for account objects, modify the code as follows:

- The `SingleAccountImpl` constructor identifies the ORB instead of an object's account ID.

- Each Account operation calls `resolve_initial_references()` on the ORB to obtain a reference to the `PortableServer::Current` object, and uses this reference to identify the current account object.

So, you might use the following servant code to implement an account object:

**Example 12:** *Implementation of a default servant*

```
class SingleAccountIn pl : public virtual POA_BankDem o::Account{
public:
 //constructor
 SingleAccountIn pl (CORBA::ORB_ptr orb) : orb_ (orb) {}

 //get account holder's name
 char* name() throw (CORBA::System Exception){

 CORBA::String_var acct = get_acct_id();
 //rest of function not shown
 }

 //get account balance
 CORBA::Float balance() throw (CORBA::System Exception){

 CORBA::String_var acct = get_acct_id();
 //rest of function not shown
 }

 //similar processing for other operations

private:
 char* get_acct_id(void){
 CORBA::Object_var obj =
 orb_ -> resolve_initial_references("POACurrent");
 PortableServer::Current_var cur =
 PortableServer::Current::narrow (obj);
 try {
 PortableServer::ObjectID_var id =
 cur-> get_object_id();
 return PortableServer::ObjectID_to_string(id);
 } catch (const PortableServer::Current::NoContext&) {
 cerr << " NoContext error" << endl;
 }
 }
}
```

In this implementation, the servant [constructor](#) takes a single argument, a pointer to the ORB. Each method such as `balance()` calls the private helper method `get_account_id()`, which obtains a reference to the current object (`PortableServer::Current`) and gets its object ID. The method converts the object ID to a string (`PortableServer::ObjectID_to_string`), and returns with this string.

This implementation assumes that account object IDs are generated from account ID strings. See [“Creating Inactive Objects” on page 344](#) to see how you can create object IDs from a string and use them to generate object references.

---

## Setting a Default Servant

You can establish a POA's default servant by instantiating the desired servant class and supplying it as an argument to `set_servant()`, which you invoke on that POA. The following code fragment from the server's `main()` instantiates servant `def_serv` from servant class `SingleAccountImpl`, and sets this as the default servant for POA `acct_poa`:

```
//Initialize the ORB
CORBA::ORB_var orb = CORBA::ORB_init(argc, argv);

//Instantiate default account object servant
SingleAccountImpl def_serv(orb);
...

//Set default servant for POA
acct_poa-> set_servant(&def_serv);
```

## Creating Inactive Objects

An application that uses a servant manager or default servant typically creates objects independently of the servants that incarnate them. The various implementations shown earlier in this chapter assume that all account objects are available before they are associated with servants in the POA. Thus, the account objects are initially inactive—that is, servants are unavailable to process any requests that are invoked on them.

You can create inactive objects by calling either `create_reference()` or `create_reference_with_id()` on a POA. In the next example, the POA that is to maintain these objects has an ID assignment policy of `USER_ID`; therefore, the server code calls `create_reference_with_id()` to create objects in that POA:

**Note:** The repetitive mechanism used in this example to create objects is used only for illustrative purposes. A real application would probably use a factory object to create account objects from persistent data.

```
int main(int argc, char **argv) {
 // initialize ORB
 CORBA::ORB_var orb = CORBA::ORB_init(argc, argv);

 // get object reference to the root POA
 CORBA::Object_var obj =
 orb->resolve_initial_references("RootPOA");
 PortableServer::POA_var poa = POA::narrow(obj);

 // set policies for persistent POA that uses servant locator
 CORBA::PolicyList policies;
 policies.length(2);
 policies[0] = poa->create_lifespan_policy
 (PortableServer::PERSISTENT);
 policies[1] = poa->create_id_assignment_policy
 (PortableServer::USER_ID);
 policies[2] = poa->create_servant_retention_policy
 (PortableServer::NON_RETAIN);
 policies[3] = poa->create_request_processing_policy
 (PortableServer::USE_SERVANT_MANAGER);
}
```

```

//create the POA
poa = poa-> create_POA('acct_poa',NULL,policies);

AccountDatabase account_database = new AccountDatabase();

AccountServantLocatorInPl locator_in_pl(account_database);

//Associate the locator with the accounts POA
acct_poa-> set_servant_manager(& locator_in_pl);

//Set Bank Account interface repository ID
const char *repository_id = "DL:BankDemoAccount1.0";

//create account object
PortableServer::ObjectId_var acct_id =
 PortableServer::string_to_ObjectId("112-1110001");
CORBA::Object_var acctObj =
 acct_poa-> create_reference_with_id(
 acct_id, repository_id);

//Export object reference to Naming Service (not shown)

//create another account object
PortableServer::ObjectId_var acct_id =
 PortableServer::string_to_ObjectId("112-1110002");
CORBA::Object_var acctObj =
 acct_poa-> create_reference_with_id(
 acct_id, repository_id);

//Export object reference to Naming Service (not shown)

//Repeat for each account object...

//Start ORB
orb-> run();
return 0 ;
}

```

As shown, `main()` executes as follows:

1. Creates all account objects in `acct_poa` without incarnating them.
2. Calls `run()` on the ORB so it starts listening to requests.
3. As the POA receives requests for objects, it passes them on to the servant locator. The servant locator instantiates a servant to process each request.

4. After the request returns from processing, the servant locator destroys its servant.

# Asynchronous Method Invocations

*Orbix support for asynchronous method invocations allows a client to continue other work while it awaits responses from previous requests.*

Examples of client implementations in earlier chapters show client invocations that follow a synchronous two-way model—that is, after a client sends a request, it blocks on that thread until it receives a reply. If single-threaded, the client is generally unable to perform any other work while it awaits a response. This can be unacceptable in an application that requires clients to issue requests in rapid succession and needs to process replies as soon as they become available.

---

## Callbacks to reply handlers

To avoid this problem, Orbix supports asynchronous method invocations (AMI) through callbacks to reply handlers. In its invocation, the client supplies an object reference to the appropriate reply handler. When it is ready to reply, the server invokes on this object reference. The client ORB dispatches the invocation to the reply handler servant.

In most cases, AMI usage affects only client implementations; servers are unaware that an invocation is synchronous or asynchronous. Client asynchrony matters only to transactional servers, and in this case can require changes to the server.

### Example IDL

The examples in this chapter use the following IDL, which queries banking institutions for current lending rates:

```
module LoanSearch
{
 //nonexistentBank
 exception InvalidBank{};
 //invalid loan type
 exception InvalidLoanType{};

 interface LoanRates{
 float get_loan_rate(
 in string bank_name,
 in string loan_type
) raises (InvalidBank, InvalidLoanType);
 };
 // ...
};
```

Client implementations must be able to invoke the `get_loan_rate()` operation asynchronously on multiple lenders, so that information from each one can be reviewed as soon as it is available, without waiting for previous queries to return. Each implementation uses the following global variables:

```
static const char *banks[] =
{
 "Fleet",
 "Citizens",
 "BkBoston",
 "USTrust",
 //...
}
static const int MAX_BANKS = (sizeof(banks)/sizeof(const char*));
static const int replies_left = MAX_BANKS;
```

```
static const char* loan_types[] =
{
 'AUTO',
 'MORTGAGE',
 'EQUITY',
 'PERSONAL',
 'BUSINESS',
 // ...
}
```

---

### In this chapter

This chapter contains the following sections:

|                                                |                          |
|------------------------------------------------|--------------------------|
| <a href="#">Implied IDL</a>                    | <a href="#">page 350</a> |
| <a href="#">Calling Back to Reply Handlers</a> | <a href="#">page 351</a> |

## Implied IDL

In order to support AMI, the IDL compiler provides the `-xAM Callbacks` option. This generates an *implied IDL* `sendc_` operation for each interface operation and attribute, which supports AMI callbacks. You must supply the `-xAM Callbacks` modifier with both `-base` and `-poa` switches, as in the following example:

```
DL -poa:-xAM Callbacks -base:-xAM Callbacks LoanSearch.idl
```

For example, given the `get_loan_rate()` operation, the IDL compiler generates an implied IDL `sendc_get_loan_rate()` operation that it adds to the `LoanRates` interface. The compiler then generates stub and skeleton code from the entire set of explicit and implicit IDL.

### Mapping operations to implied IDL

In general, each `in` and `inout` parameter in an IDL operation is mapped to an argument of the same name and type in the corresponding `sendc_` operation. `sendc_` operations return `void` and supply as their first argument an object reference to the client-implemented reply handler. They have the following syntax

```
void sendc_op-name(
 reply-hdlr-ref,
 [type argument [type argument] ...]);
```

### Mapping attributes to implied IDL

Each IDL attribute is mapped to a `sendc_get_` operation which takes an object reference to its reply handler. If the attribute is not read-only, the IDL compiler also generates a `sendc_set_` operation, which takes an addition argument of the same name and type as the attribute.

`sendc_get_` and `sendc_set_` operations return `void` and supply as their first argument an object reference to the client-implemented reply handler. They have the following syntax:

```
void sendc_get_attribute-name(reply-hdlr-ref);
void sendc_set_attribute-name(
 reply-hdlr-ref,
 type attribute-name);
```

---

# Calling Back to Reply Handlers

For each IDL operation and attribute, the IDL compiler generates:

- A `send_c` operation that supports AMI callbacks.
- A reply handler class for each interface, derived from `Messaging:ReplyHandler`.

The generated reply handler class name uses the following convention:

`AM Iinterface-nameHandler`

For example, all `send_c` invocations on interface `LoanRates` take a reference to an instance of `AM ILoanRatesHandler` as their first argument.

The client instantiates reply handlers like any servant, and registers them with a client-side POA. If a reply handler serves time-independent invocations, its object reference must be persistent.

For each `send_c` invocation on the interface, the following events occur:

1. The client supplies an object reference to the invocation's reply handler.
2. The invocation returns immediately to the client, which can continue processing other tasks while it awaits a reply.
3. The reply handler is invoked when a reply is ready.

**Note:** A client-side POA has the same requirements as a POA that is implemented on a server—for example, the `POAManager` must be in an active state before the client can process reply handler callbacks.

## Interface-to-Reply Handler Mapping

The client can implement a reply handler for each interface. For each interface operation and attribute, a reply handler provides two types of operations: one to handle normal replies and another to handle exceptions.

For example, when you run the IDL compiler on interface `LoanSearch:LoanRates` (shown earlier), it generates skeleton class `LoanSearch:AM_ILoanRatesHandler`:

```
namespace POA_LoanSearch{
class AM_ILoanRatesHandler
:public POA_Messaging:ReplyHandler{
public:
// ...
virtualvoid get_ban_rate_complete(
CORBA:Flatam_i_return_val)
IT_THROW_DECL((CORBA::SystemException))= 0;
// ...
virtualvoid get_ban_rate_except(
Messaging:ExceptionHandler* am_i_holder)
IT_THROW_DECL((CORBA::SystemException))= 0;
};
}
```

`LoanRates` contains only one operation, `get_ban_rate()`, which maps to AMI operation `sendc_get_ban_rate()`. The reply handler `AM_ILoanRatesHandler` therefore has two operations:

- `get_ban_rate_complete()` handles normal replies to `sendc_get_ban_rate()`.
- `get_ban_rate_except()` handles exceptions that might be raised by `sendc_get_ban_rate()`.

So, if the client invokes `sendc_get_ban_rate()` and supplies a valid bank name and loan type, the client ORB invokes an implementation of `AM_ILoanRatesHandler::get_ban_rate_complete()` to handle the reply. However, if either argument is invalid, the client ORB invokes `AM_ILoanRatesHandler::get_ban_rate_except()`.

**Normal replies**

A reply handler can contain up to three types of operations to handle normal replies—that is, replies on invocations that raise no exceptions:

**Table 14:** *Reply Handler Operation Types for Normal Replies*

| For invocations on... | The reply handler uses...                                                                                             |
|-----------------------|-----------------------------------------------------------------------------------------------------------------------|
| Operations            | An operation with the same name:<br><pre>void op-name_complete(   [type am_i_return_val   [type argument]... );</pre> |
| Read-only attributes  | A <code>get_operation</code> :<br><pre>void get_attr-name (type am_i_return_val);</pre>                               |
| Read/write attributes | A <code>set_operation</code> :<br><pre>void set_attr-name (type attr-name);</pre>                                     |

If the operation has a return value, it is the first argument of `op-name_complete`. In addition, an argument is included for each `out` or `inout` parameter in the IDL definition. All arguments have the same type as the original IDL. Arguments have the same order as in the original IDL.

**Exceptional replies**

A reply handler can contain up to three types of operations to handle exceptional replies:

**Table 15:** *Reply Handler Operation Types for Exceptional Replies*

| For invocations on... | The reply handler uses...                                                           |
|-----------------------|-------------------------------------------------------------------------------------|
| Operation             | <pre>void op-name_excep(   Messaging::ExceptionHandler*   am_i_holder);</pre>       |
| Read-only attribute   | <pre>void get_attr-name_excep(   Messaging::ExceptionHandler*   am_i_holder);</pre> |

**Table 15:** *Reply Handler Operation Types for Exceptional Replies*

| For invocations on... | The reply handler uses...                                                              |
|-----------------------|----------------------------------------------------------------------------------------|
| Read/write attribute  | <pre>void set_attr-name_except(     Messaging:ExceptionHolder*     an_i_holder);</pre> |

All three operations has a single argument of type `Messaging:ExceptionHolder*`, which contains the exception raised by the original client invocation. You access this exception using `get_exception()`. The call returns an `Any*` from which the exception can be extracted.

## Implementing a Client with Reply Handlers

As shown earlier, the reply handler `AM_ILoanRatesHandler` for interface `LoanRates` contains two operations to handle normal and exceptional replies to `send_get_ban_rate()`. The client implementation of this reply handler might look like this:

**Figure 18:** Reply handler implementation

```
class MyLoanRatesHandler :
public POA_ILoanSearch:AM_ILoanRatesHandler{
public:
 //handler constructor
 MyLoanRatesHandler(const char*bank_name,
 const char*ban_type) :
 bank_name_(CORBA::string_dup(bank_name)),
 ban_type_(CORBA::string_dup(ban_type))
 { }
 ~MyLoanRatesHandler(void)
 { }

 //process normal replies
 virtual void get_ban_rate_complete(CORBA::Fbatreply_val)
 {
 cout << ban_type_
 << "ban: from "
 << bank_name_
 << " Current rate is "
 << reply_val
 << endl;

 //Decrement the number of replies still pending
 replies_left--;
 }
}
```

**Figure 18:** Reply handler implementation

```

//process exceptional replies
virtual void get_bank_rate_except(Message::ExceptionHandler*
 an_i_handler)
{
 CORBA::Any* tmp = an_i_handler->get_exception();
 LoanSearch::InvalidBank* ex_invalid_bank;
 if ((*tmp) >= ex_invalid_bank)
 {
 cerr << "bank name_
 << "is not a valid bank name."
 << endl;
 }
 else
 {
 LoanSearch::InvalidLoan* ex_invalid_loan;
 if ((*tmp) >= ex_invalid_loan)
 {
 cerr << "loan_type_
 << "is not a valid loan type."
 << endl;
 }
 else
 {
 cerr << "get_bank_rate() raised exception "
 << tmp
 << " for "
 << bank_name_
 << " and "
 << loan_type_
 << endl;
 }
 }
}

//Decrement the number of replies still pending
replies_left--;
}

private:
 CORBA::String_var bank_name_, loan_type_;
};

```

Given this reply handler, a client can call `get_latest_rates()`, which is implemented as follows:

1. The client call to `get_latest_rates()` supplies it with three arguments: a pointer to the client ORB, an object reference to the `LoanSearch` object, and the desired loan type.
2. The method calls the callback operation `sendc_get_ban_rates()` repeatedly, once for each bank. Each call to `sendc_get_ban_rates()` supplies an `AM_I_LoanRatesHandler` reply handler argument.

1

```

void get_latest_rates(
CORBA::ORB_ptr,
LoanSearch::LoanRates_ref,
CORBA::String ban_type)
{
//array of pointers to bank reply handlers
MyLoanRatesHandler *handlers[MAX_BANKS];

//create object references for each reply handler
LoanSearch::AM_I_LoanRatesHandler_ptr
*handler_refs[MAX_BANKS];

inti;

//instantiate reply handler servants
for(i= 0;i< MAX_BANKS;i++)
handlers[i]= new MyLoanRatesHandler(
banks[i], ban_types[i]);

//get object references to reply handlers
for(i= 0;i< MAX_BANKS;i++)
handler_refs[i]= handlers[i]->_this();

//Issue asynchronous calls via callbacks
for(i= 0;i< MAX_BANKS;i++)
LoanRates_ref-> sendc_get_ban_rate(
handler_refs[i], banks[i], ban_type);
}

```

2



# Exceptions

*Implementations of IDL operations and attributes throw exceptions to indicate when a processing error occurs.*

An IDL operation can throw two types of exceptions:

- *User-defined exceptions* are defined explicitly in your IDL definitions.
- *System exceptions* are predefined exceptions that all operations can throw.

While IDL operations can throw user-defined and system exceptions, accessor methods for IDL attributes can only throw system-defined exceptions.

---

## Example IDL

This chapter shows how to throw and catch both types of exceptions. The `Bank` interface is modified to include two user-defined exceptions:

**AccountNotFound** is defined by `find_account()`.

**AccountAlreadyExists** is defined by `create_account()`.

The `account_id` member in both exceptions indicates an invalid account ID:

```

module BankDemo
{
 ...
 interface Bank {
 exception AccountAlreadyExists { AccountId account_id; };
 exception AccountNotFound { AccountId account_id; };

 Account find_account(in AccountId account_id)
 raises(AccountNotFound);

 Account create_account(
 in AccountId account_id,
 in CashAmount initial_balance
) raises (AccountAlreadyExists);
 };
};

```


### In this chapter

This chapter contains the following sections:

|                                            |          |
|--------------------------------------------|----------|
| <a href="#">Exception Code Mapping</a>     | page 361 |
| <a href="#">User-Defined Exceptions</a>    | page 362 |
| <a href="#">Handling Exceptions</a>        | page 364 |
| <a href="#">Throwing Exceptions</a>        | page 373 |
| <a href="#">Exception Safety</a>           | page 374 |
| <a href="#">Throwing System Exceptions</a> | page 377 |

# Exception Code Mapping

The C++ mapping arranges CORBA exceptions into the hierarchy shown in [Figure 19](#). Abstract base class `CORBA::Exception` is the root of the hierarchy tree. Base abstract classes `SystemException` and `UserException` derive from `CORBA::Exception` and provide the base for all concrete system and user exceptions:



**Figure 19:** *The C++ mapping arranges exceptions into a hierarchy*

Given this hierarchy, you can catch all CORBA exceptions in a single catch handler. Alternatively, you can catch system and user exceptions separately, or handle specific exceptions individually.

---

# User-Defined Exceptions

Operations are defined to raise one or more user exceptions to indicate application-specific error conditions. An exception definition can contain multiple data members to convey specific information about the error, if desired. For example, you might include a graphic image in the exception data in order to display an error icon.

---

## Exception design guidelines

When you define exceptions, be sure to follow these guidelines:

**Exceptions are thrown only for exceptional conditions.** Do not throw exceptions for expected outcomes. For example, a database lookup operation should not throw an exception if a lookup does not locate anything; it is normal for clients to occasionally look for things that are not there. It is harder for the caller to deal with exceptions than return values, because exceptions break the normal flow of control. Do not force the caller to handle an exception when a return value is sufficient.

**Exceptions carry complete information.** Ensure that exceptions carry all the data the caller requires to handle an error. If an exception carries insufficient information, the caller must make a second call to retrieve the missing information. However, if the first call fails, it is likely that subsequent calls will also fail.

**Exceptions only carry useful information.** Do not add exception members that are irrelevant to the caller.

**Exceptions carry precise information** Do not lump multiple error conditions into a single exception type. Instead, use a different exception for each semantic error condition; otherwise, the caller cannot distinguish between different causes for an error.

**C++ mapping for user exceptions**

When you run the IDL compiler on IDL interface `Bank`, it translates user exceptions into C++ classes. For example, the compiler translates `Bank::AccountAlreadyExists` into a C++ class of the same name:

```
class Bank : public virtual CORBA::Object
{
public:
...
class AccountAlreadyExists : public CORBA::UserException
{
public:

 AccountAlreadyExists();
 AccountAlreadyExists(const char* _ifid_account_id);
 ...
 //string manager
 IIFGenAccountId_mgr account_id;

 static AccountAlreadyExists* _downcast(
 CORBA::Exception* exc
);

 static const AccountAlreadyExists* _downcast(
 const CORBA::Exception* exc
);
 ...
 virtual void _raise() const;
 ...
};
...
};
```

The `AccountAlreadyExists` class is nested within class `Bank`. Each C++ class that corresponds to an IDL exception has a constructor that takes a parameter for each exception member. Because the `AccountAlreadyExists` exception has one `AccountId` member, class `Bank::AccountAlreadyExists` has a constructor that allows it to be initialized.

## Handling Exceptions

Client code uses standard `try` and `catch` blocks to isolate processing logic from exception handling code. You can associate multiple `catch` blocks with each `try` block. You should write the code so that handling for specific exceptions takes precedence over handling for other unspecified exceptions.

## Handling User Exceptions

If an operation might throw a user exception, its caller should be prepared to handle that exception with an appropriate `catch` clause.

[Example 13](#) shows how you might program a client to catch exceptions. In it, the handler for the `AccountAlreadyExists` exception outputs an error message and exits the program. The code follows standard C++ practice by passing the parameter to the `catch` clause by reference. The `operator<()` that is defined on class `SystemException` outputs a text description of the individual system exception that was thrown.

### Example 13: Programming a client to catch user exceptions

```
void
BankMenu::do_create()
 throw(CORBA::SystemException)
{
 cout << "Enter account name: " << flush;
 char name[1024];
 cin >> name;
 cout << "Enter starting balance: " << flush;
 BankDemo::CashAmount amount;
 cin >> amount;

 //try/catch to handle user exception, system exceptions are
 //handled in the main menu loop
 try
 {
 BankDemo::AccountVar account =
 m_bank->create_account(name, amount);

 //start a sub-menu with the returned account reference
 AccountMenu sub_menu(account);
 sub_menu.run();

 //_var types automatically clean up on return
 //orexception
 }
}
```

**Example 13:** *Programming a client to catch user exceptions*

```
catch (
 const BankDemo::Bank::AccountAlreadyExists& already_exists)
{
 cout << "Account already exists: "
 << already_exists.account_id << endl;
}
}
```

## Handling System Exceptions

A client often provides a handler for a limited set of anticipated system exceptions. It also must provide a way to handle all other unanticipated system exceptions that might occur.

### Precedence of exception handlers

The handler for a specific system exception must appear before the handler for `CORBA::SystemException`. C++ catch clauses are attempted in the order specified, and the first matching handler is called. Because of implicit casting, a handler for `CORBA::SystemException` matches all system exceptions (all system exception classes are derived from class `CORBA::SystemException`), so it should appear after all handlers for specific system exceptions.

If you want to know the type of system exception that occurred, use the message output by the proprietary `operator<<()` function on class `CORBA::SystemException`. Handlers for individual system exceptions are necessary only when they require a specific action.

The following client code specifically tests for a `COMM_FAILURE` exception; it can also handle any other system exceptions:

#### Example 14: Handling system exception `COMM_FAILURE`

```
void
BankMenu::run() {
 //make sure bank reference is valid
 if (CORBA::is_nil(m_bank)) {
 cout<< "Cannot proceed -bank reference is nil";
 }
 else {
 //begin printing the menu and executing selections
 for (;;) {
 cout<< endl;
 cout<< "0 -quit"<< endl;
 cout<< "1 -create_account"<< endl;
 cout<< "2 -find_account"<< endl;
 cout<< "Selection [0-2]: "<< flush;
 int selection;
 cin>> selection;
 }
 }
}
```

**Example 14:** *Handling system exception COMM\_FAILURE*

```
try {
 switch(selection) {
 case 0: return;
 case 1: do_create(); break;
 case 2: do_find(); break;
 }
}
catch (CORBA::COMM_FAILURE& e) {
 cout << "Communication failure exception: "
 << e << endl;
 return;
}
catch (const CORBA::SystemException& e) {
 cout << "Unexpected exception: " << e << endl;
 return;
}
}
```

---

## Evaluating System Exceptions

System exceptions have two member methods, `completed()` and `minor()`, that let a client evaluate the status of an invocation:

- `completed()` returns an enumerator that indicates how far the operation or attribute call progressed.
- `minor()` returns an IDL `unsigned long` that offers more detail about the particular system exception that was thrown.

---

### Obtaining invocation completion status

Each standard exception includes a `completion_status` code that takes one of the following integer values:

**COMPLETED\_NO:** The system exception was thrown before the operation or attribute call began to execute.

**COMPLETED\_YES:** The system exception was thrown after the operation or attribute call completed execution.

**COMPLETED\_MAYBE:** It is uncertain whether or not the operation or attribute call started to execute, and if so, whether execution completed. For example, the status is `COMPLETED_MAYBE` if a client's host receives no indication of success or failure after transmitting a request to a target object on another host.

---

### Evaluating minor codes

`minor()` returns an IDL `unsigned long` that offers more detail about the particular system exception thrown. For example, if a client catches a `COMM_FAILURE` system exception, it can access the system exception's `minor` field to determine why this occurred

All standard exceptions have an associated minor code that provides more specific information about the exception in question. Given these minor codes, the ORB is not required to maintain an exhaustive list of all possible exceptions that might arise at runtime.

Minor exception codes are defined as an `unsigned long` that contains two components:

- 20-bit vendor minor code ID (VMCID)
- Minor code that occupies the 12 low order bits

All minor codes are based on the IONA vendor minor code ID (DNA\_VMCID), which is 0x49540000. The space reserved to IONA ends at 0x49540FFF.

The VMCID assigned to OMG standard exceptions is 0x494d0000. You can obtain the minor code value for any exception by OR'ing the VMCID with the minor code for the exception in question. All minor code definitions are associated with readable strings.

### Subsystem minor codes

Orbix defines minor codes within each subsystem. When an exception is thrown, the current subsystem associates the exception with a valid minor code that maps to a unique error condition. Table 16 lists Orbix subsystems and base values for their minor codes:

**Table 16:** Base minor code values for Orbix subsystems

| Subsystem              | Logging ID              | Minor Code ID     |
|------------------------|-------------------------|-------------------|
| IT_SOAP                | IT_SOAP                 | DNA_VMCID + 0x080 |
| IT_Core                | IT_CORE                 | DNA_VMCID + 0x100 |
| IT_CONFIG_REP          | IT_CONFIG_REP           | DNA_VMCID + 0x140 |
| IT_SOAP_Profile        | IT_SOAP_PROFILE         | DNA_VMCID + 0x180 |
| IT_GDP                 | IT_GDP                  | DNA_VMCID + 0x200 |
| Thread/Synch Package   | IT_TS                   | DNA_VMCID + 0x240 |
| IT_IDP                 | IT_IDP                  | DNA_VMCID + 0x300 |
| IT_PSS_ODBC            | IT_PSS_ODBC             | DNA_VMCID + 0x340 |
| IT_W SDL               | IT_W SDL                | DNA_VMCID + 0x380 |
| IT_IDP_PROFILE         | IT_IDP_PROFILE          | DNA_VMCID + 0x400 |
| IT_ATLI_DP             | none                    | DNA_VMCID + 0x440 |
| IT_ATLI_TCP            | IT_ATLI_TCP             | DNA_VMCID + 0x480 |
| IT_POA                 | IT_POA                  | DNA_VMCID + 0x500 |
| IT_PortableInterceptor | IT_PORTABLE_INTERCEPTOR | DNA_VMCID + 0x540 |
| IT_OTS_TM              | IT_OTS_TM               | DNA_VMCID + 0x580 |
| IT_PSS_R               | IT_PSS_R                | DNA_VMCID + 0x600 |

**Table 16:** Base minor code values for Orbix subsystems

| Subsystem          | Logging ID         | Minor Code ID     |
|--------------------|--------------------|-------------------|
| IT_XA              | IT_XA              | DNA_VM CD + 0x640 |
| IT_OTS_Encina      | IT_OTS_ENCINA      | DNA_VM CD + 0x680 |
| IT_PSS_DB          | IT_PSS_DB          | DNA_VM CD + 0x700 |
| IT_PAS subsystem s | IT_PAS_*           | DNA_VM CD + 0x740 |
| IT_SHM DP          | IT_SHM_DP          | DNA_VM CD + 0x780 |
| IT_PSS             | IT_PSS             | DNA_VM CD + 0x800 |
| IT_NOTIFICATION    | IT_NOTIFICATION    | DNA_VM CD + 0x840 |
| IT_ATLISHM         | IT_ATLISHM         | DNA_VM CD + 0x880 |
| IT_OTS             | IT_OTS             | DNA_VM CD + 0x900 |
| IT_TLS             | IT_TLS             | DNA_VM CD + 0x940 |
| IT_ATLIMULTICAST   | IT_ATLIMULTICAST   | DNA_VM CD + 0x980 |
| IT_OTS_Lite        | IT_OTS_LITE        | DNA_VM CD + 0xA00 |
| IT_IDP_TLS         | IT_IDP_TLS         | DNA_VM CD + 0xA40 |
| IT_OPAL            | IT_OPAL            | DNA_VM CD + 0xA80 |
| IT_LOCATOR         | IT_LOCATOR         | DNA_VM CD + 0xB00 |
| IT_NodeDaemon      | IT_NODE_DAEMON     | DNA_VM CD + 0xB40 |
| IT_EGMDP_Component | IT_EGMDP_COMPONENT | DNA_VM CD + 0xB80 |
| IT_POA_LOCATOR     | IT_POA_LOCATOR     | DNA_VM CD + 0xC00 |
| IT_KDM             | IT_KDM             | DNA_VM CD + 0xC40 |
| IT_EGMDP           | IT_EGMDP           | DNA_VM CD + 0xC80 |
| IT_ACTIVATOR       | IT_ACTIVATOR       | DNA_VM CD + 0xD00 |
| IT_Daemon          | IT_DAEMON          | DNA_VM CD + 0xE00 |
| IT_JIA             | IT_JIA             | DNA_VM CD + 0xE40 |
| IT_NAMING          | IT_NAMING          | DNA_VM CD + 0xF00 |

**Table 18:** Base minor code values for Orbix subsystems

| Subsystem    | Logging ID   | Minor Code ID       |
|--------------|--------------|---------------------|
| IT_COBOL_PLI | IT_COBOL_PLI | IONA_VM CID + 0xF40 |
| IT_MVS       | IT_MVS       | IONA_VM CID + 0xF80 |

For example, the locator subsystem defines a number of minor codes for the `BAD_PARAM` standard exception. These distinguish among the various conditions under which the locator might throw the `BAD_PARAM` exception.

Definitions for all subsystem minor codes can be found in the directory `asp/version/xml/minor_codes` in a UNIX System Services installation, and in the `orbixhlq.INCLUDE.ORBIX@XT.HH` PDS in an OS/390 installation.

**Note:** OMG minor code constants are Orbix-specific mappings to minor codes that are set by the OMG. If you define minor codes for your own application, make sure that they do not overlap the ranges that are reserved for IONA-defined minor codes.

---

# Throwing Exceptions

Client code uses standard C++ syntax to initialize and throw both user-defined and system exceptions.

This section modifies `BankImpl::create_account()` to throw an exception. You can implement `create_account()` as follows:

### Example 15: Throwing an exception

```
// create a new account given an id and initial balance
// throw AccountAlreadyExists if account already in database

BankDem o::Account_ptr BankImpl::create_account(
 const char* account_id,
 CashAmount initial_balance) throw (
 CORBA::SystemException,
 BankDem o::Bank::AccountAlreadyExists)
{
 // create new account in database, then return a new
 // reference to that account
 if (!m_account_db.create_account(account_id,
 initial_balance))
 {
 throw BankDem o::Bank::AccountAlreadyExists(account_id);
 }

 return create_account_ref(account_id);
}
```

## Exception Safety

You should be careful that your code does not throw user exceptions that are not part of the operation's raises expression. Doing so can throw an `UNKNOWN` exception, or cause the program to terminate abruptly.

### Throwing illegal exceptions

For example, the following IDL defines operations `some_operation()` and `some_helper()`:

```
exception Failed {};
interface Example {
 void some_operation() raises(Failed);
};

exception DidnWork {};
interface Helper {
 void some_helper() raises(Failed, DidnWork);
};
```

The following implementation of `some_operation()` incorrectly calls `some_helper()`:

```
void ExampleImpl::some_operation()
 throw (CORBA::SystemException, Failed) {
 //do some work...
 //call helper operation.
 Helper_var help = ...;
 help->some_helper(); //BAD!
 //do remainder of work...
}
```

At some point during runtime, `some_helper()` is liable to throw an exception of `DidnWork` back to `some_operation()`, which is unable to handle it, and causing the server process to die.

## Catching illegal exceptions

If an operation calls helper operations on other objects, make sure that it can handle illegal exceptions. For example, the following example modifies `some_operation()` so that it can translate `Different` into a legal exception:

```
void ExampleImpl::some_operation()
 throw (CORBA::SystemException, Failed) {
 //do some work...
 //call helper operation.
 Helper_var help = ...;
 try {
 help->some_helper();
 }
 catch (const Different &) {
 throw Failed; //translate into legal exception
 }
 //do remainder of work...
 return;
}
```

## Avoiding resource leaks

Be careful also to avoid resource leaks in the presence of exceptions. For example, the IDL for `some_operation()` is modified here to return a string as an out parameter:

```
exception Failed {};
interface Example {
 void some_operation(out string s) raises(Failed);
};
```

The following implementation incorrectly leaks the string that is allocated to the `out` parameter:

```
void ExampleImpl::some_operation(CORBA::String_out s)
 throw (CORBA::SystemException, Failed) {

 //do some work to get the string value to be returned...
 char* str = some_function();
 s = CORBA::string_dup(str); //assign out param

 //call helper operation to do something else
 Helper_var help = ...;
 try {
 help->some_helper(); //memory leak!
 }
}
```

```

catch (const std::exception & e) {
 throw Failed; //memory leak!
}
//do remainder of work...
}

```

You can correct this problem by explicitly deallocating the parameter again, as in the following example:

```

void ExampleImpl::some_operation(CORBA::String_out& s)
throw (CORBA::SystemException, Failed) {

 //do some work to get the string value to be returned...
 char* str= some_function();
 s= CORBA::string_dup(str); //assign outparam

 //call helper operation to do something else
 Helper_var helper = ...;
 try {
 helper->some_helper();
 }
 catch (const std::exception & e) {
 CORBA::string_free(s.ptr()); //clean up
 throw Failed; //translate
 }
 catch (const CORBA::Exception & e) {
 CORBA::string_free(s.ptr()); //clean up
 throw; //rethrow
 }
 //do remainder of work...
}

```

---

# Throwing System Exceptions

Occasionally, a server program might need to throw a system exception. Specific system exceptions such as `COMM_FAILURE` inherit the `SystemException` constructor:

```
class SystemException : public Exception {
public:
 SystemException();
 SystemException(const SystemException &);
 SystemException(
 ULong minor_id, CompletionStatus completed_status);

class COMM_FAILURE : public SystemException { ... };
```

The following code uses this constructor to throw a `COMM_FAILURE` exception with minor code `SOCKET_WRITE_FAILED` and completion status `COMPLETED_NO`:

```
throw CORBA::COMM_FAILURE(HOST_LOOKUP_FAILED, COMPLETED_NO);
```



# Using Type Codes

*Orbix uses type codes to describe IDL types. The IDL pseudo interface `CORBA::TypeCode` lets you describe and manipulate type code values.*

Type codes are essential for the DII and DSI, to specify argument types. The interface repository also relies on type codes to describe types in IDL declarations. In general, type codes figure importantly in any application that handles `CORBA::Any` data types.

---

**In this chapter**

This chapter contains the following sections:

|                                      |                          |
|--------------------------------------|--------------------------|
| <a href="#">Type Code Components</a> | <a href="#">page 380</a> |
| <a href="#">Type Code Operations</a> | <a href="#">page 383</a> |
| <a href="#">Type Code Constants</a>  | <a href="#">page 390</a> |

# Type Code Components

Type codes are encapsulated in `CORBA::TypeCode` pseudo objects. Each `TypeCode` has two components:

**kind:** A `CORBA::TCKind` enumerator that associates the type code with an IDL type. For example, enumerators `tk_short`, `tk_boolean`, and `tk_sequence` correspond to IDL types `short`, `boolean`, and `sequence`, respectively.

**description:** One or more parameters that supply information related to the type code's kind. The number and contents of parameters varies according to the type code.

- The type code description for IDL type `fixed< 5, 3 >` contains two parameters, which specify the number of digits and the scale.
- The type code description for a `string` or `wstring` contains a single parameter that specifies the string's bound, if any.
- Type codes for primitive types require no description, and so have no parameters associated with them—for example, `tk_short` and `tk_long`.

## TCKind enumerators

The `CORBA::TCKind` enumeration defines all built-in IDL types:

```
// In module CORBA
enum TCKind {
 tk_null, tk_void, tk_short, tk_long, tk_ushort, tk_ulong,
 tk_float, tk_double, tk_boolean, tk_char, tk_octet, tk_any,
 tk_TypeCode, tk_Principal, tk_Object, tk_struct, tk_union,
 tk_enum, tk_string, tk_sequence, tk_array, tk_alias,
 tk_except, tk_longlong, tk_ulonglong, tk_longdouble,
 tk_wchar,
 tk_wstring, tk_fixed, tk_value, tk_value_box, tk_native,
 tk_abstract_interface
};
```

Most of these are self-explanatory—for example, a type code with a `TCKind` of `tk_boolean` describes the IDL type `boolean`. Some, however, have no direct association with an IDL type:

**tk\_alias** describes an IDL type definition such as `typedef string`.

**tk\_null** describes an empty value condition. For example, if you construct an `Any` with the default constructor, the `Any`'s type code is initially set to `tk_null`.

**tk\_Principal** is deprecated for applications that are compliant with CORBA 2.3 and later; retained for backward compatibility with earlier applications that use the BOA.

**tk\_TypeCode** describes another type code value.

**tk\_value** describes a value type.

**tk\_value\_box** describes a value box type.

**tk\_void** is used by the interface repository to describe an operation that returns no value.

[Table 17](#) shows type code parameters. The table omits type codes with an empty parameter list.

**Table 17:** *Type Codes and Parameters*

| TCKind                             | Parameters                                                                 |
|------------------------------------|----------------------------------------------------------------------------|
| <code>tk_abstract_interface</code> | <code>repository-id, name</code>                                           |
| <code>tk_alias</code>              | <code>repository-id, name, type-code</code>                                |
| <code>tk_anay</code>               | <code>type-code, length...</code>                                          |
| <code>tk_enum</code>               | <code>repository-id, name, { member-name }...</code>                       |
| <code>tk_except</code>             | <code>repository-id, name,<br/>{ member-name, member-type-code }...</code> |
| <code>tk_fixed</code>              | <code>digits, scale</code>                                                 |
| <code>tk_native</code>             | <code>repository-id, name</code>                                           |
| <code>tk_objref</code>             | <code>repository-id, name</code>                                           |
| <code>tk_sequence</code>           | <code>element-type-code, max-length<sup>a</sup></code>                     |

**Table 17:** *Type Codes and Parameters*

| TCKind                  | Parameters                                                                                                                |
|-------------------------|---------------------------------------------------------------------------------------------------------------------------|
| tk_string<br>tk_wstring | <i>max-length</i> <sup>a</sup>                                                                                            |
| tk_struct               | <i>repository-id, name,</i><br><i>{ member-name, member-type-code }...</i>                                                |
| tk_union                | <i>repository-id, name, switch-type-code, default-index,</i><br><i>{ member-label, member-name, member-type-code }...</i> |
| tk_value                | <i>repository-id, name, type-modifier, type-code,</i><br><i>{ member-name, member-type-code, visibility }...</i>          |
| tk_value_box            | <i>repository-id, name,</i><br><i>{ member-name, member-type-code } ...</i>                                               |

a. For unbounded sequences, strings, and wstrings, this value is 0

---

# Type Code Operations

The `CORBA::TypeCode` interface provides a number of operations that you can use to evaluate and compare `TypeCode` objects. These operations can be divided into two categories:

- [General type code operations](#) that can be invoked on all `TypeCode` objects.
- [Type-specific operations](#) that are associated with `TypeCode` objects of a specific `TCKind`, and raise a `BadKind` exception if invoked on the wrong type code.

---

## General Type Code Operations

The following operations are valid for all `TypeCode` objects:

- `equal()`, `equivalent()`
  - `get_compact_typecode()`
  - `kind()`
- 

### `equal()`, `equivalent()`

```
boolean equal(in TypeCode tc);
boolean equivalent(in TypeCode tc);
```

`equal()` and `equivalent()` let you evaluate a type code for equality with the specified type code, returning true if they are the same:

**`equal()`** requires that the two type codes be identical in their `TCKind` and all parameters—member names, type names, repository IDs, and aliases.

**`equivalent()`** resolves an aliased type code (`TCKind = tk_alias`) to its base, or unaliased type code before it compares the two type codes' `TCKind` parameters. This also applies to aliased type codes of members that are defined for type codes such as `tk_struct`.

For both operations, the following parameters are always significant and must be the same to return true:

- Number of members for `TCKinds` of `tk_enum`, `tk_except`, `tk_struct`, and `tk_union`.
- Digits and scale for `tk_fixed` type codes.
- The value of the bound for type codes that have a bound parameter—`tk_array`, `tk_sequence`, `tk_string` and `tk_wstring`.
- Default index for `tk_union` type codes.
- Member labels for `tk_union` type codes. Union members must also be defined in the same order.

Both `equal()` and `equivalent()` can take a type code constant as an argument—for example, `_to_short` or `_to_float` for IDL types `short` or `float` respectively. For more information about type code constants, [see page 390](#).

You must use `equal()` and `equivalent()` to evaluate a type code. For example, the following code is illegal:

```
CORBA::Any another_any;
another_any <<= "Hello world";
CORBA::TypeCode_ptr tc = another_any.type();

if (tc = CORBA::tc_string) { ... } //Bad code!!
```

You can correct this code as follows:

```
CORBA::Any another_any;
another_any <<= "Hello world";
CORBA::TypeCode_ptr tc = another_any.type();

//use equal or equivalent to evaluate type code
if (tc->equivalent(CORBA::tc_string)) { ... }
if (tc->equal(CORBA::tc_string)) { ... }
```

---

## `get_compact_typecode()`

```
TypeCode get_compact_typecode();
```

`get_compact_typecode()` removes type and member names from a type code. This operation is generally useful only to applications that must minimize the size of type codes that are sent over the wire.

---

## `kind()`

```
TCKind kind();
```

`kind()` returns the `TCKind` of the target type code. You can call `kind()` on a `TypeCode` to determine what other operations can be called for further processing—for example, use the `TCKind` return as a switch discriminator:

```

CORBA::Any another_any = ...;
CORBA::TypeCode_var = another_any.type();

switch(t->kind()){
case CORBA::tk_short:
...
case CORBA::tk_long:
...
//continue for all tk_values
default:
...
}

```

## Type-Specific Operations

Table 18 shows operations that can be invoked only on certain type codes. In general, each operation gets information about a specific type-code parameter. If invoked on the wrong type code, these operations raise an exception of `BadKind`.

**Table 18:** *Type-Specific Operations*

| TCKind                 | Operations                                                                                                                          |
|------------------------|-------------------------------------------------------------------------------------------------------------------------------------|
| <code>tk_alias</code>  | <code>id()</code><br><code>name()</code><br><code>content_type()</code>                                                             |
| <code>tk_array</code>  | <code>length()</code><br><code>content_type()</code>                                                                                |
| <code>tk_enum</code>   | <code>id()</code><br><code>name()</code><br><code>member_count()</code><br><code>member_name()</code>                               |
| <code>tk_except</code> | <code>id()</code><br><code>name()</code><br><code>member_count()</code><br><code>member_name()</code><br><code>member_type()</code> |

Table 18: Type-Specific Operations

| TCKind                  | Operations                                                                                                                           |
|-------------------------|--------------------------------------------------------------------------------------------------------------------------------------|
| tk_fixed                | fixed_digits()<br>fixed_scale()                                                                                                      |
| tk_native               | id()<br>name()                                                                                                                       |
| tk_objref               | id()<br>name()                                                                                                                       |
| tk_sequence             | length()<br>content_type()                                                                                                           |
| tk_string<br>tk_wstring | length()                                                                                                                             |
| tk_struct               | id()<br>name()<br>member_count()<br>member_name()<br>member_type()                                                                   |
| tk_union                | id()<br>name()<br>member_count()<br>member_name()<br>member_label()<br>discriminator_type()<br>default_index()                       |
| tk_value                | id()<br>name()<br>member_count()<br>member_name()<br>member_type()<br>type_modifier()<br>concrete_base_type()<br>member_visibility() |
| tk_value_box            | id()<br>name()<br>member_name()                                                                                                      |

Table 19 briefly describes the information that you can access through type code-specific operations. For detailed information about these operations, see the *CORBA Programmer's Reference*.

**Table 19:** *Information Obtained by Type-Specific Operations*

| Operation                         | Returns:                                                                                                                                                                        |
|-----------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>concrete_base_type()</code> | Type code of the concrete base for the target type code; applies only to value types.                                                                                           |
| <code>content_type()</code>       | For aliases, the original type. For sequences and arrays, the specified member's type.                                                                                          |
| <code>default_index()</code>      | Index to a union's default member. If no default is specified, the operation returns <code>-1</code> .                                                                          |
| <code>discriminator_type()</code> | Type code of the union's discriminator.                                                                                                                                         |
| <code>fixed_digits()</code>       | Number of digits in a fixed-point type code.                                                                                                                                    |
| <code>fixed_scale()</code>        | Scale of a fixed-point type code.                                                                                                                                               |
| <code>id()</code>                 | Type code's repository ID.                                                                                                                                                      |
| <code>length()</code>             | Value of the bound for a type code with <code>TK.ind</code> of <code>tk_string</code> , <code>tk_wstring</code> , <code>tk_sequence</code> , or <code>tk_array</code> .         |
| <code>member_count()</code>       | Number of members in the type code.                                                                                                                                             |
| <code>member_label()</code>       | An <code>Any</code> value that contains the value of the union case label for the specified member.                                                                             |
| <code>member_name()</code>        | Name of the specified member. If the supplied index is out of bounds (greater than the number of members), the function raises the <code>TypeCode:Bounds</code> exception.      |
| <code>member_type()</code>        | Type code of the specified member. If the supplied index is out of bounds (greater than the number of members), the function raises the <code>TypeCode:Bounds</code> exception. |

**Table 19:** *Information Obtained by Type-Specific Operations*

| Operation           | Returns:                                                                                                           |
|---------------------|--------------------------------------------------------------------------------------------------------------------|
| member_visibility() | The <code>Visibility</code> ( <code>PRIVATE_MEMBER</code> or <code>PUBLIC_MEMBER</code> ) of the specified member. |
| name()              | Type code's user-assigned unscoped name.                                                                           |
| type_modifier()     | Value modifier that applies to the value type that the target type code represents.                                |

---

# Type Code Constants

Orbis provides type code constants that you can use to evaluate and compare type code objects:

- [Built-in type code constants](#) are provided for each `TKind` enumerator (see page 380).
- [User-defined type code constants](#) are generated by the IDL compiler for IDL types that you declare in your application code.

---

## Built-in type code constants

Orbis provides predefined `CORBA::TypeCode` object reference constants that let you access type codes for standard types.

|                                   |                                  |
|-----------------------------------|----------------------------------|
| <code>CORBA::tc_any</code>        | <code>CORBA::tc_string</code>    |
| <code>CORBA::tc_boolean</code>    | <code>CORBA::tc_ulong</code>     |
| <code>CORBA::tc_char</code>       | <code>CORBA::tc_ulonglong</code> |
| <code>CORBA::tc_double</code>     | <code>CORBA::tc_ushort</code>    |
| <code>CORBA::tc_float</code>      | <code>CORBA::tc_void</code>      |
| <code>CORBA::tc_long</code>       | <code>CORBA::tc_wchar</code>     |
| <code>CORBA::tc_longdouble</code> | <code>CORBA::tc_wstring</code>   |
| <code>CORBA::tc_longlong</code>   | <code>CORBA::tc_Object</code>    |
| <code>CORBA::tc_null</code>       | <code>CORBA::tc_TypeCode</code>  |
| <code>CORBA::tc_octet</code>      | <code>CORBA::tc_ValueBase</code> |
| <code>CORBA::tc_short</code>      |                                  |

---

## User-defined type code constants

The IDL compiler generates type code constants for declarations of these types:

```
interface
typedef
struct
union
enum
valuetype
valuebox
```

For each user-defined type that is declared in an IDL file, the IDL compiler generates a `CORBA::TypeCode_ptr` that points to a type code constant. These constants have the format `_tc_type` where `type` is the user-defined type. For example, given the following IDL:

```
interface Interesting {
 typedef long longType;
 struct Useful
 {
 longType l;
 };
};
```

the IDL compiler generates the following `CORBA::TypeCode_ptr` constants:

- `_tc_Interesting`
- `Interesting::_tc_longType`
- `Interesting::_tc_Useful`



# Using the Any Data Type

*IDL's any type lets you specify values that can express any IDL type.*

This allows a program to handle values whose types are not known at compile time. The any type is most often used in code that uses the interface repository or the dynamic invocation interface (DII).

---

## IDL-C++ mapping

The IDL `any` type maps to the C++ `CORBA::Any` class. Conceptually, this class contains the following two instance variables:

**type** is a `TypeCode` object that provides full type information for the value contained in the `any`. The `Any` class provides a `type()` method to return the `TypeCode` object.

**value** is the internal representation used to store `Any` values and is accessible via standard insertion and extraction methods.

For example, the following interface, `AnyDemo`, contains an operation that defines an `any` parameter:

```
//IDL
interface AnyDemo {
 //Takes in any type that can be specified in IDL
 void passSomethingIn (in any any_type_parameter);

 //Passes out any type specified in IDL
 any getSomethingBack();

 ...
};
```

Given this interface, a client that calls `passSomethingIn` constructs an `any` that specifies the desired IDL type and value, and supplies this as an argument to the call. On the server side, the `AnyDemo` implementation that processes this call can determine the type of value the `any` stores and extract its value.

## In this chapter

This chapter covers the following topics:

|                                                                             |                          |
|-----------------------------------------------------------------------------|--------------------------|
| <a href="#">Inserting Typed Values Into Any</a>                             | <a href="#">page 395</a> |
| <a href="#">Extracting Typed Values From Any</a>                            | <a href="#">page 398</a> |
| <a href="#">Inserting and Extracting Booleans, Octets, Chars and WChars</a> | <a href="#">page 401</a> |
| <a href="#">Inserting and Extracting Array Data</a>                         | <a href="#">page 402</a> |
| <a href="#">Inserting and Extracting String Data</a>                        | <a href="#">page 403</a> |
| <a href="#">Inserting and Extracting Alias Types</a>                        | <a href="#">page 406</a> |
| <a href="#">Querying a CORBA::Any's Type Code</a>                           | <a href="#">page 408</a> |
| <a href="#">Using DynAny Objects</a>                                        | <a href="#">page 409</a> |
| <a href="#">Creating a DynAny</a>                                           | <a href="#">page 412</a> |
| <a href="#">Inserting and Extracting DynAny Values</a>                      | <a href="#">page 417</a> |

---

# Inserting Typed Values Into Any

The insertion operator `< <=` lets you set an `any`'s value and data type. The insertion operator sets a `CORBA::Any` value and its data type property (`CORBA::TypeCode`). Thus set, you can extract an `any`'s value and data type through the corresponding extraction operator (see page 398).

## Type-specific insertion operator functions

The C++ class `CORBA::Any` contains predefined overloaded versions of the insertion operator function `operator< <= ()`. Orbix provides insertion operator functions for all IDL types that map unambiguously to C++ types, such as `long`, `float`, or unbounded `string`. For a full listing of these functions and their data types, refer to `CORBA::Any::operator< <= ()`. The IDL compiler also generates an insertion operator for each user-defined type.

For example, `CORBA::Any` contains the following insertion operator function for `short` data types:

```
void operator< <= (CORBA::Short& s);
```

Given this function, you can use the insertion operator to supply a short data type to `passSomethingIn()` as follows:

```
void AnyDemo::do_send_short() {
 try {
 AnyDemo o_varx= ...;
 CORBA::Any a;
 CORBA::Short toPass;
 toPass = 26;
 a < <= toPass;
 x->passSomethingIn(a);
 }
 catch (CORBA::SystemException &sysEx) {
 ...
 }
}
```

## Type safety

Insertion operators provide a type-safe mechanism for inserting data into an `any`. The type of value to insert determines which insertion operator is used. Attempts to insert a value that has no corresponding IDL type yield compile-time errors.

**Memory management of inserted data**

Depending on the type of the data, insertion using an `operator< = ()` has one of the following effects:

- `_duplicate()` is called on an object reference.
- `_add_ref()` is called on a valuetype.
- a deep copy is made for all other data types.

When the `Any` is subsequently destroyed, the `Any` destructor performs one of the following actions, depending on the `Any.type()` field:

- `CORBA::release()` is called on an object reference.
- `_remove_ref()` is called on a valuetype.
- `delete` is called on all other data types.

**Inserting user-defined types**

The IDL shown earlier can be modified to include this `typedef` declaration:

```
//IDL
typedef sequence< long> LongSequence;
```

Given this statement, the IDL compiler generates the following insertion operator function for `LongSequence` data types:

```
void operator< = (CORBA::Any& a, const LongSequence& t);
```

Clients that call `passSomethingIn()` can use the insertion operator to insert `LongSequence` data into the function's `any` parameter:

**Example 16: Inserting user-defined type**

```
void AnyDemo::do_send_sequence() {
 try {
 CORBA::Any a;

 //Build a sequence of length 2
 LongSequence sequence_to_insert(2);
 sequence_to_insert.length(2);

 //Initialize the sequence values
 sequence_to_insert[0] = 1;
 sequence_to_insert[1] = 2;
 }
}
```

**Example 16:** *Inserting user-defined type*

```
//Insert sequence into the any
a <<= sequence_to_insert;
...
//Call passSomething and supply any data as argument
m_any_demo->passSomething(a);
}
catch (CORBA::SystemException &sysEx) {
...
}
}
```

## Extracting Typed Values From Any

The extraction operator `>>=` lets you get the value that a `CORBA::Any` contains and returns a `CORBA::Boolean`: `true` (1) if the any's `TypeCode` matches the extraction operation's target operand, or `false` (0) if a mismatch occurs.

### Type-specific extraction operator functions

The C++ class `CORBA::Any` contains predefined overloaded versions of the extraction operator function `operator>>=()`. Orbix provides extraction operator functions for all IDL types that map unambiguously to C++ types, such as `long`, `float`, or unbounded `string`. For a full listing of these functions and their data types, refer to `CORBA::Any::operator>>=()`. The IDL compiler also generates an extraction operator for each user-defined type.

For example, `CORBA::Any` contains the following extraction operator function for `short` data types:

```
CORBA::Boolean operator>>= (CORBA::Short& s) const;
```

Given this function, a server implementation of `passSomethingIn()` can use the extraction operator to extract a `short` from the function's parameter `anyIn`:

```
void AnyDemo_i::passSomethingIn(const CORBA::Any& anyIn) {
 CORBA::Short toExtract = 0;

 if (anyIn >>= toExtract) {
 //Print the value
 cout << "passSomethingIn() returned a string:"
 << toExtract << endl << endl;
 }
 else {
 cerr << "Unexpected value contained in any" << endl;
 }
}
```

### Memory management of extracted data

When a user-defined type is extracted from an `Any`, the data is not copied or duplicated in any way. The extracted data is, therefore, subject to the following restrictions:

- No modifications to the extracted data are allowed. The extracted data is read-only.
- Deallocation of the extracted data is not allowed. The `Any` retains ownership of the data.

To overcome the restrictions on extracted data, you must explicitly make a copy of the data and modify the new copy instead.

## Extracting user-defined types

More complex, user-defined types can be extracted with the extraction operators generated by the IDL compiler. For example, the IDL shown earlier can be modified to include this `typedef` declaration:

```
//IDL
typedef sequence< long> LongSequence;
```

Given this statement, the IDL compiler generates the following extraction operator function for `LongSequence` data types:

```
CORBA::Boolean operator>> = (CORBA::Any& a, LongSequence*& t)
const;
```

The generated extraction operator for user-defined types takes a pointer to the generated type as the second parameter. If the call to the operator succeeds, this pointer points to the memory managed by the `CORBA::Any`. Because a `CORBA::Any` manages this memory, it is not appropriate to extract its value into a `_var` variable—attempting to do so results in a compile-time error.

You can extract a `LongSequence` from a `CORBA::Any` as follows:

### Example 17: Extracting a `LongSequence`

```
void AnyDemo::do_get_any() {
 CORBA::Any var_a;
 cout << "Call getSomethingBack" << endl;
 a = m_any_demo->getSomethingBack();

 LongSequence* extracted_sequence = 0;
```

**Example 17:** *Extracting a LongSequence*

```
if (a >= extracted_sequence) {
 cout << "returned any contains sequence with value :"
 << endl;
 print_sequence(extracted_sequence);
}

else {
 cout << "unexpected value contained in any" << endl;
}
}
```

**Note:** It is an error to attempt to access the storage associated with a `CORBA::Any` after the `CORBA::Any` variable has been deallocated.

# Inserting and Extracting Booleans, Octets, Chars and WChars

Orbix's IDL to C++ mapping for IDL types `char`, `wchar`, `boolean` and `octet` prevents the overloaded insertion and extraction operators from distinguishing between these four data types. Consequently, you cannot use these operators directly to insert and extract data for these three IDL types.

The `CORBA::Any` class contains a set of insertion and extraction operator functions that use helper types for `char`, `wchar`, `boolean`, and `octet` types:

```
void operator< <= (CORBA::Any::from_char c);
void operator< <= (CORBA::Any::from_wchar wc);
void operator< <= (CORBA::Any::from_boolean b);
void operator< <= (CORBA::Any::from_octet o);

Boolean operator> >= (CORBA::Any::to_char c) const;
Boolean operator> >= (CORBA::Any::to_wchar wc) const;
Boolean operator> >= (CORBA::Any::to_boolean b) const;
Boolean operator> >= (CORBA::Any::to_octet o) const;
```

You can use these helper types as in the following example:

## Example 18: Inserting and extracting boolean types

```
CORBA::Any a;

// Insert a boolean into CORBA::Any
CORBA::Boolean b = 1;
a <<= CORBA::Any::from_boolean(b);

// Extract the boolean
CORBA::Boolean extractedValue;
if (a >>= CORBA::Any::to_boolean(extractedValue)){
 cout << "Success!" << endl;
}
```

## Inserting and Extracting Array Data

IDL arrays map to regular C++ arrays. Because arrays can have different lengths and an array variable points only to the array's first element, the IDL compiler generates a distinct C++ type for each IDL array. The type name is concatenated from the array name and the suffix `_foany`.

For example, the IDL shown earlier can be modified to include this two-dimensional array definition:

```
//IDL
typedef long lngArray[2][2];
```

Given this `typedef` statement, the IDL compiler generates a `lngArray_foany` type. The following example shows how to use insertion and extraction operators to move data between this type and a `CORBA:Any`:

### Example 19: Inserting and extracting array data

```
lngArray m_array = { {14,15}, {24,25} };

//Insertion
CORBA:Any a;
a <<= lngArray_foany(m_array);

//Extraction
lngArray_foany extractedValue;
if (a >>= extractedValue) {
 cout << "Element [1][2] is "
 << extractedValue[1][2] << endl;
}
```

Like `array_vartypes`, `_foany` types provide an `operator[]()` function to access array members. However, when a `_foany` type is destroyed, the storage that is associated with the array remains intact. This is consistent with the behavior of the extraction operator `>>=`, where the `CORBA:Any` retains ownership of the memory that the operator returns. Thus, the previous code is safe from memory leaks.

---

# Inserting and Extracting String Data

Helper types are also provided for insertion and extraction of `string` and `wstring` types.

## Inserting strings

The `from_string` and `from_wstring` struct types are used in combination with the insertion operator `>>=` to insert strings and wide strings. Two constructors are provided for the `from_string` type:

```
CORBA::Any::from_string(
 char* s,
 CORBA::ULong b,
 CORBA::Boolean ncopy = 0
)
CORBA::Any::from_string(const char* s, CORBA::ULong b)
```

The constructor parameters can be explained as follows:

`s` is a pointer to the string to be inserted.

`b` specifies the bound of a bounded string (0 implies unbounded).

`ncopy` specifies whether the string is copied before insertion (0 implies copying, 1 implies no copying and adoption).

Analogous constructors are provided for the `from_wstring` type:

```
CORBA::Any::from_wstring(
 CORBA::WChar* s,
 CORBA::ULong b,
 CORBA::Boolean ncopy = 0
)
CORBA::Any::from_wstring(const CORBA::WChar* s, CORBA::ULong b)
```

Examples of inserting bounded and unbounded string types are shown in the following code:

**Example 20:** *Inserting bounded and unbounded strings*

```
// Insert a copy of an unbounded string, string'.
CORBA::Any a1;
a1 << = CORBA::Any::from_string("Unbounded string", 0);
...
// Insert a copy of a bounded string, string< 100> '.
CORBA::Any a2;
a2 << = CORBA::Any::from_string("Bounded string", 100);
...

// Insert an unbounded string, string', passing
// ownership to the CORBA::Any'.
CORBA::Any a3;
char* unbounded = CORBA::string_dup("Unbounded string");
a3 << = CORBA::Any::from_string(unbounded, 0, 1);
...
// Insert a bounded string, string< 100> ', passing
// ownership to the CORBA::Any'.
CORBA::Any a4;
char* bounded = CORBA::string_dup("Bounded string");
a3 << = CORBA::Any::from_string(bounded, 100, 1);
```

Insertion of wide strings is performed in an analogous manner using the `CORBA::Any::from_wstring` type.

## Extracting strings

The `to_string` and `to_wstring` struct types are used in combination with the extraction operator `>>=` to extract strings and wide strings. One constructor is provided for the `to_string` type:

```
CORBA::Any::to_string(const char*& s, CORBA::ULong b);
```

The constructor parameters can be explained as follows:

`s` is a place holder that will point to the extracted string after a successful extraction is made.

`b` specifies the bound of a bounded string (0 implies unbounded).

An analogous constructor is provided for the `to_wstring` type:

```
CORBA::Any::to_wstring(const CORBA::WChar*& s, CORBA::ULong b);
```

Examples of extracting bounded and unbounded string types are shown in the following code:

**Example 21:** *Extracting bounded and unbounded strings*

```
//Extract an unbounded string, 'string'.
CORBA:Anya1;
const char* readonly_s;
if (a1 >> = CORBA:Any::to_string(readonly_s,0)){
 //process string, 'readonly_s'
}
...

//Extract a bounded string, 'string< 100> '.
CORBA:Anya2;
const char* readonly_bs;
if (a2 >> = CORBA:Any::to_string(readonly_bs,100)){
 //process bounded string, 'readonly_bs'
}
```

Extraction of wide strings is performed in an analogous manner using the `CORBA:Any::to_wstring` type.

## Inserting and Extracting Alias Types

The insertion and extraction operators `<<=` and `>>=` are invalid for *alias* types. An alias type is a type defined using a `typedef`.

For example, a bounded string alias is a type defined by making a `typedef` of a bounded string:

```
//DL
typedef string< 100> BoundedString;
```

This is mapped by the IDL compiler to a C++ `typedef` as follows:

```
//Stub code generated by the IDL compiler.
typedef char* BoundedString;
...
```

A C++ alias, such as `BoundedString`, cannot be used to distinguish an overloaded operator because it is not a distinct C++ type. This is the reason why the `<<=` and `>>=` operators cannot be used with alias types.

### Inserting alias types

The `BoundedString` alias type can be inserted into an `Any` as follows:

#### Example 22: Inserting an alias type

```
CORBA:Any a;
BoundedString bs = "Less than 100 characters.";
1 a <<= CORBA:Any::from_string(bs, 100);
2 a.type(_to_BoundedString); //Correct the type code!
```

The code executes as follows:

1. The data is inserted using the `<<=` operator and the `from_string` helper type. Initially, the `Any`'s type code is set equal to that of a bounded string with bound 100 (the type code for `string< 100>`). There is no type code constant available for the `string< 100>` type—the `<<=` operator creates one on the fly and uses it.
2. `CORBA:Any::type()` corrects the `Any`'s type code, setting it equal to the `_to_BoundedString` type code.

It is not permissible to use `type()` to reset the type code to arbitrary values—the new type code must be equivalent to the old one. Attempting to reset the type code to a non-equivalent value raises the `BAD_TYPECODE` system exception.

For example, calling `type()` with the `_tc_BoundedString` argument succeeds because the `BoundedString` type is equivalent to the `string< 100>` type.

## Extracting alias types

The `BoundedString` alias type can be extracted from an `Any` as follows:

### Example 23: Extracting an alias type

```

CORBA::Any a;
//The any 'a' is initialized with a BoundedString alias
// (as shown previously)
...
1 //Extract the BoundedString type
 const char* bs;
2 if (a >= CORBA::Any::to_string(bs, 100)) {
 cout << "Bounded string is:" << bs << "\n" << endl;
 }

```

1. The pointer to receive the extracted value, `bs`, is declared as `const char*`. You cannot declare `bs` as `const BoundedString` because that means a `const` pointer to `char`, or `char* const` which is not the same as `const char*` (pointer to `const char`).
2. The `to_string` constructor manufactures a type code for a `string< 100>` bounded string and compares this type with the `Any`'s type code. If the type codes are equivalent, the extraction succeeds.

## Querying a CORBA::Any's Type Code

Type code operations are commonly used to query a `CORBA::Any` for its type at runtime. For example, given this interface definition:

```
//IDL
struct Example {
 long l;
};
```

the IDL compiler generates the `CORBA::TypeCode_ptr` constant `_tc_Example`.

Assuming this interface definition:

```
//IDL
interface Bar {
 void op(in any a);
};
```

a client might invoke operation `op()` as follows:

```
//Client code
Bar_var bVar;
CORBA::Any a = ... ; // somehow initialize
...
bVar->op(a);
```

The server can then query the actual type of the parameter to `op()` as follows:

### Example 24: Querying a Any's type code


```
//Server code
void Bar::op(const CORBA::Any& a) {
 CORBA::TypeCode_ptr t(a->type());
 if (t->equivalent(_tc_Example)) {
 cerr << "Don't like struct Example!" << endl;
 }
 else ... //Continue processing here.
}
```

# Using DynAny Objects

The `DynAny` interface allows applications to compose and decompose `any` type values dynamically. With `DynAny`, you can compose a value at runtime whose type was unknown when the application was compiled, and transmit that value as an `any`. Conversely, an application can receive a value of type `any` from an operation, and interpret its type and extract its value without compile-time knowledge of its IDL type.

## Interface hierarchy

The `DynAny` API consists of nine interfaces. One of these, interface `DynAnyFactory`, lets you create `DynAny` objects. The rest of the `DynAny` API consists of the `DynAny` interface itself and derived interfaces, as shown in [Figure 20](#).



**Figure 20:** Interfaces that derive from the `DynAny` interface

The derived interfaces correspond to complex, or constructed IDL types such as `array` and `struct`. Each of these interfaces contains operations that are specific to the applicable type.

The `DynAny` interface contains a number of operations that apply to all `DynAny` objects; it also contains operations that apply to basic IDL types such as `long` and `string`.

The `DynStruct` interface is used for both IDL `struct` and `exception` types.

## Generic operations

The `DynAny` interface contains a number of operations that can be invoked on any basic or constructed `DynAny` object:

```
interface DynAny {
 exception InvalidValue{};
 exception TypeMismatch{};
 // ...

 void assign(in DynAny dyn_any) raises (TypeMismatch);
 DynAny copy();
 void destroy();

 boolean equal(in DynAny da);

 void from_any(
 in any value) raises (TypeMismatch, InvalidValue);
 any to_any();

 CORBA::TypeCode type();
 // ...
};
```

**assign()** initializes one `DynAny` object's value from another. The value must be compatible with the target `DynAny`'s type code; otherwise, the operation raises an exception of `TypeMismatch`.

**copy()** creates a `DynAny` whose value is a deep copy of the source `DynAny`'s value.

**destroy()** destroys a `DynAny` and its components.

**equal()** returns true if the type codes of the two `DynAny` objects are equivalent and if (recursively) all component `DynAny` objects have identical values.

**from\_any()** initializes a `DynAny` object from an existing `any` object. The source `any` must contain a value and its type code must be compatible with that of the target `DynAny`; otherwise, the operation raises an exception of `TypeMismatch`.

**to\_any()** initializes an `any` with the `DynAny`'s value and type code.

**type()** obtains the type code associated with the `DynAny` object. A `DynAny` object's type code is set at the time of creation and remains constant during the object's lifetime.

## Creating a DynAny

The `DynAnyFactory` interface provides two creation operations for `DynAny` objects:

```
module DynamicAny {
 interface DynAny; //Forward declaration

 //...
 interface DynAnyFactory
 {
 exception InconsistentTypeCode {};

 DynAny create_dyn_any(in any value)
 raises (InconsistentTypeCode);
 DynAny create_dyn_any_from_type_code(in CORBA::TypeCode type)
 raises (InconsistentTypeCode);
 };
};
```

### Create operations

The create operations return a `DynAny` object that can be used to manipulate any objects:

`create_dyn_any()` is a generic create operation that creates a `DynAny` from an existing `any` and initializes it from the `any`'s type code and value.

The type of the returned `DynAny` object depends on the `any`'s type code. For example: if the `any` contains a struct, `create_dyn_any()` returns a `DynStruct` object.

`create_dyn_any_from_type_code()` creates a `DynAny` from a type code. The value of the `DynAny` is initialized to an appropriate default value for the given type code. For example, if the `DynAny` is initialized from a string type code, the value of the `DynAny` is initialized to "" (empty string).

### Returned types

The type of the returned `DynAny` object depends on the type code used to initialize it. For example: if a struct type code is passed to `create_dyn_any_from_type_code()`, a `DynStruct` object is returned.

If the returned `DynAny` type is one of the constructed types, such as a `DynStruct`, you can narrow the returned `DynAny` before processing it further.

## create\_dyn\_any()

`create_dyn_any()` is typically used when you need to parse an `any` to analyse its contents. For example, given an `any` that contains an `enum` type, you can extract its contents as follows:

### Example 25: Creating a DynAny

```

//C++
#include <omg/DynAny.h>
//...
void get_any_val(const CORBA::Any& a){
1 //Get a reference to a 'DynAnyFactory' object
 CORBA::Object_var obj =
 global_obj->resolve_initial_references("DynAnyFactory");
 Dynam icAny::DynAnyFactory_var dyn_fact =
 Dynam icAny::DynAnyFactory::_narrow(obj);
 if (CORBA::is_nil(dyn_fact)) {
 //error: throw exception
 }

 //Get the Any's type code
 CORBA::TypeCode_var tc = a.type();
2 switch (tc->kind()){
 // ...
3 case CORBA::tk_enum : {
 Dynam icAny::DynAny_var da =
 dyn_fact->create_dyn_any(a);
 Dynam icAny::DynEnum_var de =
 Dynam icAny::DynEnum::_narrow(da);
 // ...
4 de->destroy();
 }
 break;
 }
}

```

The code executes as follows:

1. Call `resolve_initial_references("DynAnyFactory")` to obtain an initial reference to the `DynAnyFactory` object.

It is assumed that `global_orb` refers to an existing `CORBA::ORB` object that has been initialized prior to this code fragment.

Narrow the `CORBA::Object_ptr` object reference to the `DynAny::DynAnyFactory_ptr` type before it is used.

2. Analysis of a type code is begun by branching according to the value of its `kind` field. A general purpose subroutine for processing `DynAnyS` would require case statements for every possible IDL construct. Only the case statement for an `enum` is shown here.
3. The `DynAny` created in this step is initialized with the same type and value as the given `CORBA::Any` data type.

Because the `any` argument of `create_dyn_any()` contains an `enum`, the return type of `create_dyn_any()` is `DynAny::DynEnum_ptr`. The return value can therefore be narrowed to this type.

4. `destroy()` must be invoked on the `DynAny` object when you are finished with it.

## create\_dyn\_any\_from\_type\_code()

`create_dyn_any_from_type_code()` is typically used to create an `any` when stub code is not available for the particular type.

For example, consider the IDL `string< 128 >` bounded string type. In C++ you can insert this anonymous bounded string using the `CORBA::Any::from_string` helper type. Alternatively, you can use the `DynAny` programming interface as follows:

**Example 26:** *Inserting an anonymous bounded string.*

```

//C++
include <omg/DynAny.h>
//...
//Get a reference to a DynAny::DynAnyFactory' object
1 CORBA::Object_var obj
 = global_obj-> resolve_initial_references("DynAnyFactory");
DynAny::DynAnyFactory_var dyn_fact
 = DynAny::DynAnyFactory::narrow(obj);
if (CORBA::is_nil(dyn_fact)) {
 //error: throw exception
}

//Create type code for an anonymous bounded string type
CORBA::ULong bound = 128;
2 CORBA::TypeCode_var tc_v = global_obj-> create_string_tc(bound);

//Initialize a DynAny' containing a bounded string
3 DynAny::DynAny_var dyn_bounded_str
 = dyn_fact-> create_dyn_any_from_type_code(tc_v);
4 dyn_bounded_str-> insert_string("Less than 128 characters.");

//Convert DynAny' to a plain 'any'
5 CORBA::Any_var a = dyn_bounded_str-> to_any();
//...
//Cleanup DynAny'
6 dyn_bounded_str-> destroy();

```

The code executes as follows:

1. The initialization service gets an initial reference to the `DynAnyFactory` object by calling `resolve_initial_references("DynAnyFactory")`.

It is assumed that `global_orb` refers to an existing `CORBA::ORB` object that has been initialized prior to this code fragment.

The plain `CORBA::Object_ptr` object reference must be narrowed to the `DynAny::DynAnyFactory_ptr` type before it is used.

2. The `CORBA::ORB` class supports a complete set of functions for the dynamic creation of type codes. For example, `create_string_tc()` creates bounded or unbounded string type codes. The argument of `create_string_tc()` can be non-zero, to specify the bound of a bounded string, or zero, for unbounded strings.
3. A `DynAny` object, called `dyn_bounded_str`, is created using `create_dyn_any_from_type_code()`. The `dyn_bounded_str` is initialized with its type equal to the given bounded string type code, and its value equal to a blank string.
4. The value of `dyn_bounded_str` is set equal to the given argument of the `insert_string()` operation. Insertion operations, of the form `insert_BasicType`, are defined for all basic types as described in [“Accessing basic DynAny values” on page 417](#).
5. The `dyn_bounded_str` object is converted to a plain `any` that is initialized with the same type and value as the `DynAny`.
6. `destroy()` must be invoked on the `DynAny` object when you are finished with it.

**Note:** A `DynAny` object’s type code is established at its creation and cannot be changed thereafter.

---

# Inserting and Extracting DynAny Values

The interfaces that derive from `DynAny` such as `DynArray` and `DynStruct` handle insertion and extraction of `any` values for the corresponding IDL types. The `DynAny` interface contains insertion and extraction operations for all other basic IDL types such as `string` and `long`.

---

## Accessing basic DynAny values

The `DynAny` interface contains two operations for each basic type code, to insert and extract basic `DynAny` values: +

- An insert operation is used to set the value of the `DynAny`. The data being inserted must match the `DynAny`'s type code.

The `TypeMismatch` exception is raised if the value to insert does not match the `DynAny`'s type code.

The `InvalidValue` exception is raised if the value to insert is unacceptable—for example, attempting to insert a bounded string that is longer than the acceptable bound. The `InvalidValue` exception is also raised if you attempt to insert a value into a `DynAny` that has components when the current position is equal to `-1`. See [“Iterating Over DynAny Components” on page 422](#).

- Each extraction operation returns the corresponding IDL type.

The `DynAny::DynAny::TypeMismatch` exception is raised if the value to extract does not match the `DynAny`'s type code.

The `DynAny::DynAny::InvalidValue` exception is raised if you attempt to extract a value from a `DynAny` that has components when the current position is equal to `-1`. See [“Iterating Over DynAny Components” on page 422](#).

It is generally unnecessary to use a `DynAny` object in order to access `any` values, as it is always possible to access these values directly (see [page 395](#) and [page 398](#)). Insertion and extraction operations for basic `DynAny` types are typically used in code that iterates over components of a constructed `DynAny`, in order to compose and decompose its values in a uniform way (see [page 424](#)).

The IDL for insertion and extraction operations is shown in the following sections.

---

## Insertion Operations

The `DynAny` interface supports the following insertion operations:

```
void insert_boolean(in boolean value)
 raises (TypeM ism atch, InvalidValue);
void insert_octet(in octet value)
 raises (TypeM ism atch, InvalidValue);
void insert_char(in char value)
 raises (TypeM ism atch, InvalidValue);
void insert_short(in short value)
 raises (TypeM ism atch, InvalidValue);
void insert_ushort(in unsigned short value)
 raises (TypeM ism atch, InvalidValue);
void insert_long(in long value)
 raises (TypeM ism atch, InvalidValue);
void insert_ulong(in unsigned long value)
 raises (TypeM ism atch, InvalidValue);
void insert_float(in float value)
 raises (TypeM ism atch, InvalidValue);
void insert_double(in double value)
 raises (TypeM ism atch, InvalidValue);
void insert_string(in string value)
 raises (TypeM ism atch, InvalidValue);
void insert_reference(in Object value)
 raises (TypeM ism atch, InvalidValue);
void insert_typecode(in CORBA::TypeCode value)
 raises (TypeM ism atch, InvalidValue);
void insert_longlong(in long long value)
 raises (TypeM ism atch, InvalidValue);
void insert_ulonglong(in unsigned long long value)
 raises (TypeM ism atch, InvalidValue);
void insert_longdouble(in long double value)
 raises (TypeM ism atch, InvalidValue);
void insert_wchar(in wchar value)
 raises (TypeM ism atch, InvalidValue);
void insert_wstring(in wstring value)
 raises (TypeM ism atch, InvalidValue);
void insert_any(in any value)
 raises (TypeM ism atch, InvalidValue);
void insert_dyn_any(in DynAny value)
 raises (TypeM ism atch, InvalidValue);
void insert_val(in ValueBase value)
 raises (TypeM ism atch, InvalidValue);
```

For example, the following code fragment invokes `insert_string()` on a `DynAny` to create an `any` value that contains a string:

**Example 27:** *Creating an any with insert\_string()*

```
include <omg/DynAny.h>
//...
//Get a reference to a 'DynAnyFactory' object
CORBA::Object_var obj
 = global_obj->resolve_initial_references("DynAnyFactory");
DynAny::DynAnyFactory_var dyn_fact
 = DynAny::DynAnyFactory::narrow(obj);
if (CORBA::is_nil(dyn_fact)) {
 //error: throw exception
}

//create DynAny with a string value
DynAny::DynAny_var dyn_a;
dyn_a = dyn_fact->create_dyn_any_from_type_code(
 CORBA::to_string
);
dyn_a->insert_string("hot to worry!");

//convert DynAny to any
CORBA::Any_var a;
a = dyn_a->to_any();
//...
//destroy the DynAny
dyn_a->destroy();
```

## Extraction Operations

The IDL extraction operations supported by the DynAny interface are:

```

boolean get_boolean()
 raises (TypeM ism atch, InvalidValue);
octet get_octet()
 raises (TypeM ism atch, InvalidValue);
char get_char()
 raises (TypeM ism atch, InvalidValue);
short get_short()
 raises (TypeM ism atch, InvalidValue);
unsigned short get_ushort()
 raises (TypeM ism atch, InvalidValue);
long get_long()
 raises (TypeM ism atch, InvalidValue);
unsigned long get_ulong()
 raises (TypeM ism atch, InvalidValue);
float get_float()
 raises (TypeM ism atch, InvalidValue);
double get_double()
 raises (TypeM ism atch, InvalidValue);
string get_string()
 raises (TypeM ism atch, InvalidValue);
Object get_reference()
 raises (TypeM ism atch, InvalidValue);
CORBA::TypeCode get_typecode()
 raises (TypeM ism atch, InvalidValue);
long long get_longlong()
 raises (TypeM ism atch, InvalidValue);
unsigned long long get_ulonglong()
 raises (InvalidValue,TypeM ism atch);
long double get_longdouble()
 raises (TypeM ism atch, InvalidValue);
wchar get_wchar()
 raises (TypeM ism atch, InvalidValue);
wstring get_wstring()
 raises (TypeM ism atch, InvalidValue);
any get_any()
 raises (TypeM ism atch, InvalidValue);
DynAny get_dyn_any()
 raises (TypeM ism atch, InvalidValue);
ValueBase get_val()
 raises (TypeM ism atch, InvalidValue);

```

For example, the following code converts a basic `any` to a `DynAny`. It then evaluates the `DynAny`'s type code in a switch statement and calls the appropriate `get_` operation to obtain its value:

**Example 28:** *Converting a basic any to a DynAny.*

```
include <omg/DynAny.h>
//...
//Get a reference to a 'DynAnyFactory' object
CORBA::Object_var obj
 = global_obj-> resolve_initial_references("DynAnyFactory");
DynAny::DynAnyFactory_var dyn_fact
 = DynAny::DynAnyFactory::narrow(obj);
if (CORBA::is_nil(dyn_fact)) {
 //error: throw exception
}

CORBA::Any a = ...; //get Any from somewhere

//create DynAny from Any
DynAny::DynAny_var dyn_a = dyn_fact-> create_dyn_any(a);

//get DynAny's type code
CORBA::TypeCode_var tocode = dyn_a-> type();

//evaluate type code
switch(tocode-> kind()){
case CORBA::tk_short:
 {
 CORBA::Short s = dyn_a-> get_short();
 cout << "any contains short value of " << s << endl;
 break;
 }
case CORBA::tk_long:
 {
 CORBA::Long l = dyn_a-> get_long();
 cout << "any contains long value of " << l << endl;
 break;
 }
//other cases follow
...
} //end of switch statement

dyn_a-> destroy(); //cleanup
```

## Iterating Over DynAny Components

Five types of `DynAny` objects contain components that must be accessed to insert or extract values: `DynStruct`, `DynSequence`, `DynArray`, `DynUnion`, and `DynValue`. On creation, a `DynAny` object holds a current position equal to the offset of its first component. The `DynAny` interface has five operations that let you manipulate the current position to iterate over the components of a complex `DynAny` object:

```
module DynamicAny {
 //...
 interface DynAny {
 // ...
 // Iteration operations
 unsigned long component_count();
 DynAny current_component() raises (TypeMismatch);
 boolean seek(in long index);
 boolean next();
 void rewind();
 };
};
```

**component\_count()** returns the number of components of a `DynAny`. For simple types such as `long`, and for enumerated and fixed-point types, this operation returns 0. For other types, it returns as follows:

- `sequence`: number of elements in the sequence.
- `struct`, `exception` and `valuetype`: number of members.
- `array`: number of elements.
- `union`: 2 if a member is active; otherwise 1.

**current\_component()** returns the `DynAny` for the current component:

```
DynAny current_component()
```

You can access each of the `DynAny`'s components by invoking this operation in alternation with the `next()` operation. An invocation of `current_component()` alone does not advance the current position.

If an invocation of `current_component()` returns a derived type of `DynAny`, for example, `DynStruct`, you can narrow the `DynAny` to this type.

If you call `current_component()` on a type that has no components, such as a `long`, it raises the `TypeMismatch` exception.

If you call `current_component()` when the current position of the `DynAny` is `-1`, it returns a `nil` object reference.

**next()** advances the `DynAny`'s current position to the next component, if there is one:

```
boolean next();
```

The operation returns `true` if another component is available; otherwise, it returns `false`. Thus, invoking `next()` on a `DynAny` that represents a basic type always returns `false`.

**seek()** advances the current position to the specified component:

```
boolean seek (in long index);
```

Like `next()`, this operation returns `true` if the specified component is available; otherwise, it returns `false`.

**rewind()** resets the current position to the `DynAny` object's first component:

```
void rewind();
```

It is equivalent to calling `seek()` with a zero argument.

## Undefined current position

In some circumstances the current position can be undefined. For example, if a `DynSequence` object contains a zero length sequence, both the current component and the value of the `DynAny`'s current position are undefined.

The special value `-1` is used to represent an undefined current position.

When the current position is `-1`, an invocation of `current_component()` yields a `nil` object reference.

The current position becomes undefined (equal to `-1`) under the following circumstances:

- When the `DynAny` object has no components.  
For example, a `DynAny` containing a zero-length sequence or array would have no components.
- Immediately after `next()` returns `false`.
- If `seek()` is called with a negative integer argument, or with a positive integer argument greater than the largest valid index.

## Accessing Constructed DynAny Values

Each interface that derives from `DynAny`, such as `DynArray` and `DynStruct`, contains its own operations which enable access to values of the following `DynAny` types:

- [DynEnum](#)
- [DynStruct](#)
- [DynUnion](#)
- [DynSequence and DynArray](#)
- [DynFixed](#)
- [DynValue](#)
- [DynValueBox](#)

### DynEnum

The `DynEnum` interface enables access to enumerated `any` values:

```
module DynamicAny {
 //...
 interface DynEnum : DynAny {
 string get_as_string();
 void set_as_string(in string val) raises(InvalidValue);
 unsigned long get_as_ulong();
 void set_as_ulong(in unsigned long val)
 raises(InvalidValue);
 };
};
```

The `DynEnum` interface defines the following operations:

**get\_as\_string() and set\_as\_string()** let you access an enumerated value by its IDL string identifier or its ordinal value. For example, given this enumeration:

```
enum Exchange { NYSE, NASD, AMEX, CHGO, DAX, FTSE };
```

`set_as_string("NASD")` sets the `enum`'s value as `NASD`, while you can get its current string value by calling `get_as_string()`.

**get\_as\_ulong() and set\_as\_ulong()** provide access to an enumerated value by its ordinal value.

The following code uses a `DynEnum` to decompose an `any` value that contains an enumeration:

**Example 29:** *Using `DynEnum`*

```

void extract_any(const CORBA::Any* a){
 //...
 //Get a reference to a Dynam icAny: DynAnyFactory' object
 CORBA::Object_var obj
 =
 global_obj-> resolve_initial_references("DynAnyFactory");
 Dynam icAny: DynAnyFactory_var dyn_fact
 = Dynam icAny: DynAnyFactory:: narrow (obj);
 if (CORBA::is_nil(dyn_fact)) {
 //error: throw exception
 }

 Dynam icAny: DynAny_var dyn_a = dyn_fact-> create_dyn_any(*a);
 CORBA::TypeCode_var tcode = dyn_a-> type();

 switch (tcode-> kind()){
 case CORBA::tk_enum :
 {
 Dynam icAny: DynEnum_var dyn_e =
 Dynam icAny: DynEnum:: narrow (dyn_a);
 CORBA::String_var s = dyn_e-> get_as_string();
 cout << s << endl;
 dyn_e-> destroy();
 }

 //other cases follow
 }
}

```

## DynStruct

The `DynStruct` interface is used for `struct` and `exception` types. The interface is defined as follows:

```
module DynamicAny {
// ...
typedef string FielName;

struct NameValuePair {
 FielName fil;
 any value;
};
typedef sequence< NameValuePair> NameValuePairSeq;

struct NameDynAnyPair {
 FielName fil;
 DynAny value;
};
typedef sequence< NameDynAnyPair> NameDynAnyPairSeq;

interface DynStruct : DynAny {
 FielName current_member_name()
 raises(TypeMismatch, InvalidValue);
 CORBA::TCKind current_member_kind()
 raises(TypeMismatch, InvalidValue);
 NameValuePairSeq get_members();
 void set_members (in NameValuePairSeq value)
 raises(TypeMismatch, InvalidValue);
 NameDynAnyPairSeq get_members_as_dyn_any();
 void set_members_as_dyn_any(
 in NameDynAnyPairSeq value
) raises(TypeMismatch, InvalidValue);
};
};
```

The `DynStruct` interface defines the following operations:

- `set_members()` and `get_members()` are used to get and set member values in a `DynStruct`. Members are defined as a `NameValuePairSeq` sequence of name-value pairs, where each name-value pair consists of the member's name as a string, and an `any` that contains its value.

- `current_member_name()` returns the name of the member at the current position, as established by `DynAny` base interface operations. Because member names are optional in type codes, `current_member_name()` might return an empty string.
- `current_member_kind()` returns the `TCKind` value of the current `DynStruct` member's type code.
- `get_members_as_dyn_any()` and `set_members_as_dyn_any()` are functionally equivalent to `get_members()` and `set_members()`, respectively. They operate on sequences of name-`DynAny` pairs. Use these operations if you work extensively with `DynStruct` objects; doing so allows you to avoid converting a constructed `DynAny` into an `any` before using the operations to get or set struct members.

The following code iterates over members in a `DynStruct` and passes each member over to `eval_member()` for further decomposition:

**Example 30: Using a `DynStruct`**

```
DynAny*DynStruct_var dyn_s = ...;
CORBA::TypeCode_var tcode = dyn_s->type();
int counter = tcode->member_count();

for (int i = 0; i < counter; i++) {
 DynAny*DynAny_var member = dyn_s->current_component();
 eval_member(member);
 dyn_s->next();
}
```

## DynUnion

The `DynUnion` interface enables access to any values of union type:

```

module DynamicAny {
 //...
 typedef string FfiBName;

 interface DynUnion : DynAny {
 DynAny get_discriminator();
 void set_discriminator(in DynAny d) raises(TypeError);
 void set_to_default_member() raises(TypeError);
 void set_to_no_active_member() raises(TypeError);
 boolean has_no_active_member() raises(InvalidValue);
 CORBA::TCKind discriminator_kind();
 DynAny member() raises(InvalidValue);
 FfiBName member_name() raises(InvalidValue);
 CORBA::TCKind member_kind() raises(InvalidValue);
 };
};

```

The `DynUnion` interface defines the following operations:

**get\_discriminator()** returns the current discriminator value of the `DynUnion`.

**set\_discriminator()** sets the discriminator of the `DynUnion` to the specified value. If the type code of the parameter is not equivalent to the type code of the union's discriminator, the operation raises `TypeError`.

**set\_to\_default\_member()** sets the discriminator to a value that is consistent with the value of the default case of a union; it sets the current position to zero and causes `component_count` to return 2. Calling `set_to_default_member()` on a union that does not have an explicit default case raises `TypeError`.

**set\_to\_no\_active\_member()** sets the discriminator to a value that does not correspond to any of the union's case labels; it sets the current position to zero and causes `component_count` to return 1. Calling `set_to_no_active_member()` on a union that has an explicit default case or on a union that uses the entire range of discriminator values for explicit case labels raises `TypeError`.

**has\_no\_active\_member()** returns true if the union has no active member (that is, the union's value consists solely of its discriminator, because the discriminator has a value that is not listed as an explicit case label). Calling this operation on a union that has a default case returns false. Calling this operation on a union that uses the entire range of discriminator values for explicit case labels returns false.

**discriminator\_kind()** returns the `TCKind` value of the discriminator's `TypeCode`.

**member()** returns the currently active member. If the union has no active member, the operation raises `InvalidValue`. Note that the returned reference remains valid only as long as the currently active member does not change. Using the returned reference beyond the life time of the currently active member raises `OBJECT_NOT_EXIST`.

**member\_name()** returns the name of the currently active member. If the union's type code does not contain a member name for the currently active member, the operation returns an empty string. Calling `member_name()` on a union that does not have an active member raises `InvalidValue`.

**member\_kind()** returns the `TCKind` value of the currently active member's `TypeCode`. Calling this operation on a union that does not have a currently active member raises `InvalidValue`.

## DynSequence and DynArray

The interfaces for `DynSequence` and `DynArray` are virtually identical:

```
module DynamicAny {
 //...
 typedef sequence< any> AnySeq;
 typedef sequence< DynAny> DynAnySeq;

 interface DynArray : DynAny {
 AnySeq get_elements();
 void set_elements(in AnySeq value)
 raises (TypeMismatch, InvalidValue);
 DynAnySeq get_elements_as_dyn_any();
 void set_elements_as_dyn_any(in DynAnySeq value)
 raises (TypeMismatch, InvalidValue);
 };
};
```

```

interface DynSequence : DynAny {
 unsigned long get_length();
 void set_length(in unsigned long len)
 raises(InvalidValue);

 // remaining operations same as for DynArray
 // ...
};
};

```

You can get and set element values in a `DynSequence` or `DynArray` with operations `get_elements()` and `set_elements()`, respectively. Members are defined as an `AnySeq` sequence of `anyObjects`.

Operations `get_elements_as_dyn_any()` and `set_elements_as_dyn_any()` are functionally equivalent to `get_elements()` and `set_elements()`; unlike their counterparts, they return and accept sequences of `DynAny` elements.

`DynSequence` has two of its own operations:

**get\_length()** returns the number of elements in the sequence.

**set\_length()** sets the number of elements in the sequence.

If you increase the length of a sequence, new elements are appended to the sequence and default-initialized. If the sequence's current position is undefined (equal to -1), increasing the sequence length sets the current position to the first of the new elements. Otherwise, the current position is not affected.

If you decrease the length of a sequence, `set_length()` removes the elements from its end.

You can access elements with the iteration operations described in [“Iterating Over DynAny Components” on page 422](#). For example, the following code iterates over elements in a `DynArray`:

```

DynamicAny: DynArray_var dyn_array = ...;
CORBA::TypeCode_var tcode = dyn_array->type();
int counter = tcode->length();

for (int i = 0; i < counter; i++) {
 DynamicAny: DynAny_var elem = dyn_array->current_component();
 eval_member_member();
 dyn_array->next();
}

```

**DynFixed**

The `DynFixed` interface lets you manipulate an `any` that contains fixed-point values.

```
interface DynAny{
...
 interface DynFixed :DynAny{
 string get_value();
 void set_value(in string val)
 raises (TypeMismatch, InvalidValue);
 };
};
```

The `DynFixed` interface defines the following operations:

**get\_value()** returns the value of a `DynFixed` as a string.

**set\_value()** sets the value of a `DynFixed`. If `val` is an uninitialized string or contains a fixed point literal that exceeds the scale of `DynFixed`, the `InvalidValue` exception is raised. If `val` is not a valid fixed point literal, the `TypeMismatch` exception is raised.

**DynValue**

The `DynValue` interface lets you manipulate an `any` that contains a value type (excluding boxed value types):

```
module DynamicAny {
 //...
 typedef string FieldName;

 struct NameValuePair
 {
 FieldName id;
 any value;
 };
 typedef sequence< NameValuePair > NameValuePairSeq;

 struct NameDynAnyPair
 {
 FieldName id;
 DynAny value;
 };
 typedef sequence< NameDynAnyPair > NameDynAnyPairSeq;
}
```

```

interface DynValue : DynAny
{
 FieldName current_member_name()
 raises (TypeMismatch, InvalidValue);
 CORBA::TCKind current_member_kind()
 raises (TypeMismatch, InvalidValue);
 NameValuePairSeq get_members();
 void set_members(in NameValuePairSeq values)
 raises (TypeMismatch, InvalidValue);
 NameDynAnyPairSeq get_members_as_dyn_any();
 void set_members_as_dyn_any(in NameDynAnyPairSeq value)
 raises (TypeMismatch, InvalidValue);
};
};

```

The `DynValue` interface defines the following operations:

**current\_member\_name()** returns the name of the value type member indexed by the current position.

**current\_member\_kind()** returns the type code kind for the value type member indexed by the current position.

**get\_members()** returns the complete list of value type members in the form of a `NameValuePairSeq`.

**set\_members()** sets the contents of the value type members using a `NameValuePairSeq`.

**get\_members\_as\_dyn\_any()** is similar to `get_members()`, except that the result is returned in the form of a `NameDynAnyPairSeq`.

**set\_members\_as\_dyn\_any()** is similar to `set_members()`, except that the contents are set using a `NameDynAnyPairSeq`.

## DynValueBox

The `DynValueBox` interface lets you manipulate an `any` that contains a boxed value type:

```
module DynAny {
 //...
 interface DynValueBox : DynAny
 {
 any get_boxed_value();
 void set_boxed_value(in any val)
 raises (TypeMismatch);
 DynAny get_boxed_value_as_dyn_any();
 void set_boxed_value_as_dyn_any(in DynAny val)
 raises (TypeMismatch);
 };
};
```

The `DynValue` interface defines the following operations:

**get\_boxed\_value()** returns the boxed value as an `any`.

**set\_boxed\_value()** sets the boxed value as an `any`.

**get\_boxed\_value\_as\_dyn\_any()** returns the boxed value as a `DynAny`.

**set\_boxed\_value\_as\_dyn\_any()** sets the boxed value as a `DynAny`.



# Generating Interfaces at Runtime

*The dynamic invocation interface lets a client invoke on objects whose interfaces are known only at runtime; similarly, the dynamic skeleton interface lets a server process requests on objects whose interfaces are known only at runtime.*

An application's IDL usually describes interfaces to all the CORBA objects that it requires at runtime. Accordingly, the IDL compiler generates the stub and skeleton code that clients and servers need in order to issue and process requests. The client can issue requests only on those objects whose interfaces are known when the client program is compiled; similarly, the server can process requests only on those objects that are known when the server program is compiled.

Some applications cannot know ahead of time which objects might be required at runtime. In this case, Application Server Platform provides two interfaces that let you construct stub and skeleton code at runtime, so clients and servers can issue and process requests on those objects:

- The *dynamic invocation interface* (DII) builds stub code for a client so it can call operations on IDL interfaces that were unknown at compile time.

- The *dynamic skeleton interface* (DSI) builds skeleton code for a server, so it can receive operation or attribute invocations on an object whose IDL interface is unknown at compile time.

**In this chapter**

---

This chapter discusses the following topics:

|                               |                          |
|-------------------------------|--------------------------|
| <a href="#">Using the DII</a> | <a href="#">page 437</a> |
| <a href="#">Using the DSI</a> | <a href="#">page 449</a> |

---

# Using the DII

---

## Overview

Some application programs and tools must be able to invoke on objects whose interfaces cannot be determined ahead of time—for example, browsers, gateways, management support tools, and distributed debuggers. With DII, invocations can be constructed at runtime by specifying the target object reference, the operation or attribute name, and the parameters to pass. A server that receives a dynamically constructed invocation request does not differentiate between it and static requests.

---

## Clients that use DII

Two types of client programs commonly use the DII:

- A client interacts with the interface repository to determine a target object's interface, including the name and parameters of one or all of its operations, then uses this information to construct DII requests.
  - A client, such as a gateway, receives the details of a request. In the case of a gateway, the request details might arrive as part of a network package. The gateway can then translate this into a DII call without checking the details with the interface repository. If a mismatch occurs, an exception is raised to the gateway, which in turn can report an error to the caller.
- 

## Steps

To invoke on an object with DII, follow these steps:

1. Construct a `Request` object with the operation's signature.
2. Invoke the request.
3. Retrieve results of the operation.

**Example IDL**

The bank example is modified here to show how to use the DII. The `Bank::newAccount()` operation now takes an `inout` parameter that sets a new account's initial balance:

```
//IDL
interface Account {
 readonly attribute float balance;

 void makeDeposit(in float f);
 void makeWithdrawal(in float f);
};

interface Bank {
 exception Reject {string reason;};

 //Create an account
 Account newAccount(
 in string owner,
 inout float initialBalance,
 out long status)
 raises (Reject);

 //Delete an account
 void deleteAccount(in Account a);
};
```

The following section shows how to construct a `Request` object that can deliver client requests for `newAccount()` operations such as this one:

```
bankVar-> newAccount(ownerName, initialBalance, status);
```

**In this section**

This section discusses the following topics:

|                                                        |                          |
|--------------------------------------------------------|--------------------------|
| <a href="#">Constructing a Request Object</a>          | <a href="#">page 439</a> |
| <a href="#">Invoking a Request</a>                     | <a href="#">page 446</a> |
| <a href="#">Retrieving Request Results</a>             | <a href="#">page 447</a> |
| <a href="#">Invoking Deferred Synchronous Requests</a> | <a href="#">page 448</a> |

---

## Constructing a Request Object

---

### Overview

To construct a `Request` object and set its data, you must first obtain a reference to the target object. You then create a request object by invoking one of these methods on the object reference:

- `_request()` returns an empty request object whose signature—return type and parameters—must be set.
- `_create_request()` returns with a request object that can contain all the data required to invoke the desired request.

### In this section

This section discusses the following topics:

|                                   |                          |
|-----------------------------------|--------------------------|
| <a href="#">_request()</a>        | <a href="#">page 440</a> |
| <a href="#">_create_request()</a> | <a href="#">page 443</a> |

---

## **\_request()**

### **Overview**

You can use `_request()` to create a `Request` object in these steps:

1. [Create a request object](#) and set the name of its operation.
  2. [Set the operation's return type](#).
  3. [Set operation parameters](#) and supply the corresponding arguments.
  4. [Set exception type codes](#).
  5. [Set the operation's context clause](#), if necessary.
- 

### **Create a request object**

Call `_request()` on the target object and specify the name of the operation to invoke:

```
//Get object reference
CORBA::Object_var target = ... ;

//Create Request object for operation newAccount()
CORBA::Request_var newAcctRequest =
 target->_request("newAccount");
```

---

### **Set the operation's return type**

After you create a `Request` object, set the `TypeCode` of the operation's return value by calling `set_return_type()` on the `Request` object.

`set_return_type()` takes a single argument, the `TypeCode` constant of the return type. For example, given the `Request` object `newAcctRequest`, set the return type of its `newAccount()` operation to `Account` as follows:

```
newAcctRequest-> set_return_type(_tc_Account);
```

For information about supported `TypeCode` constants, refer to [“Type Code Constants” on page 390](#).

For information about supported `TypeCodes`, see [Chapter 14 on page 379](#).

---

### **Set operation parameters**

A request object uses an `NVList` to store the data for an operation's parameters. To set the parameters in the `NVList` you need to know the operations parameters and insert the proper values in the exact order the

parameters are specified in the operation's IDL. The `_request()` operation creates an empty `NVList` into which you insert the values needed by the operation.

To fill in the `NVList` you can use the following operations on the `Request` object:

```
add_in_arg()
add_inout_arg()
add_out_arg()
```

These operations return a reference to an `Any`. For more information on inserting values into an `Any` see ["Using the Any Data Type" on page 393](#).

[Example 31 on page 441](#) sets the parameter list for the `newAccount` operation. The values for the `out` parameters of an operation do not need to

### Example 31: Setting the parameter list

```
//C++
newAcctRequest->add_in_arg() <<= "Nom an Fellows";
CORBA::Float initBal= 1000.00;
newAcctRequest->add_inout_arg() <<= initBal;
CORBA::Long status;
newAcctRequest->add_out_arg() <<= status;
```

be set because they will be changed when the operation returns. However, the values for all `in` and `inout` parameters must be specified.

You can also fill the `NVList` object using `NVList::add_value()`. This operation has the following signature:

```
NamedValue NVList::add_value(String item_name, Any val, int
 flags);
```

The `flags` parameter is set to one of the following values:

- `CORBA::ARG_IN`
- `CORBA::ARG_INOUT`
- `CORBA::ARG_OUT`

## Set exception type codes

You must set the type codes for any exceptions defined for the `Request` object's operation. To do this use the `add()` operation defined for the `Request` object's `exceptions()` list.

`add()` takes the exceptions type codes as its only argument. To add the `Reject` exception to `newAcctRequest` use the following operation:

```
newAcctRequest-> exceptions()-> add(Bank::_to_Reject);
```

If the type code for the exception was not available in the stub code, you would need to dynamically generate the exceptions type code.

---

**Set the operation's context clause**

If the IDL operation has a `context` clause, you can add a `Context` object to its `Request` object with `CORBA::Request::ctx()`.

---

## `_create_request()`

---

### Overview

You can also create a `Request` object by calling `_create_request()` on an object reference and passing the request details as arguments. The advantage of using `_create_request()` is that you can create a `Request` object that contains all of the information needed to invoke a request. `_create_request()` has the following signature:

```
void _create_request(Context_ptr ctx,
 const char* operation,
 NVList_ptr arg_list,
 NamedValue_ptr result,
 ExceptionList_ptr exceptions,
 ContextList_ptr contexts,
 Request_out request,
 Flags req_flags);
```

At a minimum, you must provide two arguments when using `_create_request()`:

- The name of the operation
- A pointer to a `NamedValue` that holds the operation's return value

You can also supply a populated parameter list and a populated exception list to `_create_request()`. If you supply null for either list, `_create_request()` creates an empty list for the returned `Request` object. In this case you must populate the list as described above in [“\\_request\(\)” on page 440](#).

---

### Creating the parameter list

There are two operations provided by `CORBA::ORB` to create the `NVList` passed to `_create_object()` to specify the `Request` object's parameter list:

- [create\\_list\(\)](#)
- [create\\_operation\\_list\(\)](#)

#### `create_list()`

`create_list()` has the following signature:

```
void create_list(Long count, NVList_ptr list);
```

The operation allocates the space for an `NVList` of the specified number of elements and returns a pointer to the empty `NVList`. You then add the required parameters using the following operation on the `NVList`:

```
add()
add_item ()
add_item_consum e()
add_value()
add_value_consum e()
```

### create\_operation\_list()

`create_operation_list()` extends the functionality of `create_list()` by creating a prefilled parameter list based on information stored in the interface repository. It has the following signature:

```
void create_operation_list(OperationDef_ptr operation,
 NVList_out list);
```

Using the `OperationDef` object passed as a parameter, `create_operation_list()` retrieves the parameter list for the specified operation from the interface repository. When `create_operation_list()` returns, the `NVList` contains one `NamedValue` object for each operation parameter. Each `NamedValue` object contains the parameter's passing mode, name, and initial value of type `Any`.

Once you have the prefilled parameter list, you can modify the parameters by iterating over the `NVList` elements with `NVList::item()`. Use the insertion operator `<<=` to set each `NamedValue`'s `value` member.

### Example

The code in [Example 32](#) constructs a parameter list using `create_operation_list()`. It then uses the parameter list to construct a `Request` object for invoking operation `newAccount()`:

**Example 32:** *Create a Request object using `_create_request()`*

```

//get an object reference
CORBA::Object_var target = ... ;

CORBA::Request_ptr newAcctRequest;
CORBA::NamedValue_ptr result;

//Get OperationDef object from IFR
//reference to the IFR , ifr, obtained previously
CORBA::Contained_ptr cont = ifr->lookup("Bank::newAccount");
CORBA::OperationDef_ptr opDef =
 CORBA::OperationDef::_narrow(cont.in());

//Initialize the parameter list
CORBA::NVList_out param List;
CORBA::ORB::create_operation_list(opDef, param List);
param List->item(0)->value <<= "Nom an Fellows";
CORBA::Float initBal = 1000.00;
param List->item(1)->value <<= initBal;
CORBA::Long status;
param List->item(2)->value <<= status;

//Construct the Request object
target->_create_request(CORBA::Context::_nil(), "newAccount",
 param List, result, newAcctRequest, 0);

```

---

## Invoking a Request

After you set a `Request` object's data, you can use one of several methods to invoke the request on the target object. The following methods are invoked on a `Request` object:

**`invoke()`** blocks the client until the operation returns with a reply. Exceptions are handled the same as static function invocations.

**`send_deferred()`** sends the request to the target object and allows the client to continue processing while it awaits a reply. The client must poll for the request's reply (see [“Invoking Deferred Synchronous Requests” on page 448](#)).

**`send_oneway()`** invokes one-way operations. Because no reply is expected, the client resumes processing immediately after the invocation.

The following methods are invoked on the ORB, and take a sequence of requests:

**`send_multiple_requests_deferred()`** calls multiple deferred synchronous operations.

**`send_multiple_requests_oneway()`** calls multiple oneway operations simultaneously.

For example:

### Example 33: *Invoking on a request*

```
try {
 if (request-> invoke())
 //Call to invoke() succeeded
 else
 //Call to invoke() failed.
}
catch (CORBA::System Exception& se) {
 cout << "Unexpected exception" << &se << endl;
}
```

---

## Retrieving Request Results

When a request returns, Application Server Platform updates `out` and `inout` parameters in the `Request` object's `NVList`. To get an operation's output values:

1. Call `arguments()` on the `Request` object to get a reference to its `NVList`.
2. Iterate over the `NamedValue` items in the `Request` object's `NVList` by successively calling `item()` on the `NVList`. Each call to this methods returns a `NamedValue` reference.
3. Call `value()` on the `NamedValue` to get a pointer to the `Any` value for each parameter.
4. Extract the parameter values from the `Any`.

To get an operation's return value, call `return_value()` on the request object. This operation returns the request's return value as an `any`.

For example, the following code gets an object reference to the new account returned by the `newAccount()` operation:

**Example 34:** *Obtaining the return value from a request object*

```
CORBA:Object_varnewAccount;
request->return_value()>> = newAccount;
```

---

## Invoking Deferred Synchronous Requests

You can use the DII to make *deferred synchronous* operation calls. A client can call an operation, continue processing in parallel with the operation, then retrieve the operation results when required.

You can invoke a request as a deferred synchronous operation as follows:

1. Construct a `Request` object and call `send_deferred()` on it.
2. Continue processing in parallel with the operation.
3. Check whether the operation has returned by calling `poll_response()` on the `Request` object. This method returns a non-zero value if a response has been received.
4. To get the result of the operation, call `get_response()` on the `Request` object.

You can also invoke methods asynchronously. For more information, see [Chapter 12](#).

---

# Using the DSI

---

## Overview

A server uses the dynamic skeleton interface (DSI) to receive operations or attribute invocations on an object whose IDL interface is unknown to it at compile time. With DSI, a server can build the skeleton code that it needs to accept these invocations.

The server defines a function that determines the identity of the requested object; the name of the operation and the types and values of each argument are provided by the user. The function carries out the task that is being requested by the client, and constructs and returns the result. Clients are unaware that a server is implemented with the DSI.

---

## In this section

This section discusses the following topics:

|                                                 |                          |
|-------------------------------------------------|--------------------------|
| <a href="#">DSI Applications</a>                | <a href="#">page 450</a> |
| <a href="#">Programming a Server to Use DSI</a> | <a href="#">page 451</a> |

---

## DSI Applications

---

### Overview

The DSI is designed to help write gateways that accept operation or attribute invocations on any specified set of interfaces and pass them to another system. A gateway can be written to interface between CORBA and some non-CORBA system. This gateway is the only part of the CORBA system that must know the non-CORBA system's protocol; the rest of the CORBA system simply issues IDL calls as usual.

---

### Invoking on a gateway

The IIOP protocol lets an object invoke on objects in another ORB. If a non-CORBA system does not support IIOP, you can use DSI to provide a gateway between the CORBA and non-CORBA systems. To the CORBA system, this gateway appears as a CORBA-compliant server that contains CORBA objects. In reality, the server uses DSI to trap incoming invocations and translate them into calls that the non-CORBA system can understand.

---

### Bidirectional gateways

You can use DSI and DII together to construct a bidirectional gateway. This gateway receives messages from the non-CORBA system and uses the DII to make CORBA client calls. It uses DSI to receive requests from clients on a CORBA system and translate these into messages in the non-CORBA system.

DSI has other uses. For example, a server might contain many non-CORBA objects that it wants to make available to its clients. In an application that uses DSI, clients invoke on only one CORBA object for each non-CORBA object. The server indicates that it uses DSI to accept invocations on the IDL interface. When it receives an invocation, it identifies the target object, the operation or attribute to call, and its parameters. It then makes the call on the non-CORBA object. When it receives the result, it returns it to the client.

---

## Programming a Server to Use DSI

---

### Overview

The DSI is implemented by servants that instantiate dynamic skeleton classes. All dynamic skeleton classes are derived from

`PortableServer::DynamicImplementation`:

```

namespace PortableServer{
class DynamicImplementation :public virtual ServantBase{
public:
 Object_ptr_this();
 virtual void invoke(ServerRequest_ptr request) = 0;
 virtual RepositoryId_ptr any interface(
 const Object_id& oid, POA_ptr poa) = 0;
};
}

```

A server program uses DSI as follows:

1. Instantiates one or more DSI servants and obtains object references to them, which it makes available to clients.
2. Associates each DSI servant with a POA—for example, through a servant manager, or by registering it as the default servant.

### Dynamic implementation routine

When a client invokes on a DSI-generated object reference, the POA delivers the client request as an argument to the DSI servant's `invoke()` method—also known as the *dynamic implementation routine* (DIR). `invoke()` takes a single argument, a `CORBA::ServerRequest` pseudo-object, which encapsulates all data that pertains to the client request—the operation's signature and arguments. `CORBA::ServerRequest` maps to the following C++ class:

```

class ServerRequest{
public:
 const char* operation() const;
 void arguments(NVList_ptr& parameters);
 Context_ptr ctx();
 void set_result(const Any& value);
 void set_exception(const Any& value);
};

```

## invoke() processing

---

`invoke()` processing varies across different implementations, but it always includes the following steps:

1. Obtains the operation's name by calling `operation()` on the `ServerRequest` object.
2. Builds an `NVList` that contains definitions for the operation's parameters—often, from an interface definition obtained from the interface repository. Then, `invoke()` populates the `NVList` with the operation's input arguments by calling `arguments()` on the `ServerRequest` object.
3. Reconstructs the client invocation and processes it.
4. If required, sets the operation's output in one of two ways:
  - ◆ If the operation's signature defines output parameters, `invoke()` sets the `NVList` as needed. If the operation's signature defines a return value, `invoke()` calls `set_result()` on the `ServerRequest` object.
  - ◆ If the operation's signature defines an exception, `invoke()` calls `set_exception()` on the `ServerRequest` object.

**Note:** `invoke()` can either set the operation's output by initializing its output parameters and setting its return value, or by setting an exception; however, it cannot do both.

# Using the Interface Repository

*An Orbix application uses the interface repository for persistent storage of IDL interfaces and types. The runtime ORB and Orbix applications query this repository at runtime to obtain IDL definitions.*

The interface repository maintains full information about the IDL definitions that have been passed to it. The interface repository provides a set of IDL interfaces to browse and list its contents, and to determine the type information for a given object. For example, given an object reference, you can use the interface repository to obtain all aspects of the object's interface: its enclosing module, interface name, attribute and operation definitions, and so on.

---

## Benefits

These capabilities are important for a number of tools:

- Browsers that allow designers and code writers to determine what types have been defined in the system, and to list the details of chosen types.
- CASE tools that aid software design, writing, and debugging.
- Application level code that uses the dynamic invocation interface (DII) to invoke on objects whose types were not known to it at compile time. This code might need to determine the details of the object being invoked in order to construct the request using the DII.

- A gateway that requires runtime information about the type of an object being invoked.

In order to populate the interface repository with IDL definitions, run the IDL compiler with the `-R` option. For example, the following command populates the interface repository with the IDL definitions in `bank.idl`:

```
idl -R bank.idl
```

### In this chapter

This chapter contains the following sections

|                                                                   |                          |
|-------------------------------------------------------------------|--------------------------|
| <a href="#">Interface Repository Data</a>                         | <a href="#">page 455</a> |
| <a href="#">Containment in the Interface Repository</a>           | <a href="#">page 464</a> |
| <a href="#">Repository Object Descriptions</a>                    | <a href="#">page 471</a> |
| <a href="#">Retrieving Repository Information</a>                 | <a href="#">page 474</a> |
| <a href="#">Sample Usage</a>                                      | <a href="#">page 478</a> |
| <a href="#">Repository IDs and Formats</a>                        | <a href="#">page 480</a> |
| <a href="#">Controlling Repository IDs with Pragma Directives</a> | <a href="#">page 482</a> |

# Interface Repository Data

Interface repository data can be viewed as a set of CORBA objects, where the repository stores one object for each IDL type definition. All interface repository objects are derived from the abstract base interface `RObject`, which is defined as follows:

```
//In module CORBA
enum DefinitionKind
{
 dk_none, dk_all,
 dk_Attribute, dk_Constant, dk_Exception, dk_Interface,
 dk_Module, dk_Operation, dk_Typedef,
 dk_AlIAS, dk_Struct, dk_Union, dk_Enum ,
 dk_Primitive, dk_String, dk_Sequence, dk_Array,
 dk_Repository, dk_W string, dk_Fixed,
 dk_Value, dk_ValueBox, dk_ValueM ember, dk_Native
};

...
interface RObject
{
 //read interface
 readonly attribute DefinitionKind def_kind;

 //write interface
 void
 destroy();
};
```

Attribute `def_kind` identifies a repository object's type. For example, the `def_kind` attribute of an `interfaceDef` object is `dk_interface`. The enumerate constants `dk_none` and `dk_all` are used to search for objects in a repository. All other enumerate constants identify one of the repository object types in [Table 20](#), and correspond to an IDL type or group of types. `destroy()` deletes an interface repository object and any objects contained within it. You cannot call `destroy()` on the interface repository object itself or any `PrimitiveDef` object.

---

## Abstract Base Interfaces

Besides `RObject`, the interface repository defines four other abstract base interfaces, all of which inherit directly or indirectly from `RObject`:

**Container:** The interface for container objects. This interface is inherited by all interface objects that can contain other objects, such as `Repository`, `ModuleDef` and `InterfaceDef`. These interfaces inherit from `Container`. See [“Container Interface” on page 469](#).

**Contained:** The interface for contained objects. This interface is inherited by all objects that can be contained by other objects—for example, attribute definition (`AttributeDef`) objects within operation definition (`OperationDef`) objects. See [“Contained Interface” on page 467](#).

**IDLType:** All interface repository interfaces that hold the definition of a type inherit directly or indirectly from this interface. See [“IDL-type objects” on page 460](#).

**TypedefDef:** The base interface for the following interface repository types that have names: `StructDef`, `UnionDef`, `EnumDef`, and `AliasDef`, which represents IDL `typedef` definitions.

## Repository Object Types

Objects in the interface repository support one of the IDL types in [Table 20](#):

**Table 20:** *Interface Repository Object Types*

| Object type    | Description                                                                                                                                                                                                                                              |
|----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Repository     | The repository itself, in which all other objects are nested. A repository definition can contain definitions of other types such as module and interface. <a href="#">Table 21</a> lists all possible container components.                             |
| ModuleDef      | A module definition is logical grouping of interfaces and value types. The definition has a name and can contain definitions of all types except <code>Repository</code> . <a href="#">Table 21 on page 465</a> lists all possible container components. |
| InterfaceDef   | An interface definition has a name, a possible inheritance declaration, and can contain definitions of other types such as attribute, operation, and exception. <a href="#">Table 21</a> lists all possible container components.                        |
| ValueDef       | A value type definition has a name, a possible inheritance declaration, and can contain definitions of other types such as attribute, operation, and exception. <a href="#">Table 21</a> lists all possible container components.                        |
| ValueBoxDef    | A value box definition defines a value box type.                                                                                                                                                                                                         |
| ValueMemberDef | A value member definition defines a member of a value.                                                                                                                                                                                                   |
| AttributeDef   | An attribute definition has a name, a type, and a mode to indicate whether it is readonly.                                                                                                                                                               |

**Table 20:** *Interface Repository Object Types*


| Object type  | Description                                                                                                                                                                                                                                                                          |
|--------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OperationDef | An operation definition has a name, return value, set of parameters and, optionally, <code>raises</code> and <code>context</code> clauses.                                                                                                                                           |
| ConstantDef  | A constant definition has a name, type, and value.                                                                                                                                                                                                                                   |
| ExceptionDef | An exception definition has a name and a set of member definitions.                                                                                                                                                                                                                  |
| StructDef    | A struct definition has a name, and holds the definition of each of its members.                                                                                                                                                                                                     |
| UnionDef     | A union definition has a name, and holds a discriminator type and the definition of each of its members.                                                                                                                                                                             |
| EnumDef      | An enum definition has a name and a list of member identifiers.                                                                                                                                                                                                                      |
| AliasDef     | An aliased definition defines a typedef definition, which has a name and a type that it maps to.                                                                                                                                                                                     |
| PrimitiveDef | A primitive definition defines primitive IDL types such as <code>short</code> and <code>long</code> , which are predefined in the interface repository.                                                                                                                              |
| StringDef    | A string definition records its bound. Objects of this type are unnamed. If they are defined with a <code>typedef</code> statement, they are associated with an <code>AliasDef</code> object. Objects of this type correspond to bounded strings.                                    |
| SequenceDef  | Each sequence type definition records its element type and its bound, where a value of zero indicates an unbounded sequence type. Objects of this type are unnamed. If they are defined with a <code>typedef</code> statement, they have an associated <code>AliasDef</code> object. |

**Table 20:** *Interface Repository Object Types*

| Object type           | Description                                                                                                                                                                                                                                                                                                                                                            |
|-----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>ArrayDef</code> | Each array definition records its length and its element type. Objects of this type are unnamed. If they are defined with a <code>typedef</code> statement, they are associated with an <code>AliasDef</code> object. Each <code>ArrayDef</code> object represents one dimension; multiple <code>ArrayDef</code> objects can represent a multi-dimensional array type. |

Given an object of any interface repository type, you can obtain its full interface definition. For example, `InterfaceDef` defines operations or attributes to determine an interface's name, its inheritance hierarchy, and the description of each operation and each attribute.

Figure 21 shows the hierarchy for all interface repository objects.



**Figure 21:** Hierarchy of interface repository objects

## IDL-type objects

Most repository objects represent IDL types—for example, `InterfaceDef` objects represent IDL interfaces, `StructDef` objects represent struct definitions, and so on. These objects all inherit, directly or indirectly, from the abstract base interface `DLType`:

```
// In module CORBA
interface DLType : RObject {
 readonly attribute TypeCode type;
};
```

This base interface defines a single attribute that contains the `TypeCode` of the defined type.

IDL-type objects are themselves subdivided into two groups:

- [Named types](#)
- [Unnamed types](#)

### Named types

The interface repository can contain these named IDL types:

|              |             |
|--------------|-------------|
| AliasDef     | StructDef   |
| EnumDef      | UnionDef    |
| InterfaceDef | ValueBoxDef |
| NativeDef    | ValueDef    |

For example, the following IDL defines `enum` type `UD` and `typedef` type `AccountName`, which the interface repository represents as named object types `EnumDef` and `AliasDef` objects, respectively:

```
//IDL
enum UD {UP,DOWN};
typedef string AccountName;
```

The following named object types inherit from the abstract base interface `TypeDefDef`:

|           |             |
|-----------|-------------|
| AliasDef  | StructDef   |
| EnumDef   | ValueBoxDef |
| NativeDef | UnionDef    |

`TypeDefDef` is defined as follows:

```
//IDL
//Module CORBA
interface TypeDefDef : Contained, DLType {
};
```

`TypeDefDef` serves the sole purpose of enabling its derived object types to inherit `Contained` and `DLType` attributes and operations:

- Attribute `Contained:name` enables access to the object's name. For example, the IDL `enum` definition `UD` shown earlier is represented by the repository object `EnumDef`, whose inherited `name` attribute is set to `UD`.
- Operation `Contained:describe()` gets a detailed description of the object. For more information about this operation, see [“Repository Object Descriptions” on page 471](#).

Interfaces `InterfaceDef` and `ValueDef` are also named object types that inherit from three base interfaces: `Contained`, `Container`, and `DLType`. Because IDL object and value references can be used like other types, `InterfaceDef` and `ValueDef` inherit from the base interface `DLType`. For example, given the IDL definition of `interface Account`, the interface repository creates an `InterfaceDef` object whose `name` attribute is set to `Account`. This name can be reused as a type.

### Unnamed types

The interface repository can contain the following unnamed object types:

|                           |                          |
|---------------------------|--------------------------|
| <code>AnyDef</code>       | <code>SequenceDef</code> |
| <code>FixedDef</code>     | <code>StringDef</code>   |
| <code>PrimitiveDef</code> | <code>WStringDef</code>  |

### Getting an object's idl type

Repository objects that inherit the `DLType` interface have their own operations for identifying their type; you can also get an object's type through the `TypeCode` interface. Repository objects such as `AttributeDef` that do not inherit from `DLType` have their own `TypeCode` or `DLType` attributes that enable access to their types.

For example the following IDL interface definition defines the return type of operation `getLongAddress` as a string sequence:

```
//IDL
interface Mailer {
 string getLongAddress();
};
```

`getLongAddress()` maps to an object of type `OperationDef` in the repository. You can query this object for its return type's definition—`string`—in two ways:

Method 1:

1. Get the object's `OperationDef:result_def` attribute, which is an object reference of type `DLType`.
2. Get the `DLType`'s `def_kind` attribute, which is inherited from `RObject`. In this example, `def_kind` resolves to `dk_primitive`.
3. Narrow the `DLType` to `PrimitiveDef`.

4. Get the `PrimitiveDef`'s `kind` attribute, which is a `PrimitiveKind` of `pk_string`.

Method 2:

1. Get the object's `OperationDef`'s `result` attribute, which is a `TypeCode`.
2. Obtain the `TypeCode`'s `TCKind` through its `kind()` operation. In this example, the `TCKind` is `tk_string`.

---

## Containment in the Interface Repository

Most IDL definitions contain or are contained by other definitions, and the interface repository defines its objects to reflect these relationships. For example, a module typically contains interface definitions, while interfaces themselves usually contain attributes, operations, and other definition types.

### Containment interfaces

The interface repository abstracts the properties of containment into two abstract base interfaces:

- `Contained`
- `Container`

These interfaces provide operations and attributes that let you traverse the hierarchy of relationships in an interface repository in order to list its contents, or ascertain a given object's container. Most repository objects are derived from one or both of `Container` or `Contained`; the exceptions are instances of `PrimitiveDef`, `StringDef`, `SequenceDef`, and `ArrayDef`.

### Example

In the following IDL, module `Finance` is defined with two interface definitions, `Bank` and `Account`. In turn, interface `Account` contains attribute and operation definitions:

```
//IDL
module Finance {
 interface Account {
 readonly attribute float balance;
 void makeDeposit(in float amount);
 void makeWithdrawal(in float amount);
 };
 interface Bank {
 Account newAccount();
 };
};
```

The corresponding interface repository objects for these definitions are each described as `Container` or `Contained` objects. Thus, the interface repository represents module `Finance` as a `ModuleDef` container for `InterfaceDef`

objects `Account` and `Bank`; these, in turn, serve as containers for their respective attributes and operations. `ModuleDef` object `Finance` is also viewed as a contained object within the container object `RepositoryDef`.

### Containment properties of interface repository objects

Table 21 shows the relationship between `Container` and `Contained` objects in the interface repository.

**Table 21:** *Container and Contained Objects in the Interface Repository*

| Container object type     | Contained Objects                                                                                                                                                         |
|---------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>Repository</code>   | <code>ConstantDef</code><br><code>TypeDefDef</code><br><code>ExceptionDef</code><br><code>InterfaceDef*</code><br><code>ModuleDef*</code><br><code>ValueDef*</code>       |
| <code>ModuleDef</code>    | <code>ConstantDef</code><br><code>TypeDefDef</code><br><code>ExceptionDef</code><br><code>ModuleDef*</code><br><code>InterfaceDef*</code><br><code>ValueDef*</code>       |
| <code>InterfaceDef</code> | <code>ConstantDef</code><br><code>TypeDefDef</code><br><code>ExceptionDef</code><br><code>AttributeDef</code><br><code>OperationDef</code>                                |
| <code>ValueDef</code>     | <code>ConstantDef</code><br><code>TypeDefDef</code><br><code>ExceptionDef</code><br><code>AttributeDef</code><br><code>OperationDef</code><br><code>ValueMemberDef</code> |

\* Also a Container object

Only a `Repository` is a pure `Container`. An interface repository server has only one `Repository` object, and it contains all other definitions.

Objects of type `ModuleDef`, `InterfaceDef`, and `ValueDef` are always contained within a `Repository`, while `InterfaceDef` and `ValueDef` can also be within a `ModuleDef`, these objects usually contain other objects, so they inherit from both `Container` and `Contained`.

All other repository object types inherit only from `Contained`.

---

## Contained Interface

The `Contained` interface is defined as follows:

```
//IDL
typedef string VersionSpec;

interface Contained : RObject
{
 //read/write interface
 attribute RepositoryId id;
 attribute Identifier name;
 attribute VersionSpec version;

 //read interface
 readonly attribute Container defined_in;
 readonly attribute ScopedName absolute_name;
 readonly attribute Repository containing_repository;

 struct Description
 {
 DefinitionKind kind;
 any value;
 };

 Description
 describe();

 //write interface
 void
 move(
 in Container new_container,
 in Identifier new_name,
 in VersionSpec new_version
);
};
```

### Name attribute

Attribute `Contained::name` is of type `Identifier`, a typedef for a string, and contains the IDL object's name. For example, module `Finance` is represented in the repository by a `ModuleDef` object. Its inherited `ModuleDef::name` attribute resolves to the string `Finance`. Similarly the `makeWithdrawal` operation is represented by an `OperationDef` object whose `OperationDef::name` attribute resolves to `makeWithdrawal`.

### defined\_in attribute

---

`Contained` also defines the attribute `defined_in`, which stores a reference to an object's `Container`. Because IDL definitions within a repository must be unique, `defined_in` stores a unique `Container` reference. However, given inheritance among interfaces, an object can be contained in multiple interfaces. For example, the following IDL defines interface `CurrentAccount` to inherit from interface `Account`:

```
//IDL
//in module Finance
interface CurrentAccount : Account {
 readonly attribute overdraftLimit;
};
```

### balance attribute

---

Given this definition, attribute `balance` is contained in interfaces `Account` and `CurrentAccount`; however, attribute `balance` is defined only in the base interface `Account`. Thus, if you invoke `AttributeDef::defined_in()` on either `Account::balance` or `CurrentAccount::balance`, it always returns `Account` as the `Container` object.

A `Contained` object can include more than containment information. For example, an `OperationDef` object has a list of parameters associated with it and details of the return type. The operation `Contained::describe()` provides access to these details by returning a generic `Description` structure (see [“Repository Object Descriptions” on page 471](#)).

## Container Interface

Interface `Container` is defined as follows:

```
//DL
enum DefinitionKind
{
 dk_none, dk_all,
 dk_Attribute, dk_Constant, dk_Exception, dk_Interface,
 dk_Module, dk_Operation, dk_Typedef,
 dk_Alias, dk_Struct, dk_Union, dk_Enum,
 dk_Primitive, dk_String, dk_Sequence, dk_Array,
 dk_Repository, dk_Wstring, dk_Fixed,
 dk_Value, dk_ValueBox, dk_ValueMember, dk_Native
};
...

typedef sequence< Contained> ContainedSeq;

interface Container : RObject
{
 //read interface
 ...

 Contained
 lookup(
 in ScopedName search_name
);

 ContainedSeq
 contents(
 in DefinitionKind limit_type,
 in boolean exclude_inherited
);

 ContainedSeq
 lookup_name (
 in Identifier search_name,
 in long levels_to_search,
 in DefinitionKind limit_type,
 in boolean exclude_inherited
);
};
```

```

struct Description
{
 Contained contained_object;
 DefinitionKind kind;
 anyvalue;
};
typedef sequence< Description> DescriptionSeq;

DescriptionSeq
describe_contents(
 in DefinitionKind in_type,
 in boolean exclude_inherited,
 in longmax returned_objs
);

//write interface

... //operations to create container objects
};

```

## lookup operations

The container interface provides four lookup operations that let you browse a given container for its contents: `lookup()`, `lookup_name()`, `contents()`, and `describe_contents()`. For more information about these operations, see [“Browsing and listing repository contents” on page 474](#).

---

# Repository Object Descriptions

Each repository object, in addition to identifying itself as a `Contained` or `Container` object, also maintains the details of its IDL definition. For each contained object type, the repository defines a structure that stores these details. Thus, a `ModuleDef` object stores the details of its description in a `ModuleDescription` structure, an `InterfaceDef` object stores its description in an `InterfaceDescription` structure, and so on.

## How to obtain object descriptions

You can generally get an object's description in two ways:

- The interface for each contained object type often defines attributes that get specific aspects of an object's description. For example, attribute `OperationDef:result` gets an operation's return type.
- You can obtain all the information stored for a given object through the inherited operation `Contained:describe()`, which returns the general purpose structure `Contained:Description`. This structure's `value` member is of type `any`, whose value stores the object type's structure.

For example, interface `OperationDef` has the following definition:

```
interface OperationDef : Contained
{
 readonly attribute TypeCode result;
 attribute IDLType result_def;
 attribute PairDescriptionSeq param_s;
 attribute OperationMode mode;
 attribute ContextIdSeq contexts;
 attribute ExceptionDefSeq exceptions;
};
```

## Accessing attributes

Interface `OperationDef` defines a number of attributes that allow direct access to specific aspects of an operation, such as its parameters (`param_s`) and return type (`result_def`).

## Invoking describe()

In a distributed environment, it is often desirable to obtain all information about an operation in a single step by invoking `describe()` on the `OperationDef` object. This operation returns a `Contained::Description` whose two members, `kind` and `value`, are set as follows:

**kind** is set to `dk_Operation`.

**value** is an `any` whose `TypeCode` is set to `_to_OperationDescription`. The `any`'s value is an `OperationDescription` structure, which contains all the required information about an operation:

```
//DL
struct OperationDescription
{
 Identifier name;
 RepositoryId id;
 RepositoryId defined_in;
 VersionSpec version;
 TypeCode result;
 OperationMode mode;
 ContextIdSeq contexts;
 ParamDescriptionSeq parameters;
 ExcDescriptionSeq exceptions;
};
```

### OperationDescription structure

`OperationDescription` members store the following information:

|                         |                                                                                                                                                                     |
|-------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>name</code>       | The operation's name. For example, for operation <code>Account::makeWithdrawal()</code> , <code>name</code> contains <code>makeWithdrawal</code> .                  |
| <code>id</code>         | <code>RepositoryId</code> for the <code>OperationDef</code> object.                                                                                                 |
| <code>defined_in</code> | The <code>RepositoryId</code> for the parent <code>Container</code> of the <code>OperationDef</code> object.                                                        |
| <code>version</code>    | Currently not supported. When implemented, this member allows the interface repository to distinguish between multiple versions of a definition with the same name. |
| <code>result</code>     | The <code>TypeCode</code> of the result returned by the defined operation.                                                                                          |

|                         |                                                                                                                                                            |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>mode</code>       | Specifies whether the operation returns ( <code>OP_NORMAL</code> ) or is oneway ( <code>OP_ONEWAY</code> ).                                                |
| <code>contexts</code>   | Lists the context identifiers specified in the operation's context clause.                                                                                 |
| <code>parameters</code> | A sequence of <code>ParameterDescription</code> structures that contain details of each operation parameter.                                               |
| <code>exceptions</code> | A sequence of <code>ExceptionDescription</code> structures that contain details of the exceptions specified in the operation's <code>raises</code> clause. |

### TypeDescription structure

Several repository object types use the `TypeDescription` structure to store their information: `EnumDef`, `UnionDef`, `AliasDef`, and `StructDef`.

### FullInterfaceDescription and FullValueDescription structures

Interfaces `InterfaceDef` and `ValueDef` contain extra description structures, `FullInterfaceDescription` and `FullValueDescription`, respectively.

These structures let you obtain a full description of the interface or value and all its contents in one step. These structures are returned by operations `InterfaceDef::describe_interface()` and `ValueDef::describe_value()`.

---

## Retrieving Repository Information

You can retrieve information from the interface repository in three ways:

- Given an object reference, find its corresponding `InterfaceDef` object and query its details.
  - Given an object reference to a `Repository`, browse its contents.
  - Given a `RepositoryId`, obtain a reference to the corresponding object in the interface repository and query its details.
- 

### Getting a CORBA object's interface

Given a reference to a CORBA object, you can obtain its interface from the interface repository by invoking `_get_interface()` on it. For example, given CORBA object `objVar`, you can get a reference to its corresponding `InterfaceDef` object as follows:

```
CORBA::InterfaceDef_var ifVar=
 objVar->_get_interface();
```

The member function `_get_interface()` returns a reference to an object within the interface repository. You can then use this reference to browse the repository, and to obtain the details of an interface definition.

---

### Browsing and listing repository contents

After you obtain a reference to a `Repository` object, you can browse or list its contents. To obtain a `Repository`'s object reference, invoke `resolve_initial_references("InterfaceRepository")` on the ORB. This returns an object reference of type `CORBA::Object`, which you narrow to a `CORBA::Repository` reference.

The abstract interface `Container` has four operations that enable repository browsing:

- `lookup()`
- `lookup_name()`
- `contents()`
- `describe_contents()`

#### Finding repository objects

`Container` operations `lookup()` and `lookup_name()` are useful for searching the contents of a repository for one or more objects.

**lookup()** conducts a search for a single object based on the supplied `ScopedName` argument, which contains the entity's name relative to other repository objects. A `ScopedName` that begins with `::` is an absolute scoped name—that is, it uniquely identifies an entity within a repository—for example, `::Finance::Account::makeWithdrawal`. A `ScopedName` that does not begin with `::` identifies an entity relative to the current one.

For example, if module `Finance` contains attribute `Account::balance`, you can get a reference to the operation's corresponding `AttributeDef` object by invoking the module's `lookup()` operation:

```
CORBA::Contained_var cVar;
cVar = moduleVar->lookup("Account::balance");
```

The `ScopedName` argument that you supply can specify to search outside the scope of the actual container on which you invoke `lookup()`. For example, the following statement invokes `lookup()` on an `InterfaceDef` in order to start searching for the `newAccount` operation from the `Repository` container:

```
CORBA::Contained_var cVar;
cVar = ifVar->lookup("::Finance::Bank::newAccount");
```

**lookup\_name()** searches the target container for objects that match a simple unscoped name. Because the name might yield multiple matches, `lookup_name()` returns a sequence of `Contained` objects. `lookup_name()` takes the following arguments:

|                               |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|-------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>search_name</code>      | A string that specifies the name of the objects to find. You can use asterisks (*) to construct wildcard searches.                                                                                                                                                                                                                                                                                                                                                                                        |
| <code>levels_to_search</code> | Specifies the number of levels of nested containers to include in the search. 1 restricts searching to the current object. -1 specifies an unrestricted search.                                                                                                                                                                                                                                                                                                                                           |
| <code>limit_type</code>       | Supply a <code>DefinitionKind</code> enumerator to include a specific type of repository object in the returned sequence. For example, set <code>limit_type</code> to <code>dk_operation</code> to find only operations. To return all objects, supply <code>dk_all</code> . You can also supply <code>dk_none</code> to match no repository objects, and <code>dk_TYPEDEF</code> , which encompasses <code>dk_AlIAS</code> , <code>dk_Struct</code> , <code>dk_Union</code> , and <code>dk_Enum</code> . |

`exclude_inherited` Valid only for `InterfaceDef` and `ValueDef` objects. Supply `TRUE` to exclude inherited definitions, `FALSE` to include.

Unlike `lookup()`, `lookup_name()` searches are confined to the target container.

### Getting object descriptions

Container operations `contents()` and `describe_contents()` let you obtain object descriptions:

**contents()** returns a sequence of `Contained` objects that belong to the `Container`. You can use this operation to search a given container for a specific object. When it is found, you can call `Contained::describe()`, which returns a `Contained::Description` for the contained object (see “Repository Object Descriptions” on page 471).

**describe\_contents()** combines operations `Container::contents()` and `Contained::describe()`, and returns a sequence of `Contained::Description` structures, one for each of the `Contained` objects found.

You can limit the scope of the search by `contents()` and `describe_contents()` by setting one or more of the following arguments:

`limit_type` Supply a `DefinitionKind` enumerator to limit the contents list to a specific type of repository object. To return all objects, supply `dk_all`. You can also supply `dk_none` to match no repository objects, and `dk_Typedef`, which encompasses `dk_Alloc`, `dk_Struct`, `dk_Union`, and `dk_Enum`.

`exclude_inherited` Valid only for `InterfaceDef` and `ValueDef` objects. Supply `TRUE` to exclude inherited definitions from the contents listing, `FALSE` to include.

`max_returned_objs` Available only for `describe_contents()`, this argument specifies the maximum length of the sequence returned.

**Finding an object using its repository id**

---

You can use a repository ID to find any object in a repository by invoking `Container::bakup_id()` on that repository. `bakup_id()` returns a reference to a `Contained` object, which can be narrowed to the appropriate object reference type.

## Sample Usage

This section contains code that uses the interface repository; it prints the list of operation names and attribute names that are defined in a given object's interface.

```
int i;
Repository_var rVar;
Contained_var cVar;
InterfaceDef_var interfaceVar;
InterfaceDef::FullInterfaceDescription_var full;
CORBA::Object_var obj;

try {
 //get an object reference to the IFR :
 obj =
 orb->resolve_initial_references("InterfaceRepository");
 rVar = Repository::_narrow(obj);

 //Get the interface definition:
 cVar = rVar->lookup("Grid");
 interfaceVar = InterfaceDef::_narrow(cVar);

 //Get a full interface description:
 full = interfaceVar->describe_interface();

 //Now print out the operation names:
 cout << "The operation names are:" << endl;
 for (i = 0; i < full->operations.length(); i++)
 cout << full->operations[i].name << endl;

 //Now print out the attribute names:
 cout << "The attribute names are:" << endl;
 for (i = 0; i < full->attributes.length(); i++)
 cout << full->attributes[i].name << endl;
}
catch (...) {
 ...
}
```

The example can be extended by finding the `OperationDef` object for an operation called `doit()`. Operation `Container::lookup_name()` can be used as follows:

```
ContainedSeq_var opSeq;
OperationDef_var doitOpVar;

try {
 cout << "Looking up operation doit()" << endl;
 << endl;
 opSeq = interfaceVar->lookup_name("doit", 1, dk_Operation, 0);
 if (opSeq->length() != 1) {
 cout << "Incorrect result for lookup_name()";
 exit(1);
 } else {
 //Narrow the result to be an OperationDef.
 doitOpVar =
 OperationDef::_narrow(opSeq[0]);
 }
 ...
}
catch (...) {
 ...
}
```

## Repository IDs and Formats

Each interface repository object that describes an IDL definition has a repository ID. A repository ID globally identifies an IDL module, interface, constant, typedef, exception, attribute, or operation definition. A repository ID is simply a string that identifies the IDL definition.

Three formats for repository IDs are defined by CORBA. However, repository IDs are not, in general, required to be in one of these formats:

- [OMG IDL](#)
- [DCE UUID](#)
- [LOCAL](#)

### OMG IDL

The default format used by Orbix, the OMG IDL format is derived from the IDL definition's scoped name:

```
DL:identifier[/identifier]...version-number
```

This format contains three colon-delimited components:

- The first component identifies the repository ID format as the OMG IDL format.
- A list of identifiers specifies the scoped name, substituting backslash (\) for double colon (::).
- *version-number* contains a version number with the following format:

```
major minor
```

For example, given the following IDL definitions:

```
//IDL
interface Account {
 readonly attribute float balance;
 void makeDeposit(in float amount);
};
```

The IDL format repository ID for attribute `Account::balance` looks like this:

```
DL#Account::balance:1.0
```

### DCE UUID

The DCE UUID has the following format:

```
DCEUUID:minor-version-number
```

**LOCAL**

---

Local format IDs are for local use within an interface repository and are not intended to be known outside that repository. They have the following format:

*LOCAL:ID*

Local format repository IDs can be useful in a development environment as a way to avoid conflicts with repository IDs that use other formats.

---

## Controlling Repository IDs with Pragma Directives

You can control repository ID formats with pragma directives in an IDL source file. Specifically, you can use pragmas to set the repository ID for a specific IDL definition, and to set prefixes and version numbers on repository IDs.

You can insert prefix and version pragma statements at any IDL scope; the IDL compiler assigns the prefix or version only to objects that are defined within that scope. Prefixes and version numbers are not applied to definitions in files that are included at that scope. Typically, prefixes and version numbers are set at global scope, and are applied to all repository IDs.

### ID pragma

---

You can explicitly associate an interface repository ID with an IDL definition, such as an interface name or typedef. The definition can be fully or partially scoped and must conform with one of the IDL formats approved by the OMG (see [“Repository IDs and Formats” on page 480](#)).

For example, the following IDL assigns repository ID `idltest:1.1` to interface `test`:

```
module Y {
 interface test {
 // ...
 };
 #pragma ID test "idltest:1.1"
};
```

## Prefix pragma

The IDL `prefix` pragma lets you prepend a unique identifier to repository IDs. This is especially useful in ensuring against the chance of name conflicts among different applications. For example, you can modify the IDL for the `Finance` module to include a `prefix` pragma as follows:

```
//IDL
pragma prefix "USB "
module Finance {
 interface Account {
 readonly attribute float balance;
 ...
 };
 interface Bank {
 Account newAccount();
 };
};
```

These definitions yield the following repository IDs:

```
DL:USB:Finance:1.0
DL:USB:Finance:Account:1.0
DL:USB:Finance:Account:balance:1.0
DL:USB:Finance:Bank:1.0
DL:USB:Finance:Bank:newAccount:1.0
```

## Version pragma

A version number for an IDL definition's repository ID can be specified with a `version` pragma. The `version` pragma directive uses the following format:

```
pragma version name major minor
```

*name* can be a fully scoped name or an identifier whose scope is interpreted relative to the scope in which the pragma directive is included. If no version pragma is specified for an IDL definition, the default version number is 1.0. For example:

```
//IDL
module Finance {
 # pragma version Account 2.5
 interface Account {
 // ...
 };
};
```

These definitions yield the following repository IDs:

```
DL:Finance:1.0
```

`DL:FinanceAccount2.5`

Version numbers are embedded in the string format of an object reference. A client can invoke on the corresponding server object only if its interface has a matching version number, or has no version associated with it.

**Note:** You cannot populate the interface repository with two IDL interfaces that share the same name but have different version numbers.

# Naming Service

*The Orbix naming service lets you associate names with objects. Servers can register object references by name with the naming service repository, and advertise those names to clients. Clients, in turn, can resolve the desired objects in the naming service by supplying the appropriate name.*

The Orbix naming service implements the OMG COS Interoperable Naming Service, which describes how applications can map object references to names.

---

## Benefits

Using the naming service can offer the following benefits:

- Clients can locate objects through standard names that are independent of the corresponding object references. This affords greater flexibility to developers and administrators, who can direct client requests to the most appropriate implementation. For example, you can make changes to an object's implementation or its location that are transparent to the client.
- The naming service provides a single repository for object references. Thus, application components can rely on it to obtain an application's initial references.

**In this chapter**

This chapter describes how to build and maintain naming graphs programmatically. It also shows how to use object groups to achieve load balancing. It contains these sections:

|                                                      |
|------------------------------------------------------|
| <a href="#">Naming Service Design</a>                |
| <a href="#">Defining Names</a>                       |
| <a href="#">Obtaining the Initial Naming Context</a> |
| <a href="#">Building a Naming Graph</a>              |
| <a href="#">Using Names to Access Objects</a>        |
| <a href="#">Listing Naming Context Bindings</a>      |
| <a href="#">Maintaining the Naming Service</a>       |
| <a href="#">Federating Naming Graphs</a>             |
| <a href="#">Sample Code</a>                          |
| <a href="#">Object Groups and Load Balancing</a>     |
| <a href="#">Load Balancing Example</a>               |

Many operations that are discussed here can also be executed administratively with Orbix tools. For more information about these and related configuration options, refer to the *Application Server Platform Administrator's Guide*.

# Naming Service Design

## Naming graph organization

The naming service is organized into a *naming graph*, which is equivalent to a directory system. A naming graph consists of one or more *naming contexts*, which correspond to directories. Each naming context contains zero or more name-reference associations, or *name bindings*, each of which refers to another node within the naming graph. A name binding can refer either to another naming context or to an object reference. Thus, any path within a naming graph finally resolves to either a naming context or an object reference. All bindings in a naming graph can usually be resolved via an *initial naming context*.

## Example

Figure 22 shows how the `Account` interface described in earlier chapters might be extended (through inheritance) into multiple objects, and organized into a hierarchy of naming contexts. In this graph, hollow nodes are naming contexts and solid nodes are application objects. Naming contexts are typically intermediate nodes, although they can also be leaf nodes; application objects can only be leaf nodes.




Figure 22: A naming graph is a hierarchy of naming contexts

Each leaf node in this naming graph associates a name with a reference to an account object such as a basic checking account or a personal loan account. Given the full path from the initial naming context—for example, `Savings.Regular`—a client can obtain the associated reference and invoke requests on it.

The operations and types that the naming service requires are defined in the IDL file `ComNaming.idl`. This file contains a single module, `ComNaming`, which in turn contains three interfaces: `NamingContext`, `NamingContextExt`, and `BindingIterator`.

# Defining Names

## Name sequence

A naming graph is composed of `Name` sequences of `NameComponent` structures, defined in the `CosNaming` module:

```
module CosNaming{
 typedef string IString;
 struct NameComponent {
 IString id;
 IString kind;
 }
 typedef sequence< NameComponent> Name;
 ...
};
```

A `Name` sequence specifies the path from a naming context to another naming context or application object. Each name component specifies a single node along that path.

## Name components

Each name component has two string members:

- The `id` field acts as a name component's principle identifier. This field must be set.
- The `kind` member is optional; use it to further differentiate name components, if necessary.

Both `id` and `kind` members of a name component are used in name resolution. So, the naming service differentiates between two name components that have the same ids but different kinds.

For example, in the naming graph shown in [Figure 22 on page 487](#), the path to a Personal loan account object is specified by a `Name` sequence in which only the `id` fields are set:

| Index | id       | kind |
|-------|----------|------|
| 0     | Loans    |      |
| 1     | Personal |      |

In order to bind another Personal account object to the same Loan naming context, you must differentiate it from the existing one. You might do so by setting their `kind` fields as follows:

| Index | id       | kind      |
|-------|----------|-----------|
| 0     | Loans    |           |
| 1     | Personal | unsecured |
| 1     | Personal | secured   |

**Note:** If the `kind` field is unused, it must be set to an empty string.

## Representing Names as Strings

The `CosNaming:NamingContextExt` interface defines a `StringName` type, which can represent a `Name` as a string with the following syntax:

```
id[kind][/id[kind]] ...
```

Name components are delimited by a forward slash (/); `id` and `kind` members are delimited by a period (.). If the name component contains only the `id` string, the `kind` member is assumed to be an empty string.

`StringName` syntax reserves the use of three characters: forward slash (/), period (.), and backslash (\). If a name component includes these characters, you can use them in a `StringFormat` by prefixing them with a backslash (\) character.

The `CosNaming:NamingContextExt` interface provides several operations that allow conversion between `StringName` and `Name` data:

- `to_name()` converts a `StringName` to a `Name` (see page 492).
- `to_string()` converts a `Name` to a `StringName` (see page 493).
- `resolve_str()` uses a `StringName` to find a `Name` in a naming graph and returns an object reference (see page 503).

**Note:** You can invoke these and other `CosNaming:NamingContextExt` operations only on an initial naming context that is narrowed to `CosNaming:NamingContextExt`.

## Initializing a Name

You can initialize a `CosNaming::Name` sequence in one of two ways:

- Set the members of each name component.
- Call `to_name()` on the initial naming context and supply a `StringName` argument. This operation converts the supplied string to a `Name` sequence.

### Setting name component members

Given the loan account objects shown earlier, you can set the name for an unsecured personal loan as follows:

#### Example 35: Initializing Name components

```
CosNaming::Name name(2);
name.length(2);
name[0].id = CORBA::string_dup("Loans");
name[0].kind = CORBA::string_dup("");
name[1].id = CORBA::string_dup("Personal");
name[1].kind = CORBA::string_dup("unsecured");
```

### Converting a stringname to a name

The name shown in the previous example can also be set in a more straightforward way by calling `to_name()` on the initial naming context (see [“Obtaining the Initial Naming Context” on page 494](#)):

#### Example 36: Using `to_name()` to initialize a Name

```
//get initial naming context
CosNaming::NamingContextExt_var root_ctx = ...;

CosNaming::Name_var name;
name = root_ctx->to_name("Loans/Personal/unsecured");
```

The `to_name()` operation takes a string argument and returns a `CosNaming::Name`, which the previous example sets as follows:

| Index | id       | kind      |
|-------|----------|-----------|
| 0     | Loans    |           |
| 1     | Personal | unsecured |

---

## Converting a Name to a StringName

You can convert a `CosNaming::Name` to a `CosNamingExt::StringName` by calling `to_string()` on the initial naming context. This lets server programs to advertise human-readable object names to clients.

For example, the following code converts `Name` sequence `name` to a `StringName`:

### Example 37: Converting a Name to a StringName

```
//get initial naming context
CosNaming::NamingContextExt_var root_ctxt = ...;
CosNaming::NamingContextExt::StringName str_n;

//initialize name
CosNaming::Name_var name = ...;
...
str_n = root_ctxt->to_string(name);
```

## Obtaining the Initial Naming Context

Clients and servers access a naming service through its initial naming context, which provides the standard entry point for building, modifying, and traversing a naming graph. To obtain the naming service's initial naming context, call `resolve_initial_references()` on the ORB. For example:

### Example 38: Obtaining the initial naming context

```
...
//Initialize the ORB
CORBA::ORB_var orb = CORBA::ORB_init(argc, argv);

//Get reference to initial naming context
CORBA::Object obj =
 orb_var->resolve_initial_references("NameService");
```

To obtain a reference to the naming context, narrow the result with `CosNaming::NamingContextExt::_narrow()`:

```
CosNaming::NamingContextExt_var root_ctx;
if (root_ctx =
 CosNaming::NamingContextExt::_narrow(obj)) {
} else { ... } //Deal with failure to _narrow()
...
```

A naming graph's initial naming context is equivalent to the root directory. Later sections show how you use the initial naming context to build and modify a naming graph, and to resolve names to object references.

**Note:** The `NamingContextExt` interface provides extra functionality over the `NamingContext` interface; therefore, the code in this chapter assumes that an initial naming context is narrowed to the `NamingContextExt` interface.

---

# Building a Naming Graph

A name binding can reference either an object reference or another naming context. By binding one naming context to another, you can organize application objects into logical categories. However complex the hierarchy, almost all paths within a naming graph hierarchy typically resolve to object references.

In an application that uses a naming service, a server program often builds a multi-tiered naming graph on startup. This process consists of two repetitive operations:

- [Bind naming contexts into the desired hierarchy.](#)
- [Bind objects into the appropriate naming contexts.](#)

## Binding Naming Contexts

A server that builds a hierarchy of naming contexts contains the following steps:

1. Gets the initial naming context (see page 494).
2. Creates the first tier of naming contexts from the initial naming context.
3. Binds the new naming contexts to the initial naming context.
4. Adds naming contexts that are subordinate to the first tier:
  - ◆ Creates a naming context from any existing one.
  - ◆ Binds the new naming context to its designated parent.

The naming graph shown in [Figure 22 on page 487](#) contains three naming contexts that are directly subordinate to the initial naming context: Checking, Loans, and Savings. The following code binds the Checking naming context to the initial naming context, as shown in [Figure 23](#):

### Example 39: Binding a naming context to the initial naming context


```
//get initial naming context
CosNaming::NamingContextExt_var root_ctxt = ...;

CosNaming::NamingContext_var checking_ctxt;

//create naming context
checking_ctxt = root_ctxt->new_context();

//initialize name
CosNaming::Name_var name;
name.length(1);
name[0].id = CORBA::string_dup("Checking");
name[0].kind = CORBA::string_dup("");

//bind new context
root_ctxt->bind_context(name, checking_ctxt);
```



**Figure 23:** *Checking context bound to initial naming context*

Similarly, you can bind the Savings and Loans naming contexts to the initial naming context. The following code uses the shortcut operation `bind_new_context()`, which combines `new_context()` and `bind()`. It also uses the `to_name()` operation to set the `Name` variable.

**Example 40:** *Binding a naming context with `bind_new_context()`*


```

CosNaming: NamingContext var savings_cxt, loan_cxt;

// create naming contexts
name = root_cxt->to_name("Savings");
savings_cxt = root_cxt->bind_new_context(name);

name = root_cxt->to_name("Loan");
loan_cxt = root_cxt->bind_new_context(name);

```



**Figure 24:** *Savings and Loans naming contexts bound to initial naming context*

## Orphaned naming contexts

The naming service can contain naming contexts that are unbound to any other context. Because these naming contexts have no parent context, they are regarded as *orphaned*. Any naming context that you create with

`new_context()` is orphaned until you bind it to another context. Although it has no parent context, the initial naming context is not orphaned inasmuch as it is always accessible through `resolve_initial_references()`, while orphan naming contexts have no reliable means of access.

You might deliberately leave a naming context unbound—for example, you are in the process of constructing a new branch of naming contexts but wish to test it before binding it into the naming graph. Other naming contexts might appear to be orphaned within the context of the current naming service; however, they might actually be bound to a federated naming graph in another naming service (see [“Federating Naming Graphs” on page 512](#)).

### Erroneous usage of orphaned naming contexts

Orphaned contexts can also occur inadvertently, often as a result of carelessly written code. For example, you can create orphaned contexts as a result of calling `rebind()` or `rebind_context()` to replace one name binding with another (see [“Rebinding” on page 501](#)). The following code shows how you might orphan the Savings naming context:

#### Example 41: Orphaned naming contexts

```
//get initial naming context
CosNaming::NamingContextExt_var root_ctxt = ...;

CosNaming::NamingContext_var savings_ctxt;

// initialize name
CosNaming::Name_var name;
name.length(1);
name[0].id = CORBA::string_dup("Savings");
name[0].kind = CORBA::string_dup("");

// create and bind checking_ctxt
savings_ctxt = root_ctxt->bind_new_context(name);

// make another context
CosNaming::NamingContext_var savings_ctxt2;
savings_ctxt2 = root_ctxt->new_context();

// bind savings_ctxt2 to root context, savings_ctxt now orphaned!
root_ctxt->rebind_context(name, savings_ctxt2);
```

An application can also create an orphan context by calling `unbind()` on a context without calling `destroy()` on the same context object (see [“Maintaining the Naming Service” on page 510](#)).

In both cases, if the application exits without destroying the context objects, they remain in the naming service but are inaccessible and cannot be deleted.


## Binding Object References

After you construct the desired hierarchy of naming contexts, you can bind object references to them with the `bind()` operation. The following example builds on earlier code to bind a Basic checking account object to the Checking naming context:

**Example 42:** *Binding an object reference*

```
//object reference 'basic_check' obtained earlier
...

nam e-> length(1);
nam e[0].id = CORBA::string_dup("Basic");
nam e[0].kind = CORBA::string_dup("");
checking_cxt-> bind(nam e,basic_check);
```



**Figure 25:** *Binding an object reference to a naming context*

The previous code assumes the existence of a `NamingContext` variable for the `Checking` naming context on which you can invoke `bind()`. Alternatively, you can invoke `bind()` on the initial naming context in order to bind `Basic` into the naming graph:

```
nam e = root_cxt-> to_name("Checking,Basic");
root_cxt-> bind(nam e,basic_check);
```

---

## Rebinding

If you call `bind()` or `bind_context()` on a naming context that already contains the specified binding, the naming service throws an exception of `AlreadyBound`. To ensure the success of a binding operation whether or not the desired binding already exists, call one of the following naming context operations:

- `rebind()` rebinds an application object.
- `rebind_context()` rebinds a naming context.

Either operation replaces an existing binding of the same name with the new binding. Calls to `rebind()` in particular can be useful on server startup, to ensure that the naming service has the latest object references.

**Note:** Calls to `rebind_context()` or `rebind()` can have the undesired effect of creating orphaned naming contexts ([see page 497](#)). In general, exercise caution when calling either function.

## Using Names to Access Objects

A client application can use the naming service to obtain object references in three steps:

1. Obtain a reference to the initial naming context (see page 494).
2. Set a `CosNaming::Name` structure with the full path of the name associated with the desired object.
3. Resolve the name to the desired object reference.

### Setting object names

You specify the path to the desired object reference in a `CosNaming::Name`. You can set this name in one of two ways:

**Explicitly set the `id` and `kind` members of each `Name` element.** For example, the following code sets the name of a Basic checking account object:

#### Example 43: Setting object name components

```
CosNaming::Name_var name;
name.length(2);
name[0].id = CORBA::string_dup("Checking");
name[0].kind = CORBA::string_dup("");
name[1].id = CORBA::string_dup("Basic");
name[1].kind = CORBA::string_dup("");
```

**Call `to_name()` on the initial naming context.** This option is available if the client code narrows the initial naming context to the `NamingContextExt` interface. `to_name()` takes a `CosNaming::CosNamingExt::StringName` argument and returns a `CosNaming::Name` as follows:

#### Example 44: Setting an object name with `to_name()`

```
CosNaming::Name_var name;
name = root_ctx->to_name("Checking/Basic");
```

For more about using a `StringName` with `to_name()`, see “Converting a stringname to a name” on page 492.

## Resolving names

Clients call `resolve()` on the initial naming context to obtain the object associated with the supplied name:

### Example 45: Calling `resolve()`

```
CORBA:Object_varobj
...
obj= root_ctx-> resolve(name);
```

Alternatively, the client can call `resolve_str()` on the initial naming context to resolve the same name using its `StringName` equivalent:

### Example 46: Calling `resolve_str()`

```
CORBA:Object_varobj
...
obj= root_ctx-> resolve_str("Checking/Basic");
```

In both cases, the object returned in `obj` is an application object that implements the IDL interface `BasicChecking`, so the client narrows the returned object accordingly:

```
BasicChecking_varchecking_var;
...
try {
 checking_var= BasicChecking::narrow(obj) {
 //perform some operation on basic checking object
 ...
 } //end of try clause, catch clauses not shown
```

## Resolving names with `corbaname`

You can resolve names with a `corbaname` URL, which is similar to a `corbaloc` URL (see [“Using corbaloc URL strings” on page 207](#)). However, a `corbaname` URL also contains a stringified name that identifies a binding in a naming context. For example, the following code uses a `corbaname` URL to obtain a reference to a `BasicChecking` object:

### Example 47: Resolving a name with `corbaname`

```
CORBA:Object_varobj
obj= orb-> string_to_object(
 "corbaname::ir::NameService#Checking/Basic"
);
```

A corbaname URL has the following syntax:

```
corbaname:iri:[NameService]#string-name
```

*string-name* is a string that conforms to the format allowed by a `CoNameing:CoNameingExt:StringName` (see [“Representing Names as Strings” on page 491](#)). A corbaname can omit the `NameService` specifier. For example, the following call to `string_to_object()` is equivalent to the call shown earlier:

```
obj= oib-> string_to_object('corbaname:iri#CheckingBasic');
```

---

## Exceptions Returned to Clients

Invocations on the naming service can result in the following exceptions:

**NotFound** The specified name does not resolve to an existing binding. This exception contains two data members:

|                           |                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|---------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>why</code>          | Explains why a lookup failed with one of the following values: <ul style="list-style-type: none"><li>• <code>missing_node</code>: one of the name components specifies a non-existent binding.</li><li>• <code>not_context</code>: one of the intermediate name components specifies a binding to an application object instead of a naming context.</li><li>• <code>not_object</code>: one of the name components points to a non-existent object.</li></ul> |
| <code>rest_of_name</code> | Contains the trailing part of the name that could not be resolved.                                                                                                                                                                                                                                                                                                                                                                                            |

**InvalidName** The specified name is empty or contains invalid characters.

**CannotProceed** The operation fails for reasons not described by other exceptions. For example, the naming service's internal repository might be in an inconsistent state.

**AlreadyBound** Attempts to create a binding in a context throw this exception if the context already contains a binding of the same name.

**Not Empty** Attempts to delete a context that contains bindings throw this exception. Contexts must be empty before you delete them.

## Listing Naming Context Bindings

In order to find an object reference, a client might need to iterate over the bindings in one or more naming contexts. You can invoke the `list()` operation on a naming context to obtain a list of its name bindings. This operation has the following signature:

```
void list(
 in unsigned long how_many,
 out BindingList bl,
 out BindingIterator it);
```

`list()` returns with a `BindingList`, which is a sequence of `Binding` structures:

```
enum BindingType{ nobject, ncontext };

struct Binding{
 Name binding_name
 BindingType binding_type;
}
typedef sequence< Binding> BindingList
```

### Iterating over binding list elements

Given a binding list, the client can iterate over its elements to obtain their binding name and type. Given a `Binding` element's name, the client application can call `resolve()` to obtain an object reference; it can use the binding type information to determine whether the object is a naming context or an application object.

For example, given the naming graph in [Figure 22](#), a client application can invoke `list()` on the initial naming context and return a binding list with three `Binding` elements:

| Index | Name     | BindingType |
|-------|----------|-------------|
| 0     | Checking | ncontext    |
| 1     | Savings  | ncontext    |
| 2     | Loan     | ncontext    |

---

## Using a Binding Iterator

---

### Limiting number of bindings returned by list()

In the previous example, `list()` returns a small binding list. However, an enterprise application is likely to require naming contexts with a large number of bindings. `list()` therefore provides two parameters that let a client obtain all bindings from a naming context without overrunning available memory:

**how\_many** sets the maximum number of elements to return in the binding list. If the number of bindings in a naming context is greater than `how_many`, `list()` returns with its `BindingIterator` parameter set.

**it** is a `BindingIterator` object that can be used to retrieve the remaining bindings in a naming context. If `list()` returns with all bindings in its `BindingList`, this parameter is set to `nil`.

A `BindingIterator` object has the following IDL interface definition:

```
interface BindingIterator{
 boolean next_one(out Binding b);
 boolean next_n(in unsigned long how_many, out BindingList
 bl);
 void destroy();
}
```

---

### Obtaining remainder of bindings

If `list()` returns with a `BindingIterator` object, the client can invoke on it either `next_n()` to retrieve the next specified number of remaining bindings, or `next_one()` to retrieve one remaining binding at a time. Both functions return true if the naming context contains more bindings to fetch. Together, these `BindingIterator` operations and `list()` let a client safely obtain all bindings in a context.

**Note:** The client is responsible for destroying an iterator. It also must be able to handle exceptions that might return when it calls an iterator operation, inasmuch as the naming service can destroy an iterator at any time before the client retrieves all naming context bindings.

The following client code gets a binding list from a naming context and prints each element's binding name and type:

**Example 48:** *Obtaining a binding list*

```
//printing function
void
print_binding_list(const CosNaming::BindingList&bl)
{
 for(CORBA::Ulong i= 0;i< bl.length();i+){
 cout<< bl[i].binding_name[0].id;
 if(bl[i].binding_name[0].kind != '\0')
 cout<< "("<< bl[i].binding_name[0].kind<< ")";
 if(bl[i].binding_type == CosNaming::nocontext)
 cout<< ":naming context"<< endl;
 else
 cout<< ":object reference"<< endl;
 }
}

void
get_context_bindings(CosNaming::NamingContext_ptr cxt)
{
 CosNaming::BindingList_var b_list;
 CosNaming::BindingIterator_var b_iter;
 const CORBA::Ulong MAX_BINDINGS = 50;

 if (CORBA::is_nil(cxt)) {

 //get first set of bindings from cxt
 root_cxt-> list(MAX_BINDINGS, b_list, b_iter);

 //print first set of bindings
 print_binding_list(b_list);

 //look for remaining bindings
 if (CORBA::is_nil(b_iter)) {
 CORBA::Boolean more;
 do {
 is_nil(b_iter)) {
 more = b_iter-> next_n(MAX_BINDINGS, b_list);
 //print next set of bindings
 print_binding_list(b_list);
 } while (more);
 } while (more);
 }
 }
}
```

**Example 48:** *Obtaining a binding list*

```
}
//get rid of iterator
b_iter-> destroy();
}
}
```

When you run this code on the initial naming context shown earlier, it yields the following output:

```
Checking: naming context
Savings: naming context
Loan: naming context
```

## Maintaining the Naming Service

Destruction of a context and its bindings is a two-step procedure:

- Remove bindings to the target context from its parent contexts by calling `unbind()` on them.
- Destroy the context by calling the `destroy()` operation on it. If the context contains bindings, these must be destroyed first; otherwise, `destroy()` returns with a `NotEmpty` exception.

These operations can be called in any order; but it is important to call both. If you remove the bindings to a context without destroying it, you leave an orphaned context within the naming graph that might be impossible to access and destroy later (see “Orphaned naming contexts” on page 497). If you destroy a context but do not remove its bindings to other contexts, you leave behind bindings that point nowhere, or *dangling bindings*.

For example, given the partial naming graph in [Figure 26](#), you can destroy the Loans context and its bindings to the loan account objects as follows:

### Example 49: Destroying a naming context

```
CosNaming:NamingVarName;

//get initial naming context
CosNaming:NamingContextExt_varroot_ctx= ...;


//assume availability of Loans naming context variable
CosNaming:NamingContext_varloans_ctx= ...;

//remove bindings to Loans context
Name = root_ctx-> to_name("LoansMortgage");
root_ctx-> unbind(Name);
Name = root_ctx-> to_name("LoansAuto");
root_ctx-> unbind(Name);
Name = root_ctx-> to_name("LoansPersonal");
root_ctx-> unbind(Name);

//remove binding from Loans context to initial naming context
Name = root_ctx-> to_name("Loans");
root_ctx-> unbind(Name);
```

**Example 49:** *Destroying a naming context*

```
//destroy orphaned Loans context
loans_ctx->destroy();
```



**Figure 26:** *Destroying a naming context and removing related bindings*

**Note:** Orbix provides administrative tools to destroy contexts and remove bindings. These are described in the *Application Server Platform Administrator's Guide*.

---

# Federating Naming Graphs

A naming graph can span multiple naming services, which can themselves reside on different hosts. Given the initial naming context of an external naming service, a naming context can transparently bind itself to that naming service's naming graph. A naming graph that spans multiple naming services is said to be *federated*.

---

## Benefits

A federated naming graph offers the following benefits:

- *Reliability*: By spanning a naming graph across multiple servers, you can minimize the impact of a single server's failure.
  - *Load balancing*: You can distribute processing according to logical groups. Multiple servers can share the work load of resolving bindings for different clients.
  - *Scalability*: Persistent storage for a naming graph is spread across multiple servers.
  - *Decentralized administration*: Logical groups within a naming graph can be maintained separately through different administrative domains, while they are collectively visible to all clients across the network.
- 


## Federation models

Each naming graph in a federation must obtain the initial naming context of other members in order to bind itself to them. The binding possibilities are virtually infinite; however, two federation models are widely used:

- **Hierarchical federation** — All naming graphs are bound to a root server's naming graph. Clients access objects via the initial naming context of the root server.
- **Fully-connected federation** — Each naming graph directly binds itself to all other naming graphs. Typically, each naming graph binds the initial naming contexts of all other naming graphs into its own initial naming context. Clients can access all objects via the initial naming context of their local naming service.

**Hierarchal federation**

Figure 27 shows a hierarchal naming service federation that comprises three servers. The Deposits server maintains naming contexts for checking and savings accounts, while the Loans server maintains naming contexts for loan accounts. A single root server serves as the logical starting point for all naming contexts.



**Figure 27:** A naming graph that spans multiple servers

In this hierarchical structure, the naming graphs in the Deposits and Loans servers are federated through an intermediary root server. The initial naming contexts of the Deposits and Loans servers are bound to the root server's initial naming context. Thus, clients gain access to either naming graph through the root server's initial naming context.

The following code binds the initial naming contexts of the Deposits and Loans servers to the root server's initial naming context:

**Example 50:** *Federating naming graphs to a root server's initial naming context*

```
//Root server
#include <omg/CosNaming.h>
...
int main (int argc, char** argv) {
 CosNaming::NamingContextExt var
 root_inc, deposits_inc, bans_inc;
 CosNaming::Name name;
 CORBA::Object varobj;
 CORBA::ORB varorb;
 char*bans_inc_ior, deposits_inc_ior;
 ...
 try {
 orb_var = CORBA::ORB_init(argc, argv, "Orbix");

 //code to obtain stringified IRI of initial naming
 //contexts for Loans and Deposits servers (not shown)
 ...


 obj = orb_var->string_to_object (bans_inc_ior);
 bans_inc =
 CosNaming::NamingContextExt::_narrow (obj);
 obj = orb_var->string_to_object (deposits_inc_ior);
 deposits_inc =
 CosNaming::NamingContextExt::_narrow (obj);

 //get initial naming context for Root server
 root_inc = ...;

 //bind Deposits initial naming context to root server
 //initial naming context
 name = root_inc->to_name ("Deposits");
 root_inc->bind_context(name, deposits_inc);

 //bind Loans initial naming context to root server's
 //initial naming context
 name = root_inc->to_name ("Loans");
 root_inc->bind_context(name, deposits_inc);
 }
}
```

This yields the following bindings between the three naming graphs:




**Figure 28:** Multiple naming graphs are linked by binding initial naming contexts of several servers to a root server.

### Fully-connected federation

In a purely hierarchical model like the naming graph just shown, clients obtain their initial naming context from the root server, and the root server acts as the sole gateway into all federated naming services. To avoid bottlenecks, it is possible to modify this model so that clients can gain access to a federated naming graph via the initial naming context of any member naming service.

The next code example shows how the Deposits and Loans servers can bind the root server's initial naming context into their respective initial naming contexts. Clients can use this binding to locate the root server's initial naming context, and then use root-relative names to locate objects.

Figure 29 shows how this federates the three naming graphs:



**Figure 29:** The root server's initial naming context is bound to the initial naming contexts of other servers, allowing clients to locate the root naming context.

The code for both Deposits and Loans server processes is virtually identical:

**Example 51:** Federating naming graphs through the initial naming contexts of multiple servers

```
include <omg/CosNaming.h>
...
int main (int argc, char** argv) {
 CosNaming::NamingContextExt_var
 root_inc, this_inc;
 CosNaming::Name_var name;
 CORBA::Object_var obj;
 CORBA::ORB_var orb_var;
 char* root_inc_ior;
 ...
 try {
 orb_var= CORBA::ORB_init (argc, argv, "Orbix");

 //code to obtain stringified IORs of root servers
 //initial naming context (not shown)
 ...

 obj= orb_var-> string_to_object (root_inc_ior);
 root_inc = =
 CosNaming::NamingContextExt::_narrow (obj);
 }
}
```

**Example 51:** *Federating naming graphs through the initial naming contexts of multiple servers*

```
//get initial naming context for this server
this_inc = ...;

name = this_inc->to_name("parent");

//bind root server's initial naming context to
//this server's initial naming context
this_inc->bind_context(name, root_inc);
...
}
```

---

## Sample Code

The following sections show the server and client code that is discussed in previous sections of this chapter.

---

### Server code

#### Example 52: Server naming service code

```
#include <omg/CosNaming.h>
...
int main (int argc, char** argv) {
 CosNaming::NamingContextExt_var root_ctxt;
 CosNaming::NamingContext_var
 checking_ctxt, savings_ctxt, ban_ctxt;
 CosNaming::Name_var name;
 CORBA::ORB_var orb;
 CORBA::Object_var obj;
 Checking_var basic_check, now_check, premium_check;
 //Checking_var objects initialized from
 //persistent data (not shown)

 try {
 //Initialize the ORB
 orb = CORBA::ORB_init(argc, argv, "Orbix");

 //Get reference to initial naming context
 obj =
 orb_var->resolve_initial_references("NameService");
 root_ctxt = CosNaming::NamingContextExt::_narrow(obj);
 if (CORBA::is_nil(root_ctxt)) {
 //build naming graph

 //initialize name
 name = root_ctxt->to_name("Checking");
 //bind new naming context to root
 checking_ctxt = root_ctxt->bind_new_context(name);
 }
 }
}
```

**Example 52:** *Server naming service code*

```

//bind checking objects to Checking context
name = root_ctxt-> to_name("Checking/Basic");
checking_ctxt-> bind(name, basic_check);
name = root_ctxt-> to_name("Checking/Premium");
checking_ctxt-> bind(name, premium_check);
name = root_ctxt-> to_name("CheckingNOW");
checking_ctxt-> bind(name, now_check);

name = root_ctxt-> to_name("Savings");
savings_ctxt = root_ctxt-> bind_new_context(name);

//bind savings objects to savings context
...

name = root_ctxt-> to_name("Loan");
loan_ctxt = root_ctxt-> bind_new_context(name);

//bind loan objects to loan context
...
}

else {...} //deal with failure to_narrow()
...
} //end of try clause, catch clauses not shown
...
}

```

**Client code****Example 53:** *Client naming service code*

```

#include <omg/CosNaming.h>
...
int main (int argc, char** argv) {
 CosNaming:NamingContextExt_var root_ctxt;
 CosNaming:Name_var name;
 BasicChecking_var checking_var;
 CORBA:Object_var obj;
 CORBA:ORB_var orb_var;

 try {
 orb_var = CORBA:ORB_init (argc, argv, "Orbik");
 }
}

```

**Example 53:** *Client naming service code*

```
//Find the initial naming context
obj=
obj_var-> resolve_initial_references("NameService");
if (root_ctx==
 CosNaming::NamingContextExt::_narrow(obj)) {
 obj= root_ctx-> resolve_str("Checking/Basic");
 if (checking_var== BasicChecking::_narrow(obj)) {
 //perform some operation on basic checking object
 ...
 }
 else { ... } //Dealwith failure to _narrow()
} else { ... } //Dealwith failure to _narrow()

} //end of try clause, catch clauses not shown
...
}
```

---

# Object Groups and Load Balancing

The naming service defines a repository of names that map to objects. A name maps to one object only. Orbix extends the naming service model to allow a name to map to a group of objects. An *object group* is a collection of objects that can increase or decrease in size dynamically.

---

## Selection algorithms

Each object group has a selection algorithm that is set when the object group is created (see [page 525](#)). This algorithm is applied when a client resolves the name associated with the object group; and the naming service directs client requests to objects accordingly.


Three selection algorithms are supported:

**Round-robin:** The locator uses a round-robin algorithm to select from the list of active servers—that is, the first client is sent to the first server, the second client to the second server, and so on.

**Random:** The locator randomly selects an active server to handle the client.

**Active load balancing:** Each object group member is assigned a load value. The naming service satisfies client `resolve()` invocations by returning references to members with the lowest load values.

Figure 30 shows how a name can bind to multiple objects through an object group.



**Figure 30:** Associating a name with an object group

Orbix supports object groups through its own IDL interfaces. These interfaces let you create object groups and manipulate them: add objects to and remove objects from groups, and find out which objects are members of a particular group. Object groups are transparent to clients.

## Load balancing interfaces

IDL modules `II_LoadBalancing` and `II_Naming`, defined in `orbix/load_balancing.idl` and `orbix/naming.idl`, respectively, provide operations that allow access to Orbix load balancing:

```
module II_LoadBalancing
{
 exception NoSuchMember{};
 exception DuplicateMember{};
 exception DuplicateGroup{};
 exception NoSuchGroup{};
}
```

```

typedef string MemberId;
typedef sequence< MemberId> MemberList;

enum SelectionMethod
{ ROUND_ROBIN_METHOD, RANDOM_METHOD, ACTIVE_METHOD };

struct Member
{
 Object obj;
 MemberId id;
};

typedef string GroupId;
typedef sequence< GroupId> GroupList;

interface ObjectGroup
{
 readonly attribute string id;
 attribute SelectionMethod selection_method;
 Object pick();
 void add_member (in Member m)
 raises (DuplicateMember);
 void remove_member (in Member id)
 raises (NoSuchMember);
 Object get_member (in Member id)
 raises (NoSuchMember);
 MemberList members();
 void destroy();
 void update_member_bad(
 in MemberList ids,
 in double curr_load
) raises (NoSuchMember);
 double get_member_bad(
 in Member id
) raises (NoSuchMember);
 void set_member_timeout(
 in MemberList ids,
 in long timeout_sec
) raises (NoSuchMember);
 long get_member_timeout(
 in Member id
) raises (NoSuchMember);
};

```

```
interface ObjectGroupFactory
{
 ObjectGroup create_round_robin (in GroupId id)
 raises (DuplicateGroup);
 ObjectGroup create_random (in GroupId id)
 raises (DuplicateGroup);
 ObjectGroup create_active (in GroupId id)
 raises (DuplicateGroup);
 ObjectGroup find_group (in GroupId id)
 raises (NoSuchGroup);
 GroupList r_groups();
 GroupList random_groups();
 GroupList active_groups();
};
};
```

For detailed information about these interfaces, see the *CORBA Programmer's Reference*.

---

## Using Object Groups in Orbix

The `IT_LoadBalancing` module lets servers perform the following tasks:

- [Create an object group](#) and add objects to it.
- [Add objects to an existing object group](#).
- [Remove objects from an object group](#).
- [Remove an object group](#).
- [Set member load values](#) and direct client requests accordingly.

---

### Create an object group

You create an object group and add objects to it in the following steps:

1. Get a reference to a naming context such as the initial naming context and narrow to `IT_NamingContextExt`.
2. Create an object group factory by calling `og_factory()` on the naming context object. This returns a reference to an `IT_LoadBalancing::ObjectGroupFactory` object.
3. Create an object group by calling `create_random()`, `create_round_robin()`, or `create_active()` on the object group factory. These operations return a reference to an object group of interface `IT_LoadBalancing::ObjectGroup` that uses the desired selection algorithm.
4. Add application objects to the newly created object group by calling `add_member()` on it.
5. Bind a name to the object group by calling `bind_object_group()` on the naming context object created in step 1.

When you create the object group, you must supply a group identifier. This identifier is a string value that is unique among other object groups.

Similarly, when you add a member to the object group, you must supply a reference to the object and a corresponding member identifier. This identifier is a string value that must be unique within the object group.

In both cases, you decide the format of the identifier string. Orbix does not interpret these identifiers.

---

**Add objects to an existing object group**

Before you add objects to an existing object group, you must get a reference to the corresponding `IT_LoadBalancing::ObjectGroup` object. You can do this by using either the group identifier or the name that is bound to the object group. This section uses the group identifier.

To add objects to an existing object group:

1. Get a reference to a naming context such as the initial naming context.
2. Narrow the reference to `IT_NamingContextExt`.
3. Call `og_factory()` on the naming context object. This returns a reference to an `ObjectGroupFactory` object.
4. Call `find_group()` on the object group factory, passing the identifier for the group as a parameter. This returns a reference to the object group.
5. Add application objects to the object group by calling `add_member()` on it.

---

**Remove objects from an object group**

Removing an object from a group is straightforward if you know the object group identifier and the member identifier for the object:

1. Get a reference to a naming context such as the initial naming context and narrow to `IT_NamingContextExt`.
2. Call `og_factory()` on the naming context object. This returns a reference to an `ObjectGroupFactory` object.
3. On the object group factory, call `find_group()`, passing the identifier for the target object group as a parameter. This operation returns a reference to the object group.
4. Call `remove_member()` on the object group to remove the required object from the group. You must specify the member identifier for the object as a parameter to this operation.

If you already have a reference to the object group, the first three steps are unnecessary.

---

**Remove an object group**

To remove an object group for which you have no reference:

1. Call `unbind()` on the initial naming context to unbind the name associated with the object group.

2. Call `og_factory()` on the initial naming context object. This returns a reference to an `ObjectGroupFactory` object.
3. Call `find_group()` on the object group factory, passing the identifier for the target object group as a parameter. This operation returns a reference to the object group.
4. Call `destroy()` on the object group to remove it from the naming service.

If you already have a reference to the target object group, steps **2** and **3** are unnecessary.

---

### Set member load values

In an object group that uses active load balancing, each object group member is assigned a load value. The naming service satisfies client `resolve()` invocations by returning references to members with the lowest load values.

A member's default load value can be set administratively through the configuration variable `pluginsnaming:lb_default_initial_load`.

Thereafter, load counts should be updated with periodic calls to `ObjectGroup::update_member_load()`. `itadm` in provides an equivalent command, `nsog update_member_load`, in cases where manual intervention is required, or scripting is feasible.

You should also set or modify member timeouts with

`ObjectGroup::set_member_timeout()` or with `itadm` in `nsog`

`set_member_timeout`. You can configure default timeout values with the configuration variable `pluginsnaming:lb_default_load_timeout`. If an object's load value is not updated within its timeout interval, its object reference becomes unavailable to client `resolve()` invocations. This typically happens because the object itself or an associated process is no longer running, and therefore cannot update the object's load value.

A member reference can be made available again to client `resolve()` invocations by resetting its load value with

`ObjectGroup::update_member_load()` or `itadm` in `nsog`


`update_member_load`. In general, an object's timeout should be set to an interval greater than the frequency of load count updates.

## Load Balancing Example

This section uses a simple stock market system to show how to use object groups in CORBA applications. In this example, a CORBA object has access to all current stock prices. Clients request stock prices from this CORBA object and display those prices to the end user.

A realistic stock market application needs to make available many stock prices, and provide many clients with price updates immediately. Given such a high processing load, one CORBA object might be unable to satisfy client requirements. You can solve this problem by replicating the CORBA object, invisibly to the client, through object groups.

Figure 31 shows the architecture for the stock market system, where a single server creates two CORBA objects from the same interface. These objects process client requests for stock price information.



**Figure 31:** Architecture of the stock market example

## Defining the IDL for the application

The IDL for the load balancing example consists of a single interface `StockMarketFeed`, which is defined in module `ObjectGroupDemo`:

```
//IDL
module ObjectGroupDemo
{
 exception StockSymbolNotFound{};
 interface StockMarketFeed
 {
 double read_stock (in string stock_name)
 raises(StockSymbolNotFound);
 };
};
```

`StockMarketFeed` has one operation, `read_stock()`. This operation returns the current price of the stock associated with string identifier `stock_name`, which identifies the desired stock.

## Creating an Object Group and Adding Objects

After you define the IDL, you can implement the interfaces. Using object groups has no effect on how you do this, so this section assumes that you define class `StockMarketFeedServant`, which implements interface `StockMarketFeed`.

After you implement the IDL interfaces, you develop a server program that contains and manages implementation objects. The application can have one or more servers that perform these tasks:

- Creates two `StockMarketFeed` implementation objects.
- Creates an object group in the naming service.
- Adds the implementation objects to this group.

The server's `main()` routine can be written as follows:

### Example 54: Load balancing server

```
include <stdlib.h>
include <string.h>
include <iostream.h>
include <omg/ORB.h>
include <omg/PortableServer.h>
include <it_ts/tem_ination_handler.h>
include <orbkit/naming.h>
include "stock_ih"

static CORBA::ORB_var global_orb = CORBA::ORB::_nil();
static PortableServer::POA_var the_poa;

//Needed in global scope so its available to
tem_ination_handler();
IT_LoadBalancing::ObjectGroup_var rg_var;
IT_Naming::IT_NamingContextExt_var it_ins_var;
CosNaming::Name_var nm;
char id1[100], id2[100];
```

**Example 54:** *Load balancing server*

```

static void
main_handler(long sig)
{
 try
 {
 cout << "Removing members: " << id1 << " and "
 << id2 << endl;
 mgr_var->remove_members(id1);
 mgr_var->remove_members(id2);
 }
 catch (...)
 {
 cerr << "Could not remove members." << endl;
 }

 if (LoadBalancing::MembersList_var.members()
 mgr_var->members());
 if (members->length() == 0) //Last one to remove members
 {
 try
 {
 cout << "Unbinding object group..." << endl;
 itns_var->unbind(m);
 cout << "Destroying group..." << endl;
 mgr_var->destroy();
 }
 catch (...)
 {
 cerr << "Unbind/destroy failed." << endl;
 }
 }
 cout << "Shutting down the ORB." << endl;
 global_orb->shutdown(0);
}

```

**Example 54:** *Load balancing server*

```

int
main(
 int argc,
 char* argv[]
)
{
 if (argc != 2)
 {
 cerr << "Usage: ./server < name > " << endl;
 return 1;
 }

 CORBA::String_var server_name = CORBA::string_dup(argv[1]);

 try
 {
 global_orb = CORBA::ORB_init(argc, argv);
 }
 catch (CORBA::Exception &ex)
 {
 cerr << "Could not initialize the ORB." << endl;
 cerr << "Exception info: " << ex << endl;
 return 1;
 }
 IT_TerminationHandler::set_signal_handler(
 termination_handler);

 // Initialize the POA and POA Manager:
 //
 PortableServer::POA_manager_var poa_manager;
 try
 {
 CORBA::Object_var poa_obj =
 global_orb->resolve_initial_references("RootPOA");
 the_poa = PortableServer::POA::narrow(poa_obj);
 poa_manager = the_poa->the_POA_manager();
 }
 catch (CORBA::Exception &ex)
 {
 cerr << "Could not obtain the RootPOA or the POA manager."
 << endl;
 cerr << "Exception info: " << ex << endl;
 return 1;
 }
}

```

**Example 54:** *Load balancing server*

```

1 //Create 2 StockMarketFeed objects < server_name> RR_Member1
//and< server_name> RR_Member2.
strcpy(id1,server_name.in());
strcpy(id2,server_name.in());
strcpy(id1,"");
strcpy(id2,"");
StockServantFeedServant *stk_svt1 =
 new StockServantFeedServant(id1);
StockServantFeedServant *stk_svt2 =
 new StockServantFeedServant(id2);

2 //Resolve naming service and narrow to the interface with
//DNA
//load balancing extensions, and get the object group
//factory
CORBA::Object_var ins_obj;
IT_LoadBalancing::ObjectGroupFactory_var ogf_var;
try
{
 ins_obj=

3 global_obj-> resolve_initial_references("NameService");
 it_ins_var=
 IT_Naming::IT_NamingContextExt::_narrow(ins_obj);
 ogf_var= it_ins_var-> og_factory();
}
catch (CORBA::Exception &ex)
{
 cerr<< "Could not obtain or_narrow() reference to "
 << "IT_Naming::IT_NamingContextExt "<< endl
 << "interface. Is the Naming Service running?"<< endl;
 cerr<< "Exception info: "<< ex<< endl;
 return 1;
}

//Create a round robin object group and bind it in the
//naming service
CORBA::String_var rr_id_str=
 CORBA::string_dup("StockFeedGroup");
try
{

```

**Example 54:** *Load balancing server*

```

4 rr_obj_var= ogf_var-> create_round_robin(rr_id_str);
 nm = it_ins_var-> to_name("StockSvc");
5 it_ins_var-> bind_object_group(nm, rr_obj_var);
 }
 catch (...)
 {
 //OK: assume other server created object group and
 //bound it in NS
 rr_obj_var= ogf_var-> find_group(rr_id_str);
 }

6 //Add the StockMarketFeed objects to the ObjectGroup:
 try
 {
 IT_LoadBalancing::Member member_info;

 member_info.id = CORBA::string_dup(id1);
 member_info.obj= stk_svr1-> _this();
 rr_obj_var-> add_member(member_info);

 member_info.id = CORBA::string_dup(id2);
 member_info.obj= stk_svr2-> _this();
 rr_obj_var-> add_member(member_info);
 }

 catch (CORBA::Exception &ex)
 {
 cerr<< "Could not add members "<< id1 << ", "
 << id2 << endl;
 cerr<< "Exception info: "<< ex<< endl;
 return 1;
 }

 //Start accepting requests
 try
 {
 poa_manager-> activate();
 cout<< "Server ready..."<< endl;

```

**Example 54:** *Load balancing server*

```

7 gbbal_orb-> run();
 }
 catch (CORBA::Exception &ex)
 {
 cerr<< "Could not activate the POAM anager,
 ororb-> run() failed."
 << endl;
 cerr<< "Exception info: "<< ex<< endl;
 return 1;
 }
 return 0;
}

```

This server executes as follows:

1. Instantiates two `StockServantFeedServant` servants that implement the `StockMarketFeed` interface.
2. Obtains a reference to the initial naming context and narrows it to `IT_Naming::IT_NamingContextExt`.
3. Obtains an object group factory by calling `og_factory()` on the naming context.
4. Calls `create_round_robin()` on the object group factory to create a new group with the specified identifier. `create_round_robin()` returns a new object group in which objects are selected on a round-robin basis.
5. Calls `bind_object_group()` on the naming context and binds a specified naming service name to this group. When a client resolves this name, it receives a reference to one of the group's member objects, selected by the naming service in accordance with the group selection algorithm.

The enclosing `try` block should allow for the possibility that the group already exists, where `bind_object_group()` throws an exception of `CosNaming::NamingContext::AlreadyBound`. In this case, the `catch` clause calls `find_group()` in order to obtain the desired object group. `find_group()` is also useful in a distributed system, where objects must be added to an existing object group.

6. Activates two `StockMarketFeed` objects in the POA and adds them as members to the object group:
  - ◆ The server creates an IDL `struct` of type `IF_LoadBalancing::member`, and initializes its two members: a string that identifies the object within the group; and a `StockMarketFeed` object reference, created by invoking `_this()` on each servant.
  - ◆ The server adds the new member to the object group by calling `add_member()`.
7. Prepares to receive client requests by calling `run()` on the ORB.

## Accessing Objects from a Client

All objects in an object group provide the same service to clients. A client that resolves a name in the naming service does not know whether the name is bound to an object group or a single object. The client receives a reference to one object only. A client program resolves an object group name just as it resolves a name bound to one object, using standard CORBA-compliant interfaces.

For example, the stock market client's `main()` routine might look like this:

### Example 55: Accessing objects from an object group

```
#include <iostream.h>
#include <omg/ORB.h>
#include <orbix/naming.h>
#include "stock_demo.h"

static CORBA::ORB_var global_orb = CORBA::ORB::_nil();

int
main(
 int argc,
 char*argv[]
)
{
 if (argc != 2) {
 cerr << "Usage: ./client <stock_symbol> " << endl;
 return 1;
 }

 CosNaming::NamingContextExt_var ins;

 try {
 global_orb = CORBA::ORB_init(argc, argv);

 CORBA::Object_var ins_obj =

 global_orb->resolve_initial_references("NameService");
 ins = CosNaming::NamingContextExt::narrow(ins_obj);
 }
}
```

**Example 55:** *Accessing objects from an object group*

```

catch (CORBA::Exception &ex){
 cerr<< "Cannot resolve/narrow the NamingService DR."
 << endl;
 cerr<< "Exception info:"<< ex<< endl;
 return 1;
}

StockDemo::StockMarketFeed_var stk_ref;
try {
 CORBA::Object_var stk_obj= ins-> resolve_str("StockSvc");
 stk_ref= StockDemo::StockMarketFeed::narrow(stk_obj);
}
catch (CORBA::Exception &ex) {
 cerr<< "Could not resolve/narrow the stock_svc DR from "
 << "the Naming Service."<< endl;
 cerr<< "Exception info:"<< ex<< endl;
 return 1;
}

double cur_price;

try {
 cur_price = stk_ref-> read_stock(argv[1]);
}
catch (StockDemo::StockSymbolNotFound &ex) {
 cerr<< "Stock symbol not found:"<< argv[1]<< endl;
 cerr<< "Try another stock symbol."<< endl;
 return 1;
}
catch (CORBA::Exception &ex) {
 cerr<< "Exception received:"<< ex<< endl;
 return 1;
}

cout<< argv[1]<< " stock price is "<< cur_price<< endl;
return 0;
}

```

# Persistent State Service

*The persistent state service (PSS) is a CORBA service for building CORBA servers that access persistent data.*

---

## Overview

PSS is tightly integrated with the IDL type system and the object transaction service (OTS). Orbix PSS implements the standard `CosPersistentState` module, and adds proprietary extensions in the `tr_PSS` module. PSS's close integration with OTS facilitates the development of portable applications that offer transactional access to persistent data such as a database system.

Writing a CORBA application that uses PSS is a three-step process:

- Define the data in PSDL (persistent state data language), which is an extension of IDL, then run the IDL compiler on the PSDL files to generate C++ code.
  - Write a server program that uses PSS to access and manipulate persistent data.
  - Set PSS plug-in variables in the application's configuration as required.
- 

## In this chapter

This chapter discusses the following topics:

|                                           |                          |
|-------------------------------------------|--------------------------|
| <a href="#">Defining Persistent Data</a>  | <a href="#">page 540</a> |
| <a href="#">Accessing Storage Objects</a> | <a href="#">page 555</a> |
| <a href="#">Using Replication</a>         | <a href="#">page 580</a> |
| <a href="#">PSDL Language Mappings</a>    | <a href="#">page 585</a> |

---

# Defining Persistent Data

When you develop an application with PSS, you describe datastore components in the persistent state definition language—PSDL—and save these in a file with a `.psdl` extension.

PSDL is a superset of IDL. Like IDL, PSDL is a declarative language, and not a programming language. It adds new keywords but otherwise conforms to IDL syntax conventions. A PSDL file can contain any IDL construct; and any local IDL operation can accept parameters of PSDL types.

## Reserved keywords

---

The file `CosPersistentState.psdl` contains all PSDL type definitions, and is implicitly included in any PSDL specification. The following identifiers are reserved for use as PSDL keywords (asterisks indicate keywords reserved for use in future PSS implementations). Avoid using any of the following keywords as user-defined identifiers:

```
as*
catalog*
factory
implementations
key
of
primary
provides*
ref
scope*
storagehome
storagetype
stores*
strong*
```

## Datastore Model

PSDL contains several constructs that you use to describe datastore components. These include:

- `storage_type` describes how data is organized in storage objects of that type.
- `storage_home` describes a container for storage objects. Each storage home is defined by a storage type and can only contain storage objects of that type. Storage homes are themselves contained by a datastore, which manages the data—for example a database, a set of files, or a schema in a relational database. A datastore can contain only one storage home of a given storage type.

Within a datastore, a storage home manages its own storage objects and the storage objects of all derived storage homes.

For example, the following two PSDL files describe a simple datastore with a single `Account` storage type and its `Bank` storage home:

### Example 56: Describing datastore components

```
// in bank_demo_store_base.pddl
include< BankDemo.idl>

module BankDemoStoreBase {
 abstract storage_type AccountBase {
 state BankDemo::AccountId account_id;
 state BankDemo::CashAmount balance;
 };

 abstract storage_home BankBaseOfAccountBase {
 key account_id;
 factory create(account_id, balance);
 };
};
```

**Example 56:** *Describing datastore components*

```
//in bank_demo_store.pddl

include < BankDemoLib >
include < BankDemoStoreBase.pddl >

module BankDemoStore {
 storage type Account in plem ents BankDemoStoreBase : AccountBase
 {
 ref(account_id);
 };

 storage hom e Bank of Account
 in plem ents BankDemoStoreBase : BankBase
 {};
};
```

## Abstract Types and Implementations

In the PSDL definitions shown previously, abstract types and their implementations are defined separately in two files:

- `BankDem oStoreBase.pddl` file defines the abstract storage type `AccountBase` and abstract storage home `BankBase`. Abstract storage types and abstract storage homes are abstract specifications, like IDL interfaces.
- `BankDem oStore.pddl` defines the storage type and storage home implementations for `AccountBase` and `BankBase` in `AccountStorage` type and `Bank` storage home, respectively.

A storage type implements one or more abstract storage types. Similarly, a storage home can implement any number of abstract storage homes. By differentiating abstract types and their implementations, it is possible to generate application code that is independent of any PSS implementation. Thus, it is possible to switch from one implementation to another one without recompiling and relinking.

Given the separation between abstract types and their implementations, the IDL compiler provides two switches for processing abstract and concrete definitions:

**-psdl** compiles abstract definitions. For example:

```
idl-psdl bank_dem o_store_base.pddl
```

The IDL compiler generates a C++ abstract base class for each `abstract storagetype` and `abstract storagehome` that is defined in this file.

**-pss\_r** generates C++ code that maps concrete PSDL constructs to relational and relational-like database back-end drivers. For example, given the command:

```
idl-pss_r bank_dem o_store.pddl
```

The IDL compiler generates C++ classes for each `storagetype` and `storagehome` that is defined in this file.

**Note:** If you maintain all PSDL code in a single file, you should compile it only with the `-pss_r` switch.

## Defining Storage Objects

A storage object can have both state and behavior. A storage object's abstract storage type defines both with state members and operations, respectively.

### Syntax

The syntax for an abstract storage type definition is similar to the syntax for an IDL interface; unlike an interface, however, an abstract storage type definition cannot contain constants or type definitions.

You define an abstract storage type with this syntax:

#### Example 57: Syntax for defining an abstract storage type

```
abstract storageType abstract-storage-type-name
 [:base-abstract-storage-type [, ...]
 {
 [operation-spec;] ...
 [state-member-spec;] ...
 };
```

For example:

```
abstract storageType AccountBase {
 state BankDem o:AccountId account_id;
 state BankDem o:CashAmount balance;
};
```

The following sections discuss syntax components in greater detail.

**Inheritance:** As with interfaces, abstract storage types support multiple inheritance from base abstract storage types, including diamond-shape inheritance. It is illegal to inherit two members (state or operation) with the same name.

**State members:** A storage object's state members describe the object's data; you can qualify a state member with the `readonly` keyword. You define a state member with the following syntax:

```
[readonly] state type-spec member-name ;
```

For each state member, the C++ mapping provides accessor functions that get and set the state member's value (see page 593).

A state member's type can be any IDL type, or an abstract storage type reference.

**Operations:** Operations in an abstract storage type are defined in the same way as in IDL interfaces. Parameters can be any valid IDL parameter type or abstract storage type reference.

## Inherited StorageObject operations

All abstract storagetypes implicitly inherit from

`CosPersistentState:StorageObject`

```
module CosPersistentState {
 // ...
 native StorageObjectBase;

 abstract storagetype StorageObject {
 void destroy_object();
 boolean object_exists();
 Pid get_pid();
 ShortPid get_short_pid();
 StorageHomeBase get_storage_home();
 };
};
```

You can invoke StorageObject operations on any incarnation of a storage object; they are applied to the storage object itself:

**destroy\_object()** destroys the storage object.

**object\_exists()** returns true if the incarnation represents an actual storage object.

**get\_pid()** and **get\_short\_pid()** return the storage object's `pid` and `short-pid`, respectively.

**get\_storage\_home()** returns the storage home instance that manages the target storage object instance.

## Forward declarations

As with IDL interface definitions, PSDL can contain forward declarations of abstract storage types. The actual definition must follow later in the PSDL specification.

## Defining Storage Homes

You define an abstract storage home with an `abstract storagehome` definition:

```
abstract storagehome storagehome-name of abstract-storage-type
{
 [key-specification]
 [factory-operation-name (state-member[,...]);]
};
```

For example, the following PSDL defines abstract storage home `BankBase` of storage type `AccountBase`:

### Example 58: Defining an abstract storage home

```
abstract storagehome BankBase of AccountBase
{
 key account_id;
 factory create(account_id, balance);
};
```

A storage home lacks state but it can have behavior, which is described by operations that are defined in its abstract storage homes. For example, you locate and create a storage object by calling operations on the storage home where this object is stored.

### Inheritance from interface `StorageHomeBase`

All storage home instances implicitly derive from local interface `CosPersistentState::StorageHomeBase`:

```
module CosPersistentState {
 exception NotFound {};
 native StorageObjectBase;

 // ...
 local interface StorageHomeBase {

 StorageObjectBase
 find_by_short_pid(
 in ShortPid short_pid
) raises (NotFound);
 };
};
```

`find_by_short_pid()` looks for a storage object with the given short pid in the target storage home. If the search fails, the operation raises exception `CosPersistentState::NotFound`.

---

## Keys

An abstract storage home can define one key. A key is composed from one or more state members that belong to the storage home's abstract storage type, either directly or through inheritance. This key gives the storage home a unique identifier for the storage objects that it manages.

Two IDL types are not valid for use as key members: `valuetype` and `struct`.

A key declaration implicitly declares a pair of finder operations; for more information, [see page 548](#).

---

## Simple Keys

A simple key is composed of a single state member. You declare a simple key as follows:

```
key key-name (state-member);
```

For example, the PSDL shown earlier defines abstract storage home `BankBase` for storage objects of abstract type `AccountBase`. This definition can use state member `account_id` to define a simple key as follows:

```
key accno(account_id);
```

If the key's name is the same as its state member, you can declare it in this abbreviated form:

```
key account_id;
```

---

## Composite Keys

A composite key is composed of multiple state members. You declare a composite key as follows:

```
key key-name (state-member, state-member[...])
```

A composite key declaration must specify a key name. The types of all state members must be comparable. The following types are comparable:

- integral types: `octet`, `short`, `unsigned short`, `long`, `unsigned long`, `long long`, `unsigned long long`
- fixed types
- `char`, `wchar`, `string`, `wstring`
- `sequence< octet >`
- `struct` with only comparable members

## Finder operations

A key declaration is equivalent to the declaration of two PSDL finder operations that use a given key to search for a storage object among the storage objects that are managed directly or indirectly by the target storage home:

**find\_by\_key\_name()** returns an incarnation of the abstract storage home's abstract storage type:

```
abstract-storage-type find_by_key_name(parameter-list)
 raises (CosPersistentState:NotFound);
```

**find\_ref\_by\_key\_name()** returns a reference to this storage object:

```
ref< abstract-storage-type > find_ref_by_key_name(parameter-list);
```

Both operations take a *parameter-list* that is composed of *n* parameters that correspond to each state member in the key declaration, listed in the same order. If a storage object with the given key is not found, `find_by_key_name()` raises the `CosPersistentState:NotFound` exception, and `find_ref_by_key_name()` returns a NULL reference.

For example, given the following abstract storage type and storage home definitions:

```
abstract-storage-type AccountBase {
 state BankDem o:AccountId account_id;
 state BankDem o:CashAmount balance;
};

abstract-storage-home Bank of AccountBase {
 key accno(account_id);
 // ...
};
```

The `accno` key declaration implicitly yields these two PSDL operations:

```
Account find_by_accno(in BankDem o:AccountId)
 raises (CosPersistentState:NotFound);

ref< Account > find_ref_by_accno(in BankDem o:AccountId);
```

Finder operations are polymorphic. For example, the `find_by_accno` operation can return a `CheckingAccount` that is derived from `Account`

## Operations

---

Each parameter of a local operation can be of a valid IDL parameter type, or of an abstract PSDL type.

---

## Factory operations

In the PSDL shown earlier, abstract storage home `BankBase` is defined with the `factory create` operation. This operation provides a way to create `Account` objects in a bank, given values for `account_id` and `balance`.

```
abstract storagehome Bank of AccountBase {
 key accno(account_id);
 factory create(account_id, balance);
};
```

Each parameter that you supply to a factory create operation must be the name of a state member of the abstract storage home's abstract storage type, including inherited state members.

The definition of a factory operation is equivalent to the definition of the following operation:

```
abstract-storage-type factory-op-name(parameter-list);
```

where `parameter-list` is composed of `n` parameters that correspond to each state member in the factory operation declaration, listed in the same order.

For example, given this factory declaration:

```
abstract storagetype AccountBase {
 state BankDem o:AccountId account_id;
 state BankDem o:CashAmount balance;
};

abstract storagehome Bank of AccountBase {
 // ...
 factory create(account_id, balance);
};
```

The `create` factory declaration implicitly yields this operation, which uses conventional IDL-to-C++ mapping rules:

```
Account create(
 in BankDem o:AccountId account_id,
 in BankDem o:CashAmount balance
);
```

---

## Inheritance

An abstract storage home can inherit from one or more abstract storage homes, and support diamond-shape inheritance. The following constraints apply to a base abstract storage home:

- The base abstract storage homes must already be defined.
- The base abstract storage homes must use the same abstract storage type or base abstract storage type as the derived abstract storage home.
- An abstract storage home cannot inherit two operations with the same name.

---

## Forward declarations

As with IDL interface definitions, PSDL can contain forward declarations of abstract storage homes.

## Implementing Storage Objects

A storage type implements one or more abstract storage types, and can inherit from one other storage type. Storage type implementations are defined as follows:

**Example 59:** *Syntax for defining storage type implementations*

```
storageType storagetype-name [:storagetype-name]
 implements abstract-storagetype[,abstract-storagetype]...
{
 [state-member-spec;]...
 [ref(state-member[,state-member]...)]
};
```

The implemented abstract storage type `abstract_storagetype` must specify a previously defined abstract storage type.

### State members

A storage type can define state members; these state members supplement any state members in the abstract storage types that it implements, or that it inherits from other implementations. You define a state member with the following syntax:

```
[readonly] state type-spec member-name ;
```

### Reference representation

A storage type can define a reference representation that serves as a unique identifier for storage objects in a storage home of that storage type. A storage type without any base storage type can define a single reference representation, which is composed of one or more state members. For example:

```
storageType Account implements BankDemoStoreBase::AccountBase
{
 ref(account_id);
};
```

The state members that compose a reference representation must be defined either in:

- One of the abstract storagetypes that this storage type directly implements

- The current storage type

## Implementing Storage Homes

A storage home implements one or more previously defined abstract storage homes with this syntax:

**Example 60:** *Syntax for defining a storage home implementations*

```
storage-home storagehome-name [:storagehome-name]
 of storagetype [implements abstract-storagehome [, ...]]
 {
 [primary-key-spec];
 };
```

A storage home specification must include these elements:

- A storage type that derives from the base storage home's storage type. The storage home's storage type must implement the abstract storage type of each of the implemented abstract storage homes.
- Either inherits an existing storage home, or implements one or more existing abstract storage home.

### Inheritance

A storage home can inherit from a previously defined storage home. The following constraints apply:

- The storage type of the base storage home must be a base of the storage home's own storage type.
- Two storage homes in a storage home inheritance tree cannot have the same storage type.

For example, the following specification is not legal:

```
storagetype A { /* ... */ };
storagetype B : A { /* ... */ };
storagehome H of A {};
storagehome H2 of B : H {};
storagehome H3 of B : H {}; // error - B is already storagetype
// of another sub-storage-home of H
```

### Primary key declaration

A primary key declaration specifies a distinguished key, as implemented in relational systems. You can define a primary key in any storage home without a base storage home.

You can define a primary key in two ways:


- `primarykey key-spec`, where *key-spec* denotes a key that is declared in one of the implemented abstract storagehomes.
- `primarykeyref` tells the PSS implementation to use the state members of the reference representation as the primary key.

# Accessing Storage Objects

You access a storage object through its language-specific implementation, or storage object *incarnation*. A storage object incarnation is bound to a storage object in the datastore and provides direct access to the storage object's state. Thus, updating a storage object incarnation also updates the corresponding storage object in the datastore.

Likewise, to use a storage home, you need a programming language object, or storage home *instance*.

To access a storage object, a server first obtains a logical connection between itself and the datastore that contains this storage object's storage home. This logical connection, or *session*, can offer access to one or more datastores.



**Figure 32:** A server process uses sessions to establish a logical connection with a datastore and its contents

## Creating Transactional Sessions

PSS provides a local connector object that you use to create sessions. Because PSS is designed for use in transactional servers, Orbix provides its own session manager, which automatically creates transactional sessions that can be associated with transactions. You can also manage transactional sessions explicitly.

### Procedure

In either case, you create transactional sessions in these steps:

- 1 Get a reference to the transaction service's current object by calling `resolve_initial_references("TransactionCurrent")` on the ORB, then narrow the returned reference to a `CosTransactions:Current` object.
- 2 Get a reference to a connector object by calling `resolve_initial_references("PSS")` on the ORB, then narrow the returned reference to a connector object:
  - `IT_PSS:Connector` object to use an Orbix `SessionManager`.
  - `CosPersistentState:Connector` to use standard PSS transactional sessions.
- 3 Create storage object and storage home factories and register them with a `Connector` object. This allows PSS to create storage object incarnations and storage home instances in the server process, and thereby enable access to the corresponding datastore objects.

For each PSDL storage home and storage object implementation, the IDL compiler, using the `-pss_r` switch, generates a factory creation and registration operation. For example, given a PSDL storage home definition of `BankDem oStore:Bank`, you can instantiate its storage home factory as follows:

```
CosPersistentState::StorageHomeFactory* bank_factory = new
 IT_PSS_StorageHomeFactory(BankDem oStore:Bank);
```

- 
- 4 After registering factories with the connector, the connector assumes ownership of the factories. The server code should call `_rem ove_ref()` on each factory object reference to avoid memory leaks.
- 
- 5 Create transactional sessions. You can do this in two ways:
    - Create an Orbix `SessionM anager`, which creates and manages the desired number of sessions.
    - Create standard PSS `TransactionalSession` objects.
- 
- 6 Associate sessions with transactions. How you do so depends on whether you create sessions with a `SessionM anager` or with standard PSS operations:
    - You associate an Orbix `SessionManager`'s sessions with transactions through `IT_PSS::TxSessionAssociation` objects.
    - You associate standard transactional sessions with transactions through the `TransactionalSession` object's `start()` operation.

[Example 61](#) shows how a server can implement steps 1-4. This code is valid whether you use an Orbix `SessionManager` or a standard PSS `TransactionalSession`.

**Example 61:** *Creating a transactional session*

```
int
main(int argc, char** argv)
{
 // ...
 try
 {
 // initialise the ORB as configured in the MR

 cout << "initializing the ORB" << endl;
 global_orb = CORBA::ORB_init(argc, argv, "dem cos.pss.bank");

 CORBA::Object_var obj =
 global_orb->resolve_initial_references("TransactionCurrent");

 CosTransactions::Current_var tx_current =
 IT_PSS::Connector::narrow(obj);
 assert(CORBA::is_nil(tx_current));
 }
}
```

**Example 61:** *Creating a transactional session*

```

CORBA::Object_var obj =
 global_obj->resolve_initial_references("PSS");

IT_PSS::connector_var connector =
 IT_PSS::Connector::narrow(obj);
assert(CORBA::is_nil(connector));

// Create and register storage object and
// storage home factories

CosPersistentState::StorageObjectFactory *acct_factory = new
 IT_PSS::StorageObjectFactory< BankDem oStore::Account> ;

CosPersistentState::StorageHomeFactory *bank_factory = new
 IT_PSS::StorageHomeFactory< BankDem oStore::Bank> ;

connector->register_storage_object_factory(
 BankDem oStore::tc_Account->id(),
 acct_factory);

connector->register_storage_home_factory(
 BankDem oStore::tc_Bank->id(),
 bank_factory);

// after registration, connector owns factory objects,
// so remove factory references from memory

acct_factory->_remove_ref();
bank_factory->_remove_ref();

// ...
// continuation depends on whether you use Orbix
// SessionManager
// or PSS TransactionalSessions
// ...

```

The sections that follow describe the different ways to continue this code, depending on whether you use a SessionManager or standard PSS transactional sessions.

|                                 |          |
|---------------------------------|----------|
| Using the SessionManager        | page 559 |
| Managing Transactional Sessions | page 566 |

---

## Using the SessionManager

After you create and register storage object and storage home factories, you create a SessionManager and associate transactions with its sessions as follows:

- 
- 1 Set a list of parameters for the SessionManager to be created, in a `CosPersistentState::ParameterList`. At a minimum, the parameter list specifies the `Resource` that sessions connect to—for example, a Berkeley DB environment name. It can also specify the number of sessions that are initially created for the SessionManager, and whether to add sessions when all sessions are busy with requests. [Table 22 on page 561](#) describes all parameter settings.

---

  - 2 Create a SessionManager by calling `it_create_session_manager()` on the Orbix connector. The SessionManager always creates at least two transactional sessions:
    - A shared read-only session for read-only non-transactional requests.
    - A pool of read-write serializable transactional sessions for write requests, and for any request that is executed in the context of a distributed transaction.

---

  - 3 Create an association object `IT_PSS::TxSessionAssociation` to associate the SessionManager and the transaction.

---

  - 4 Use the association object to perform transactional operations on the datastore's storage objects.

[Example 62](#) implements these steps:

### Example 62: Creating a SessionManager

```
//Create SessionManager with one read-only read-committed
//multi-threaded transactional session and one read-write
//serializable single-threaded transactional session
```

**Example 62:** *Creating a SessionManager*

```

CosPersistentState:Param eterList param eters(2);
param eters.length(2);
param eters[0].name = CORBA::string_dup("to");
param eters[0].val <= CORBA::Any::from_string("bank", true);
param eters[1].name = CORBA::string_dup("single writer");
param eters[1].val <= CORBA::Any::from_boolean(true);

IT_PSS::SessionManager var session_mgr =
 connector-> it_create_session_manager(param eters);

//use the shared read-only session
IT_PSS::TxSessionAssociation association(
 session_mgr.in(),
 CosPersistentState::READ_ONLY,
 CosTransactions::Coordinator::_nil());

//show balances in all accounts
//The query API is proprietary; it is similar to JDBC

IT_PSS::Statement var statement =
 association.get_session_nc()-> it_create_statement();

IT_PSS::ResultSet var result_set = statement-> execute_query(
 "select ref(h) from PSDL:BankDemoStore:Bank:1.0.h");

cout << "Listing database: account id, balance" << endl;
BankDemoStore:AccountBaseRef account_ref;
CORBA::Any var ref_as_any;
while (result_set-> next())
{
 ref_as_any = result_set-> get(1);
 CORBA::Boolean ok = (ref_as_any >= account_ref);
 assert(ok);
 cout << "
 << account_ref-> account_id()
 << ", $" << account_ref-> balance()
 << endl;
}

result_set-> cbse();

association.suspend();
// ...
return 0;
}

```

## Setting SessionManager parameters

You supply parameters to `it_create_session_manager()` through a `CosPersistentState:ParameterList`, which is defined as a sequence of `Parameter` types. Each `Parameter` is a struct with `name` and `val` members:

- `name` is a string that denotes the parameter type.
- `val` is an `Any` that sets the value of `name`.

The parameter list must specify the `Resource` that sessions connect to—for example, an ODBC datasource name or Oracle database name. [Table 22](#) describes all parameter settings

**Table 22:** *SessionManager parameters*

| Parameter name             | Type                 | Description                                                                                                                                                                                                                                                                                              |
|----------------------------|----------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>to</code>            | <code>string</code>  | Identifies the datastore to connect to. For example with PSS/DB, it will be an environment name.<br>You must set this parameter.                                                                                                                                                                         |
| <code>rw pool.size</code>  | <code>long</code>    | Initial size of the pool of read-write transactional sessions managed by the session manager. The value must be between 1 and 1000, inclusive.<br>The default value is 1.                                                                                                                                |
| <code>grow pool</code>     | <code>boolean</code> | If set to <code>TRUE</code> , specifies to create a new session to process a new request when all read-write transactional sessions are busy. A value of <code>FALSE</code> , specifies to wait until a read-write transactional session becomes available.<br>The default value is <code>FALSE</code> . |
| <code>single writer</code> | <code>boolean</code> | Can be set to <code>TRUE</code> only if <code>rw pool.size</code> is 1. In this case, specifies to create a single read-write transactional session that allows only one writer at a time.<br>The default value is <code>FALSE</code> .                                                                  |
| <code>master</code>        | <code>long</code>    | The IOR of the master instance of a replica. This parameter is only used when creating a replica.                                                                                                                                                                                                        |

## Creating a SessionManager

You create a SessionManager by calling `it_create_session_manager()` on the Orbix connector. `it_create_session_manager()` takes a single `ParameterList` argument (see page 561), and is defined in the `IT_PSS::Connector` interface as follows:

```
module IT_PSS {
 // ...
 local interface Connector : CosPersistentState::Connector
 {
 SessionManager
 it_create_session_manager(
 in CosPersistentState::ParameterList parameters);
 };
}
```

## Associating a transaction with a session

The association object `IT_PSS::TxSessionAssociation` associates a transaction with a session that is managed by the SessionManager. You create an association object by supplying it with a SessionManager and the access mode. The `CosPersistentState` module defines two `AccessMode` constants: `READ_ONLY` and `READ_WRITE`.

The `IT_PSS::TxSessionAssociation` interface defines two constructors for a `TxSessionAssociation` object:

### Example 63: TxSessionAssociation constructors

```
namespace IT_PSS {
 //...
 class TxSessionAssociation {
 public:

 TxSessionAssociation(
 SessionManager_ptr session_mgr,
 CosPersistentState::AccessMode access_mode
) throw (CORBA::SystemException);
 };
}
```

**Example 63:** *TxSessionAssociation* constructors

```

TxSessionAssociation(
 SessionManager_ptr session_mgr,
 CosPersistentState::AccessMode access_mode,
 CosTransactions::Coordinator_ptr tx_coordinator
) throw (CORBA::SystemException);

~TxSessionAssociation()
throw (CORBA::SystemException);
// ...
};

```

The first constructor supplies only the session manager and access mode. This constructor uses the default coordinator object that is associated with the current transaction (`CosTransactions::Current`). The second constructor lets you explicitly specify a coordinator; or to specify no coordinator by supplying `_nil()`. If you specify `_nil()`, the association uses the shared transaction that is associated with the shared read-only session; therefore, the access mode must be `READ_ONLY`.

A new association is initially in an active state—that is, it allows transactions to use the session to access storage objects. You can change the association's state by calling `suspend()` or `end()` operations on it (see [page 564](#)).

**Association object operations**

An association object has several operations that are defined as follows:

**Example 64:** *Association object operations*

```

namespace IT_PSS {
// ...
class TxSessionAssociation{
public:
// ...
TransactionalSession_ptr get_session_nc()
const throw ();

CosTransactions::Coordinator_ptr get_tx_coordinator_nc()
const throw ();

void suspend()
throw (CORBA::SystemException);

```

**Example 64:** *Association object operations*

```

void end(CORBA::Boolean success = true)
 throw (CORBA::SystemException);
};
};

```

**get\_session\_nc()** returns the session for this association object. After you obtain the session, you can access storage objects in the datastore that this session connects to.

**get\_tx\_coordinator\_nc()** returns the coordinator of this association's transaction.

**suspend()** suspends a session-Resource association. This operation can raise two exceptions:

- **PERSIST\_STORE:** there is no active association
- **INVALID\_TRANSACTION:** The given transaction does not match the transaction of the Resource actively associated with this session.

**end()** terminates a session-Resource association. The end operation raises the standard exception **PERSIST\_STORE** if there is no associated Resource, and **INVALID\_TRANSACTION** if the given transaction does not match the transaction of the Resource associated with this session. If the success parameter is **FALSE**, the Resource is rolled back immediately. Like `refresh()`, `end()` invalidates direct references to incarnations' data members.

A Resource can be prepared or committed in one phase only when it is not actively associated with any session. If asked to prepare or commit in one phase when still in use, the Resource rolls back. A Resource (provided by the PSS implementation) ends any session-Resource association in which it is involved when it is prepared, committed in one phase, or rolled back.

### Using an association to access storage objects

You can use an association object to access the data in storage objects. The example shown earlier (see page 559) queries the data in all Account storage objects in the Bank storage home. In order to obtain data from a given storage object, you typically follow this procedure:

1. Create an association between a session manager and the current transaction.

2. Call `get_session_nc()` on the association to retrieve the session manager's current session.
3. Call `find_storage_home()` on the session to retrieve the storage home.
4. Use the storage home to access the storage objects that it maintains.

The methods used to retrieve and access the storage objects are left up to the developer to implement. The most basic way is to use the `find_by_pid()` and `find_by_short_pid()` operations provided by the API. This does not stop the developer from providing implementation specific methods of to locate and manipulate storage objects.

---

## Managing Transactional Sessions

The previous section shows how to use the Orbix SessionManager to create and manage transactional sessions. The Orbix SessionManager is built on top of the `CosPersistentState::TransactionalSession` interface. You can use this interface to manage transactional sessions directly.

**Note:** PSS also provides the `CosPersistentState::Session` interface to manage basic sessions for file-like access. This interface offers only non-transactional functionality whose usefulness is limited to simple applications; therefore, it lies outside the scope of this discussion, except insofar as its methods are inherited by `CosPersistentState::TransactionalSession`.

After you create and register storage object and storage home factories, you create a session and associate transactions with it as follows:

1. Create a `TransactionalSession` by calling `create_transactional_session()` on a `Connector` object.
2. Activate the transactional session by calling `start()` on it. The transactional session creates a new `CosTransactions::Resource`, and registers it with the transaction.  
For more information about `CosTransactions::Resource` objects, see the *CORBA OTS Programmers Guide*.
3. Use the session-`Resource` association to perform transactional operations on the datastore's storage objects.

---

### Creating a transactional session

Sessions are created through `Connector` objects. A `Connector` is a local object that represents a given PSS implementation.

Each ORB-implementation provides a single instance of the local `Connector` interface, which you obtain through `resolve_initial_references("PSS")` then narrowing the returned reference to a `CosPersistentState::Connector` object. You use the `Connector` object to create a `TransactionalSession` object by calling

`create_transactional_session()` on it:

**Example 65:** *Creating a TransactionalSession object*

```
module CosPersistentState {
 // ...

 //forward declarations
 local interface TransactionalSession;

 // ...

 struct Parameter
 {
 string name;
 anyval;
 };

 typedef sequence< Parameter> ParameterList;

 local interface Connector
 {

 // ...

 TransactionalSession create_transactional_session(
 in AccessMode access_mode,
 in IsolationLevel default_isolation_level,
 in EndOfAssociationCallback callback,
 in TypeId catalog_type_name,
 in ParameterList additional_parameters);
 };
 // ...
};
```

The parameters that you supply to `create_transactional_session()` define the new session's behavior:

- The access mode for all `Resource` objects to be created by the session. The `CosPersistentState` module defines two `AccessMode` constants:
  - ◆ `READ_ONLY`
  - ◆ `READ_WRITE`
- The default isolation level for all `Resource` objects to be created by the session. The `CosPersistentState` module defines four `IsolationLevel` constants:

- ◆ READ\_UNCOMMITTED
- ◆ READ\_COMMITTED
- ◆ REPEATABLE\_READ
- ◆ SERIALIZABLE
- A callback object to invoke when a `session-Resource` association ends (see page 568).
- A `ParameterList` that specifies the datastore to connect to, and optionally other session characteristics (see page 568).

**Note:** The `catalog_type_name` parameter is currently not supported. Set it to an empty string.

### End-of-association callbacks

When a `session-Resource` association ends, the session might not become available immediately. For example, if the session is implemented with an ODBC or JDBC connection, the PSS implementation needs this connection until the `Resource` is committed or rolled back.

A session pooling mechanism might want to be notified when PSS releases a session. You can do this by passing a `EndOfAssociationCallback` local object to the `Connector::create_transactional_session` operation:

```
module CosPersistentState {
 // ...
 local interface EndOfAssociationCallback {
 void released(in TransactionalSession session);
 };
};
```

### ParameterList settings

You set session parameters in a `ParameterList`, which is a sequence of `Parameter` types. Each `Parameter` is a struct with `name` and `val` members:

**name** is a string that denotes the parameter type.

**val** is an `any` that sets the value of `name`.

The parameter list must specify the `Resource` that sessions connect to—for example, a Berkeley DB environment name. [Table 23](#) describes all parameter settings


**Table 23:** *ParameterList settings for a TransactionalSession*

| Parameter name             | Type                 | Description                                                                                                                                                                                                                                                      |
|----------------------------|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>to</code>            | <code>string</code>  | Identifies the datastore to connect to. For example with PSS/DB, it will be an environment name; with PSS/ODBC a datasource name; with PSS/Oracle, an Oracle database name.<br>You must set this parameter.                                                      |
| <code>concurrent</code>    | <code>boolean</code> | If set to <code>TRUE</code> , the session can be used by multiple concurrent threads.<br>The default value is <code>FALSE</code> .                                                                                                                               |
| <code>single writer</code> | <code>boolean</code> | Can be set to <code>TRUE</code> only if this session is the only session that writes to this database. A value of <code>TRUE</code> eliminates the risk of deadlock; the cache can remain unchanged after a commit.<br>The default value is <code>FALSE</code> . |
| <code>master</code>        | <code>long</code>    | The IOR of the master instance associated with a replica. This parameter is only used when creating replicas.                                                                                                                                                    |

### Activating a transactional session

When you create a transactional session, it is initially in an inactive state—that is, the session is not associated with any `Resource`. You associate the session with a `Resource` by calling `start()` on it, supplying the name of a transaction's coordinator object ([see page 571](#)). This function associates the session with a `Resource`, and registers the `Resource` with the coordinator's transaction.

A transactional session is associated with one `Resource` object (a datastore transaction), or with no `Resource` at all. During its lifetime, a session-`Resource` association can be in one of three states—active, suspended, or ending—as shown in [Figure 33](#):



**Figure 33:** *Transactional session states*

The state members of a storage object’s incarnation are accessible only when the transactional session has an active association with a `Resource`. Typically, a `Resource` is associated with a single session for its entire lifetime. However, with some advanced database products, the same `Resource` can be associated with several sessions, possibly at the same time.

The `TransactionalSession` interface has this definition:

```

module CosPersistentState {
 // ...
 typedef short IsolationLevel;
 const IsolationLevel READ_UNCOMMITTED = 0;
 const IsolationLevel READ_COMMITTED = 1;
 const IsolationLevel REPEATABLE_READ = 2;
 const IsolationLevel SERIALIZABLE = 3;
 }

```

```

interface TransactionalSession : Session {

 readonly attribute IsolationLevel
 default_isolation_level;

 typedef short AssociationStatus;
 const AssociationStatus NO_ASSOCIATION = 0;
 const AssociationStatus ACTIVE = 1;
 const AssociationStatus SUSPENDED = 2;
 const AssociationStatus ENDING = 3;

 void start(in CosTransactions::Coordinator transaction);
 void suspend(
 in CosTransactions::Coordinator transaction
);
 void end(
 in CosTransactions::Coordinator transaction,
 in boolean success
);

 AssociationStatus get_association_status();
 CosTransactions::Coordinator get_transaction();
 IsolationLevel
 get_isolation_level_of_associated_resource();
};
};

```

## Managing a transactional session

The `TransactionalSession` interface provides a number of functions to manage a transactional session.

**start()** activates a transactional session. If the session is new, it performs these actions:

- Creates a new `Resource` and registers it with the given transaction.
- Associates itself with this `Resource`.

If the session is already associated with a `Resource` but is in suspended state, `start()` resumes it.

**suspend()** suspends a session-`Resource` association. This operation can raise two exceptions:

- `PERSIST_STORE`: there is no active association
- `INVALID_TRANSACTION`: The given transaction does not match the transaction of the `Resource` actively associated with this session.

**end()** terminates a session-Resource association. If its `success` parameter is `FALSE`, the Resource is rolled back immediately. Like `refresh()`, `end()` invalidates direct references to the data members of incarnations.

This operation can raise one of the following exceptions

- `PERSIST_STORE`: There is no associated Resource
- `INVALID_TRANSACTION`: The given transaction does not match the transaction of the Resource associated with this session

A Resource can be prepared or committed in one phase only if it is not actively associated with any session. If asked to prepare or commit in one phase when still in use, the Resource rolls back. A Resource ends any session-Resource association in which it is involved when it is prepared, committed in one phase, or rolled back.

**Note:** In XA terms, `start()` corresponds to `xa_start()` with either the `TMNOFLAGS`, `TMJOIN` or `TMRESUME` flag. `end` corresponds to `xa_end()` with the `TMSUCCESS` or the `TMFAIL` flag. `suspend` corresponds to `xa_end()` with the `TMSUSPEND` or `TMSPEND` | `TMMGRATE` flag.

**get\_association\_status()** returns the status of the association (if any) with this session. The association status can be one of these `AssociationStatus` constants:

```
NO_ASSOCIATION
ACTIVE
SUSPENDED
ENDING
```

See [“Activating a transactional session” on page 569](#) for more information about a transactional session’s different states.

**get\_transaction()** returns the coordinator of the transaction with which the Resource associated with this session is registered. `get_transaction` returns a nil object reference when the session is not associated with a Resource.

When data is accessed through a transactional session that is actively associated with a Resource, a number of undesirable phenomena can occur:

- Dirty reads: A dirty read occurs when a Resource is used to read the uncommitted state of a storage object. For example, suppose a storage object is updated using Resource 1. The updated storage object’s state

is read using `Resource 2` before `Resource 1` is committed. If `Resource 1` is rolled back, the data read with `Resource 2` is considered never to have existed.

- Nonrepeatable reads: A nonrepeatable read occurs when a `Resource` is used to read the same data twice but different data is returned by each read. For example, suppose `Resource1` is used to read the state of a storage object. `Resource2` is used to update the state of this storage object and `Resource2` is committed. If `Resource1` is used to reread the storage object's state, different data is returned.

The degree of an application's exposure to these occurrences depends on the isolation level of the `Resource`. The following isolation levels are defined:

**Table 24:** *Isolation levels*

| Isolation level               | Exposure risk                           |
|-------------------------------|-----------------------------------------|
| <code>READ_UNCOMMITTED</code> | Dirty reads and the nonrepeatable reads |
| <code>READ_COMMITTED</code>   | Only nonrepeatable reads                |
| <code>SERIALIZABLE</code>     | None                                    |

**Note:** Isolation level `REPEATABLE_READ` is reserved for future use.

**`get_isolation_level_of_associated_resource()`** returns the isolation level of the `Resource` associated with this session. If no `Resource` is associated with this session, the operation raises the standard exception `PERSIST_STORE`.

**`resource_isolation_level`** (read-only attribute) returns the isolation level of the `Resource` objects created by this session.

## Basic session management operations

The `CosPersistentState::TransactionalSession` interface inherits a number of operations (via `CosPersistentState::Session`) from the `CosPersistentState::CatalogBase` interface. `CatalogBase` operations provide access to a datastore's storage homes and storage objects; it also provides several memory-management operations:

```
module CosPersistentState {
 interface CatalogBase {
 readonly attribute AccessMode access_mode;

 StorageHomeBase
 find_storage_home(in string storage_home_type_id)
 raises (NotFound);

 StorageObjectBase
 find_by_pid(in Pid the_pid) raises (NotFound);

 void flush();
 void refresh();
 void free_all();
 void close();
 };
 // ...

 local interface Session : CatalogBase {};

 interface TransactionalSession : Session {
 // ...
 };
};
```

**find\_storage\_home()** returns a storage home instance that matches the supplied storagehome ID. If the operation cannot find a storage home, it raises a `NotFound` exception.

**find\_by\_pid()** searches for the specified storage object among the storage homes that are provided by the target session. If successful, the operation returns an incarnation of the specified storage object; otherwise, it raises the exception `NotFound`.

**flush()** writes to disk any cached modifications of storage object incarnations that are managed by this session. This operation is useful when an application creates a new storage object or updates a storage object, and the modification is not written directly to disk. In this case, you can call `flush()` to rid the cache of “dirty” data.

**refresh()** refreshes any cached storage object incarnations that are accessed by this session. This operation is liable to invalidate any direct reference to a storage object incarnation’s data member.

**free\_all()** sets to 0 the reference count of all PSDL storage objects that have been incarnated for the given session.

PSDL storage object instances are reference-counted by the application. Freeing references can be problematic for storage objects that hold references to other storage objects. For example, if storage object A holds a reference to storage object B, A’s incarnation owns a reference count of B’s incarnation. When storage objects form a cyclic graph, the corresponding instances own reference count of each other. For example, the following PSDL storage type definition contains a reference to itself:

```
abstract storagetype Person {
 readonly state string full_name;
 state ref< Person> spouse;
};
```

When a couple is formed, each Person incarnation maintains the other Person’s incarnation in memory. Therefore, the cyclic graph can never be completely released even if you correctly release all reference counts. In this case, the application must call `free_all()`.

**close()** terminates the session. When the session is closed, it is also flushed. If the session is associated with one or more transactions (see below) when `close()` is called, these transactions are marked as roll-back only.

---

## Getting a Storage Object Incarnation

After you have an active session, you use this session to get a storage home; you can obtain from this storage home incarnations of its storage objects. You can then use these incarnations to manipulate the actual storage object data.

To get a storage home, call `find_storage_home()` on the session. You narrow the result to the specific storage home type.

Call one of the following operations on the storage home to get the desired storage object incarnation:

- One of the find operations that are generated for key in that storage home. ([see page 548](#)).
- `find_by_short_pid()`

## Querying Data

Orbis PSS provides simple JDBC-like queries. You use an `IT_PSS::CatalogBase` to create a Statement. For example:

```
IT_PSS::Statement stmt = catalog->create_statement();
```

Then you execute a query that returns a result set:

### Example 66: Executing a query

```
//Gets all accounts
IT_PSS::ResultSet var_result_set
= stmt->execute_query("select ref(h) from PSDL:Bank1.0 h");
while (result_set->next())
{
CORBA::Any var_ref_as_any = result_set->get(1);
BankDem oStore:AccountRef ref;
ref_as_any > = ref;
cout << "account_id: " << ref->account_id()
<< "balance: $" << ref->balance()
<< endl;
}
result_set->close(); //optional in C++
statement->close(); //optional in C++
```

Orbis PSS supports the following form of query:

```
select ref(h) from home_type_id h
```

The alias must be `h`.

---

## Associating CORBA and Storage Objects

The simplest way to associate a CORBA object with a storage object is to bind the identity of the CORBA object (its `oid`, an octet sequence) with the identity of the storage object.

For example, to make the storage objects stored in storage home `Bank` remotely accessible, you can create for each account a CORBA object whose object ID is the account number (`account_id`).

To make such a common association easier to implement, each storage object provides two external representations of its identity as octet sequences: the `pid` and the `short_pid`:

**short\_pid** is a unique identifier within a storage home and its derived homes.

**pid** is a unique identifier within the datastore.

---

## Thread Safety

A storage object can be used like a `struct`: it is safe to read concurrently the same storage object incarnation, but concurrent writes or concurrent read/write are unsafe. This behavior assumes that a writer typically uses its own transaction in a single thread; it is rare for an application to make concurrent updates in the same transaction.

Flushing or locking a storage object is like reading this object. Discarding an object is like updating it.

A number of `CosPersistentState::Session` operations are not thread-safe and should not be called concurrently. No thread should use the target session, or any object in the target session such as a storage object incarnation or storage home, when one of the following operations is called:

```
Session::free_all()
Session::it_discard_all()
Session::refresh()
Session::cbee()
TransactionalSession::start()
TransactionalSession::suspend()
TransactionalSession::end()
```

OTS operations are thread-safe. For example one thread can call `tx_curent->rollback()` while another thread calls `start()`, `suspend()`, or `end()` on a session involved in this transaction, or while a thread is using storage objects managed by that session.

---

# Using Replication

---

## Overview

The persistent state service provides the ability to create replicated databases. This facility can be used to make persistent data more highly available and provide some load distribution.

---

## Replication model

The persistent state service implements a simple replication model where there is one master that allows both read and write access to the data and many replicas, or slaves, that only provide read access to the data. Depending on the implementation of the data server, the replicas can forward read requests on to their associated master. By implementing the server in such a way, you minimize the impact on clients wishing to access replicated data.

---

## Platform constraints

Due to limitations in Berkeley DB's backup support, the master and all its replicas must be on platforms with a common transaction log format. This means that the platforms must use the same endian format and the same data width.

---

## Replica types

The persistent state service supports two types of replicas:

**pull-style replicas** periodically call `refresh()` to receive updates from the master instance. The frequency of the call to `refresh()` is determined by the configuration variable `pull_period`. This is the default style of replica.

**push\_style replicas** are automatically updated by the master at an interval specified by the `push_update_period` configuration variable.

The type of replicas used by the persistent state service is set at configuration time by the variable `replication_model`. This value defaults to `PULL`. For more information on configuring the persistent state service, see the *CORBA Administrators Guide*.

## Creating a replica

Both the Orbix `SessionManager` interface and the OMG `TransactionalSession` interface can be used to create and manage a replica. The steps for creating a replica and associating it with a session are identical to the steps to the step for creating a default PSS datastore.

**Note:** By default, all PSS databases are masters.

The difference is in the parameter list that is used in creating the session object. To create a replica use a parameter list that contains the `master` parameter. The value of the master parameter is the IOR of the `master` instance of the PSS datastore. It can be `nil`.

### Creating a replica using the Orbix SessionManager interface

[Example 67](#) shows how to create a replica using the Orbix SessionManager:

#### **Example 67:** *Creating a replica using the SessionManager interface*

```

1 CosPersistentState::ParameterList parameters;
 parameters.Length(2);
2 parameters[1].name = CORBA::string_dup("master");
 //value for master obtained previous to this code fragment
 parameters[1].val << = master;
3 //connector was obtained in preceding examples
 IT_PSS::SessionManager var session_mgr =
 connector-> it_create_session_manager(parameters);

```

1. Create a parameter list to hold the parameters.
2. Create the `master` parameter and assign the IOR of the master to its `val` member.
3. Create a `SessionManager` by calling `it_create_session_manager` on the connector.

**Creating a replica using the TransactionalSession interface**

Example 68 shows how to create a replica using the TransactionalSession interface:

**Example 68:** *Creating a replica using the TransactionalSession interface*

```

1 CosPersistentState::ParameterList param eters;
 param eters.length(2);
2 param eters[1].name = CORBA::string_dup("m aster");
 //value form aster obtained previous to this code fragm ent
 param eters[1].val < = m aster;

3 CosPersistentState::TransactionalSession_var=
 connector-> create_transactional_session(
4 READ_ONLY,
5 SERIALIZABLE,
6 NULL,
7 NULL,
8 param eters);

```

1. Create a parameter list.
2. Create the `m aster` parameter and assign the IOR of the master to the its `val` member.
3. Create a `TransactionalSession` by calling `create_transactional_session` on the connector.
4. Set the replicas access mode to `READ_ONLY`.
5. Set the replicas isolation level to the lowest level of risk.
6. The replica has no end of association callback.
7. The `TypeId` is not implemented.
8. The parameter list is what identifies this instance as a replica.

**Starting replica datastores**

The persistent state service leaves it up to the developer to determine if replicas can start up without an active master datastore. Because the persistent state service cannot guarantee that replicas are up to date, the possibility of presenting invalid data to clients arises. Also, because replicas are read only, clients will also be unable to modify any data in the datastore.

A replica can test if its master is running by calling `IT_PSS::TransactionalSession::get_master()` after it is created. If the call returns `NULL`, then the master is unreachable or the reference used to create the replica is invalid.

### Obtaining a reference to the master instance

The `IT_PSS::TransactionalSession` interface provides the `get_master()` function to obtain the a reference to the master instance from one of its associated replicas.

If `get_master()` is called on a master instance, the call will return an object reference to itself.

`get_master()` will return `NULL` if the associated master instance is not active or if it does not exist.

Because the IOR of the master datastore is transient, this function is useful for discovering the master datastore upon start-up of a replica. For example, the server hosting the master datastore may register a persistent POA with the naming service. This POA could contain a session object that the replicas can call `get_master()` on as they come up.

### Obtaining a Replica object from a session

The `IT_PSS::TransactionalSession` interface provides the `get_replica()` function to obtain the `Replica` object associated with a session. If the session is associated with a replica instance of a persistent state datastore, it will return a reference to the replica's `Replica` object. If the session is associated with a master instance of a persistent state datastore, the call will return `NULL`.

### The Replica Interface

The `IT_PSS::Replica` interface provides several helper functions for managing replica instances of persistent state objects.

#### **set\_master()**

`set_master()` associates a replica with a master instance. It takes the form

```
boolean set_master(Master master);
```

`set_master()` takes a reference to a `Master` object and will return `TRUE` if the association is successful. If the master instance is not active, `set_master()` will return `FALSE`.

**refresh()**

When a pull-style replica wishes to receive updated information from the master instance, it calls `refresh()`. `refresh()` takes no parameters and does not return a value. This function can be useful in updating replicas that are extremely out of date. For instance, if a push-style replica receives an update that does not completely catch it up to the master instance, it can call `refresh()` to request a full update.

**last\_successful\_refresh**

A replica can determine the last time it was refreshed by examining the `last_successful_refresh` attribute of the `Replica` interface.

---

**Recovering from a failure**

Because the replicas are inherently out of date and cannot be used to update any data records, the failure of a replica does not result in any data loss. Upon reactivation, a replica can reconnect to its master instance and will be completely refreshed.

To facilitate recovery from a failure, the master stores a list of its active registered replicas. A replica's reference is removed from the list when an invocation on it results in an `OBJECT_NOT_EXISTS` exception.

When a master restarts, it reads its list of replicas, contacts them, and updates their master object reference. At this point, you may want the replicas to immediately call `refresh()` to assure that all replicas are up to date.

---

# PSDL Language Mappings

Application code that uses PSS interacts with abstract storage types, abstract storage homes and types defined in the `CosPersistentState` module. This code is completely shielded from PSS-implementation dependencies by the C++ language mapping for abstract storage types, abstract storage homes, and the types defined by the `CosPersistentState` module.

Storage types and storage homes are mapped to concrete programming language constructs with implementation-dependent parts such as C++ members.

The C++ mapping for PSDL and IDL modules is the same. The mapping for abstract storage types and abstract storage homes is similar to the mapping for IDL structs and abstract valuetypes; the mapping for storage types and storage homes is similar to the mapping for IDL structs or valuetypes.

Implementation of operations in abstract storage types and abstract storage homes are typically provided in classes derived from classes generated by the `psdl` backend to the IDL compiler.

## Factories and connector operations

The `CosPersistentState` module defines factories to create instances of all user-defined classes, and operations to register them with a given connector:

```
module CosPersistentState {
 native StorageObjectFactory;
 native StorageHomeFactory;
 native SessionFactory;

 interface Connector {

 StorageObjectFactory
 register_storage_object_factory(
 in TypeId storage_type_name,
 in StorageObjectFactory factory
);
```

```

StorageHomeFactory
register_storage_home_factory(
 in TypeId storage_home_type_name,
 in StorageHomeFactory factory
);

SessionFactory
register_session_factory(
 in TypeId catalog_type_name,
 in SessionFactory factory
);

// ...
};
};

```

Each `register_` operation returns the factory previously registered with the given name; it returns `NULL` if there is no previously registered factory.

```

module CosPersistentState {
 enum YieldRef { YIELD_REF };
 enum ForUpdate { FOR_UPDATE };
};

```

The `CosPersistentState` module also defines two enumeration types:

**YieldRef** defines overloaded functions that return incarnations and references.

**ForUpdate** defines an overloaded accessor function that updates the state member.

---

## abstract storagehome

The language mappings for abstract storage homes are defined in terms of an equivalent local interface: the mapping of an abstract storage home is the same as the mapping of a local interface of the same name.

Inherited abstract storages homes map to inherited equivalent local interfaces in the equivalent definition.

The equivalent local interface of an abstract storage home that does not inherit from any other abstract storage home inherits from local interface

`CosPersistentState::StorageHomeBase`.

## abstract storagetype

An abstract storage type definition is mapped to a C++ abstract base class of the same name. The mapped C++ class inherits (with public virtual inheritance) from the mapped classes of all the abstract storage type inherited by this abstract storage type.

For example, given this PSDL abstract storage type definition:

```
abstract storagetype A {}; // implicitly inherits
 // CosPersistentState::StorageObject
abstract storagetype B :A {};
```

the IDL compiler generates the following C++ class:

```
class A :
 public virtual CosPersistentState::StorageObject {};
class ARef { /* ... */ };
class B : public virtual A {};
class BRef { /* ... */ };
```

The forward declaration of an abstract storage type is mapped to the forward declaration of its mapped class and `Ref` class.

### Ref class

For each abstract storage type and concrete storage type definition, the IDL compiler generates the declaration of a concrete C++ class with `Ref` appended to its name.

A `Ref` class behaves like a smart pointer: it provides an `operator->()` that returns the storage object incarnation corresponding to this reference; and conversion operators to convert this reference to the reference of any base type.

**Note:** `Ref` types manage memory in the same way as `_ptr` reference types. For functionality that is equivalent to a `_var` reference type, the IDL compiler (with the `-psdlswitch`) also generates `Ref_var` types (see [page 592](#)).

A pointer to a storage object incarnation can be implicitly converted into a reference of the corresponding type, or of any base type. Each reference also has a default constructor that builds a `NULL` reference, and a number of member functions that some implementations might be able to provide without loading the referenced object.

## Ref class members

Each `Ref` class has the following public members:

- Default constructor that creates a `NULL` reference.
- Non-explicit constructor takes an incarnation of the target storage type.
- Copy constructor.
- Destructor.
- Assignment operator.
- Assignment operator that takes an incarnation of the target [abstract] storage type.
- `operator->()` that dereferences this reference and returns the target object. The caller is not supposed to release this incarnation.
- `deref()` function that behaves like `operator->()`
- `release()` function that releases this reference
- `destroy_object()` that destroys the target object
- `get_pid()` function which returns the pid of the target object.
- `get_short_pid()` function which returns the short-pid of the target object.
- `is_null()` function that returns true only if this reference is `NULL`.
- `get_storage_home()` function that returns the storage home of the target object.
- For each direct or indirect base class of the abstract storage type, a conversion operator that converts this object to the corresponding `Ref`.

Each reference class also provides a typedef to its target type, `_target_type`. This is useful for programming with templates.

## Reference class example

For example, given this abstract storage type:

```
abstract storagetype A { };
```

the IDL compiler generates the following reference class:

**Example 69:** *Generated reference class*

```
class ARef
{
public:
 typedef A _target_type;

 //Constructors
 ARef() throw ();
 ARef(A* target) throw ();
 ARef(const ARef& ref) throw ();
 //Destructor
 ~ARef() throw ();

 //Assignment operator
 ARef& operator= (const ARef& ref) throw ();
 ARef& operator= (T* obj) throw ();

 //Conversion operators
 operator CosPersistentState::StorageObjectRef() const
 throw ();

 //Other member functions
 void release() throw ();
 A* operator-> () throw (CORBA::System Exception);
 A* deref() throw (CORBA::System Exception);
 void destroy_object() throw (CORBA::System Exception);

 CosPersistentState::Pid*
 get_pid() const throw (CORBA::System Exception);

 CosPersistentState::ShortPid*
 get_short_pid() const throw (CORBA::System Exception);

 CORBA::Boolean is_null() const throw ();

 CosPersistentState::StorageHomeBase_ptr
 get_storage_home() const throw (CORBA::System Exception);

 //additional implementation-specific members
};
```

For operation parameters, Refs are mapped as follows:

| PSDL                                | C++                    |
|-------------------------------------|------------------------|
| <code>in ref&lt; S&gt;</code>       | <code>SRef</code>      |
| <code>inout ref&lt; S&gt;</code>    | <code>SRef&amp;</code> |
| <code>out ref&lt; S&gt;</code>      | <code>SRef_out</code>  |
| <code>(return) ref&lt; S&gt;</code> | <code>SRef</code>      |

---

## Ref\_var Classes

The `_var` class associated with a `_var` provides the same member functions as the corresponding `Ref` class, and with the same behavior. It also provides these members:

- The `ref()` function returns a pointer to the managed reference, or 0 if the managed reference is `NULL`.
- Constructors and assignment operators that accept `Ref` pointers.

## State Members

Each state member is mapped to a number of overloaded public pure virtual accessor and modifier functions, with the same name as the state member. These functions can raise any CORBA standard exception.

A state member of a basic C++ type is mapped like a value data member. There is no modifier function if the state member is read-only.

For example, the following PSDL definition:

```
//PSDL
abstract storagetype Person {
 state string name;
};
```

is mapped to this C++ class:

```
class Person :public virtualCosPersistentState::StorageObject
{
public:
 virtualconst char* name() const= 0;
 virtualvoid name(const char* s)= 0; //copies
 virtualvoid name(char* s)= 0; //adopts
 virtualvoid name(constCORBA::string_var&)= 0;
};
```

### Reference to abstract storage type

A state member whose type is a reference to an abstract storage type is mapped to two accessors and two modifier functions. One of the accessor functions takes no parameter and returns a storage object incarnation, the other takes a `CosPersistentState::YieldRef` parameter and returns a reference. One of the modifier functions takes an incarnation, the other one takes a reference. If the state member is read-only, only the accessor functions are generated.

For example, the following PSDL definition:

```
abstract storagetype Bank;

abstract storagetype Account {
 state long id;
 state ref< Bank> m_y_bank;
};
```

is mapped to this C++ class:

```
class Account : public virtual CosPersistentState::StorageObject
{
public:
 virtual CORBA::Long id() = 0;
 virtual void id(CORBA::Long l) = 0;
 virtual Bank* m_y_bank() const = 0;
 virtual BankRef m_y_bank
 (CosPersistentState::YieldRefyz) const = 0;
 virtual void m_y_bank(BankRef b) = 0;
};
```

All other state members are mapped to two accessor functions—one read-only, and one read-write—and one modifier function.

### Read-only state member

If the state member is read-only, only the read-only accessor is generated. For example, the following PSDL definition:

```
abstract storagetype Person {
 readonly state string name;
 state CORBA::OctetSeq photo;
};
```

is mapped to this C++ class:

```
class Person : public virtual CosPersistentState::StorageObject
{
public:
 virtual const char* name() = 0;
 virtual const OctetSeq& photo() const = 0;
 virtual OctetSeq& photo(CosPersistentState::ForUpdate fu)
 = 0;
 virtual void photo(const OctetSeq& new_one) = 0;
};
```

---

## Operation Parameters

Table 25 shows the mapping for parameters of type  $s$  and ref  $\langle s \rangle$  (where  $s$  is an abstract storage type:).

**Table 25:** *Mapping for PSDL parameters*

| PSDL parameter  | C++ parameter     |
|-----------------|-------------------|
| in $S$ param    | const $S^*$ param |
| inout $S$ param | $S\&$ param       |
| out $S$ param   | $S\_out$ param    |
| (return) $S$    | (return) $S^*$    |

## storagetype

A `storagetype` is mapped to a C++ class of the same name. This class inherits from the mapped classes of all the abstract storage types implemented by the storage type, and from the mapped class of its base storage type, if any. This class also provides a public default constructor. All state members that are implemented directly by the storage type are implemented by the mapped class as public functions.

For example, the following PSDL definition:

```
abstract storagetype Dictionary {
 readonly state string from_language;
 readonly state string to_language;
 void insert(in string word, in string translation);
 string translate(in string word);
};

//a portable implementation:

struct Entry {
 string from;
 string to;
};
typedef sequence< Entry> EntryList;

storagetype PortableDictionary implements Dictionary {
 state EntryList entries;
};
```

is mapped to this C++ class:

```
class PortableDictionary : public virtual Dictionary /* ... */ {
public:
 const char* from_language() const;
 const char* to_language() const;
 const EntryList& entries() const;
 EntryList& entries(CosPersistentState::ForUpdate fu);
 void entries(const EntryList&);
 PortableDictionary();
 // ...
};
```

For each storage type, a concrete `Refclass` is also generated. This `Refclass` inherits from the `Refclasses` of all the abstract storage types that the storage type implements, and from the `Refclass` of the base storage type, if any.

The IDL compiler generates `Refclass` declarations for a storage type exactly as it does for an abstract storage type. For more information, [see page 588](#).

## storagehome

A `storagehome` is mapped to a C++ class of the same name. This class inherits from the mapped classes of all the abstract storage homes implemented by the storage home, and from the mapped class of its base storage home, if any. This class also provides a public default constructor.

A storage home class implements all finder operations implicitly defined by the abstract storage homes that the storage home directly implements.

The mapped C++ class provides two public non-virtual `_create()` member functions with these signatures:

- A parameter for each storage type state member. This `_create()` function returns an incarnation.
- A parameter for each storage type state member, and a `CosPersistentState::YieldRef` parameter. This `_create()` function returns a reference.

It also provides two public virtual `_create()` member functions with these signatures:

- A parameter for each storage type's reference representation members. This `_create()` function returns an incarnation
- A parameter for each storage type's reference representation members, and a `CosPersistentState::YieldRef` parameter. This `_create()` function returns a reference.

For example, given the following definition of storage home

`PortableBookStore`:

```
abstract storage type Book {
 readonly state string title;
 state float price;
};

abstract storage home BookStore of Book {};

storage type PortableBook implements Book {
 ref(title)
};

storage home PortableBookStore of PortableBook
implements BookStore {};
```

The IDL compiler (with the `pss_r` backend) generates the C++ class `PortableBookStore`:

```
class PortableBookStore :public virtualBookStore /* ... */{
public:
 virtualPortableBook* _create(const char* title,Float
 price);
 virtualPortableBook* _create();
 virtualPortableBookRef _create(
 const char* name,
 Float price,
 CosPersistentState:YieldRef yr
);
 virtualPortableBookRef _create(
 const char* title,
 CosPersistentState:YieldRef yr
);
 // ...
};
```

---

## Factory Native Types

Native factory types `StorageObjectFactory`, `StorageHomeFactory`, and `SessionFactory` map to C++ classes of the same names:

```
namespace CosPersistentState {

 template class< T>
 class Factory {
 public:
 virtual T* create()
 throw (System Exception)= 0;
 virtual void _add_ref() {}
 virtual void _remove_ref() {}
 virtual ~ Factory() {}
 };

 typedef Factory< StorageObject> StorageObjectFactory;
 typedef Factory< StorageHomeBase> StorageHomeFactory;
 typedef Factory< Session> SessionFactory;
};
```

# Event Service

*The event service enables decoupled communication between client consumers and suppliers by forwarding messages through an event channel.*

An event originates at a client *supplier* and is forwarded through an *event channel* to any number of client *consumers*. Suppliers and consumers are completely decoupled: a supplier has no knowledge of the number of consumers or their identities, and consumers have no knowledge of which supplier generated a given event.

---

**In this chapter**

This chapter discusses the following topics:

|                                                                |                          |
|----------------------------------------------------------------|--------------------------|
| <a href="#">Overview</a>                                       | <a href="#">page 602</a> |
| <a href="#">Event Communication Models</a>                     | <a href="#">page 604</a> |
| <a href="#">Developing an Application Using Untyped Events</a> | <a href="#">page 608</a> |
| <a href="#">Developing an Application Using Typed Events</a>   | <a href="#">page 624</a> |

---

# Overview

---


## Service capabilities

An event channel provides the following capabilities for forwarding events:

- Enables consumers to subscribe to events of certain types.
  - Accepts incoming events from client suppliers.
  - Forwards supplier-generated events to all connected consumers.
  - Forwarding messages using well defined IDL interfaces.
- 

## Connections

Suppliers and consumers connect to an event channel and not directly to each other, as shown in [Figure 34](#). From a supplier's perspective, the event channel appears as a single consumer; from a consumer's perspective, the event channel appears as a single supplier. In this way, the event channel decouples suppliers and consumers.



**Figure 34:** Suppliers and consumers communicating through an event channel

---


## How many clients?

Any number of suppliers can issue events to any number of consumers using a single event channel. There is no correlation between the number of suppliers and the number of consumers. New suppliers and consumers can be easily added to or removed from the system. Furthermore, any supplier or consumer can connect to more than one event channel.

For example, many documents might be linked to a spreadsheet cell, and must be notified when the cell value changes. However, the spreadsheet software does not need to know about the documents linked to its cell. When the cell value changes, the spreadsheet software should be able to issue an event that is automatically forwarded to each connected document.

## Event delivery

Figure 35 shows a sample implementation of event propagation in a CORBA system. In this example, suppliers are implemented as CORBA clients; the event channel and consumers are implemented as CORBA servers. An event occurs when a supplier invokes a clearly defined IDL operation on an object in the event channel application. The event channel then propagates the event by invoking a similar operation on objects in each of the consumer servers.



**Figure 35:** *Event propagation in a CORBA system*

---

# Event Communication Models

---

## Overview

CORBA specifies two approaches to initiating the transfer of events between suppliers and consumers

- **Push model:** Suppliers initiate transfer of events by sending those events to the channel. The channel then forwards them to any consumers connected to it.
- **Pull model:** Consumers initiate the transfer of events by requesting them from the channel. The channel requests events from the suppliers connected to it.
- **Typed push model:** Suppliers initiate the transfer of events by calling operations on an interface that is mutually agreed upon by both the consumer and the supplier. The channel forwards the events to all connected consumers that support the interface.

---

## Push model

In the push model, suppliers generate events and actively pass them to an event channel. In this model, consumers wait for events to arrive from the channel.

Figure 36 illustrates a push model architecture in which push suppliers communicate with push consumers through the event channel.





Figure 36: Push model of event transfer

In this architecture, a supplier initiates event transfer by invoking an IDL operation on an object in the event channel. The event channel then invokes a similar operation on an object in each consumer that is connected to the channel.

### Pull model

In the pull model, a consumer actively requests events from the channel. The supplier waits for a pull request to arrive from the channel. When a pull request arrives, event data is generated and returned to the channel.

Figure 37 illustrates a pull model architecture in which pull consumers communicate with pull suppliers through the event channel.




**Figure 37:** *Pull Model suppliers and consumers communicating through an event channel*

In this architecture, the event channel invokes an IDL operation on an object in each supplier to collect events. When a consumer invokes a similar operation on the event channel, the channel forwards the events to the consumer that initiated the transfer.

### Mixing push and pull models

Because suppliers and consumers are completely decoupled by the event channel, push and pull models can be mixed in a single system.

For example, suppliers can connect to an event channel using the push model, while consumers connect using the pull model, as shown in Figure 38.



**Figure 38:** *Push suppliers and pull consumers communicating through an event channel*

In this case, both suppliers and consumers participate in initiating event transfer. A supplier invokes an operation on an object in the event channel to transfer an event to the channel. A consumer then invokes another operation on an event channel object to transfer the event data from the channel.


In the case where push consumers and pull suppliers are mixed, the event channel actively propagates events by invoking IDL operations in objects in both suppliers and consumers. The pull supplier waits for the channel to invoke an event transfer before sending events. Similarly, the push consumer waits for the event channel to invoke event transfer before receiving events.

---

### Typed push model

In the typed push model suppliers connect to the channel using a consumer proxy that supports a user defined interface. The supplier then pushes strongly typed events to the channel by invoking the operations supported by the interface.

Figure 39 shows how typed push suppliers forward events to typed push consumers through a typed event channel. Push suppliers can only forward event messages to typed push consumers that support the agreed upon interface.



**Figure 39:** Push consumers pushing typed events to typed push consumers

As shown in the diagram, the decoupled nature of the event communication is preserved. Only one typed push consumer supports *Interface I*, but it receives events from two push suppliers. Also, only a single supplier pushes events using *Interface J*, but several typed push consumers support the interface and therefore receive the events.

---

# Developing an Application Using Untyped Events

## Overview

---

When using untyped events messages are packaged into `Array`s before they are forwarded through the event channel.

---

## In this section

This section discusses the following topics:

|                                            |                          |
|--------------------------------------------|--------------------------|
| <a href="#">Obtaining an Event Channel</a> | <a href="#">page 609</a> |
| <a href="#">Implementing a Supplier</a>    | <a href="#">page 612</a> |
| <a href="#">Implementing a Consumer</a>    | <a href="#">page 618</a> |

---

## Obtaining an Event Channel

---

### Overview

Consumers and suppliers obtain an event channel object reference either by creating a channel, or by finding an existing one.

You obtain an event channel factory by calling `resolve_initial_references("EventChannelFactory")`. You narrow this reference to a event channel factory with Orbix extensions.

---

### Event channel factory

Orbix provides the `EventChannelFactory` interface, which provides the operations to create and discover event channels:

```
module IT_EventChannelAdm in
{
 typedef long ChannelID;

 struct EventChannelInfo
 {
 string name;
 ChannelID id;
 CosEventChannelAdm in:EventChannel reference;
 };
 typedef sequence< EventChannelInfo> EventChannelInfoList;

 exception ChannelAlreadyExists {string name};
 exception ChannelNotFound {string name};

 interface EventChannelFactory : IT_MessagingAdm in:Manager
 {
 CosEventChannelAdm in:EventChannel create_channel(
 in string name,
 out ChannelID id)
 raises (ChannelAlreadyExists);

 CosEventChannelAdm in:EventChannel find_channel(
 in string name,
 out ChannelID id)
 raises (ChannelNotFound);
 }
}
```

```

CosEventChannelAdmin::EventChannel find_channel_by_id(
 in ChannelID id,
 out string name)
raises (ChannelNotFound);

EventChannelInfoList list_channels();
};
};

```

### Event channel factory operations

You can call one of several operations on an event channel factory to create or find an event channel. By providing both create and find operations, the event service allows any client or supplier to create an event channel, which other clients and suppliers can subsequently discover:

**create\_channel()** creates an event channel and returns an object reference.

**find\_channel()** returns an object reference to the named event channel.

**find\_channel\_by\_id()** returns an object reference to an event channel based on the channel's ID.

**list\_channels()** returns a list of event channels, which provides their names, IDs, and object references.

### Example

The following code can be used by any supplier or consumer to obtain an event channel.

#### Example 70: Obtaining an event channel

```

CosEventChannelAdmin::EventChannel var ec;
II_EventChannelAdmin in::ChannelID id;

1 CORBA::Object var obj =
 orb->resolve_initial_references("EventChannelFactory");
 II_EventChannelAdmin in::EventChannelFactory var factory =
 II_EventChannelAdmin in::EventChannelFactory::narrow(obj);
2 try {
 ec = factory->create_channel("EventChannel!", id);
 }
3 catch (II_EventChannelAdmin::ChannelAlreadyExists&) {

```

**Example 70:** *Obtaining an event channel*

4

```

//Channel has been previously created, so find it
try {
 ec = factory-> find_channel("EventChannel", id);
}
catch (II_EventChannelAdmin::ChannelNotFound&) {
 cerr<< "Couldn't create or find the event channel!"<<
 endl;
 exit(1);
}
catch (CORBA::SystemException& event_msg) {
 cerr<< "System exception occurred during find_channel: "
 << event_msg<< endl;
 exit(1);
}
} //catch ChannelAlreadyExists

```

This code executes as follows:

1. Obtains the event channel factory.
2. Tries to create an event channel by calling `create_named_channel()`.
3. Catches exception `II_EventChannelAdmin::ChannelAlreadyExists` if a channel of the specified name already exists.
4. Tries to obtain an existing channel of the same name by calling `find_channel()`.

---

## Implementing a Supplier

---

### Actions

A client supplier program performs the following actions:

1. [Instantiates suppliers](#) using the appropriate interface in module `CosEventComm`.
2. [Connects suppliers to the event channel](#).
3. [Sends event messages to the event channel](#).
4. [Disconnects from the event channel](#).

---

### Instantiating the Supplier

You instantiate a push supplier with the `PushSupplier` interface; and a pull supplier with the `PullSupplier` interface. Both are defined in the IDL module `CosEventComm`:

#### Example 71: Supplier interfaces

```
module CosEventComm {
 exception Disconnected {};

 interface PullSupplier
 {
 any pull() raises (Disconnected);
 any ty_pull(out boolean has_event)
 raises (Disconnected);
 void disconnect_pull_supplier();
 };

 interface PushSupplier
 {
 void disconnect_push_supplier();
 };
};
```

---

### Connecting to a Channel

In order to pass messages to the event channel, a supplier must connect to it through a proxy consumer that receives events from the supplier. Each supplier must have its own proxy consumer. The proxy consumer passes the events down the channel.

A client supplier connects to the event channel in three steps:

1. [Obtain a SupplierAdmin](#) object from the event channel.

2. [Obtain a proxy consumer](#) in the event channel, to receive the events that the supplier generates.
3. [Connect a supplier to a proxy consumer](#).

### Obtain a SupplierAdmin

On creation, an event channel instantiates a default `SupplierAdmin` object, which you obtain by calling `for_suppliers()` on the event channel. For example:

```
CosEventChannelAdmin::SupplierAdmin var sa =
channel-> for_suppliers();
```

### Obtain a proxy consumer

A proxy consumer is responsible for receiving event messages from its client supplier and inserting them into the event channel, where they are forwarded to all interested consumers. You obtain one proxy consumer for each client supplier.

The type of proxy consumer that you obtain depends on whether the client supplier uses the push or pull model. The type of proxy consumer must match the type of its client supplier: a push supplier must use a push proxy consumer; and a pull supplier must use a pull proxy consumer.

The `CosEventChannelAdmin` module supports the two proxy consumer object types with the following interfaces:

```
module CosEventChannelAdmin
{
 exception AlreadyConnected {};
 exception TypeError {};

 interface ProxyPushConsumer : CosEventChannelAdmin::PushConsumer
 {
 void
 connect_push_supplier(
 in CosEventChannelAdmin::PushSupplier push_supplier
) raises (AlreadyConnected);
 };
};
```

```

interface ProxyPullConsumer : CosEventChannel::PullConsumer
{
 void
 connect_pull_supplier(
 in CosEventChannel::PullSupplier pull_supplier
) raises (AlreadyConnected, TypeError);
};
// ...
};

```

You obtain a proxy consumer by invoking one of the following operations on a supplier admin:

**obtain\_push\_consumer()** returns a push-model proxy consumer.

**obtain\_pull\_consumer()** returns a pull-model proxy consumer.

### Example

The following code obtains a `ProxyPushConsumer` for a `PushSupplier` by calling `obtain_push_consumer()`.

#### Example 72: Obtaining a proxy consumer

```

try
{
 CosEventChannelAdmin::ProxyConsumer varppc =
 sa->obtain_push_consumer();
}

```

### Connect a supplier to a proxy consumer

After creating a proxy consumer, you can connect it to a compatible client supplier. This establishes the client supplier's connection to the event channel so it can send messages.

Each proxy consumer interface supports a connect operation; the operation requires that the supplier and its proxy support the same delivery model. For example, the `ProxyPushConsumer` interface defines `connect_push_supplier()`, which only accepts an object reference to a `PushSupplier` as input.:

```
interface ProxyPushConsumer : CosEventChannel::PushConsumer
{
 void
 connect_push_supplier(
 in CosEventChannel::PushSupplier push_supplier
) raises (AlreadyConnected);
};
```

### Example

The following code shows one way to implement a `PushSupplier` client that connects itself to a proxy consumer.

#### Example 73: Connecting a PushSupplier

```
//proxy ppc and PushSupplier supplier client obtained previously
try{
 ppc-> connect_push_supplier(supplier)
}
catch (CosEventChannelAdmin::AlreadyConnected value ac){
 //Handle the exception
}
catch (CORBA::SystemException& event_msg){
 cerr << "System exception occurred during connect: " <<
 event_msg << endl;
 exit(1);
}
```

## Sending Event Messages

A client supplier sends event messages in one of two ways:

- A **push supplier** invokes the `push` operation on its proxy consumer and supplies the event as an input argument.
- A **pull supplier** implements `try_pull()`. When the proxy consumer invokes a pull operation, the supplier returns an event message if one is available.

**Push supplier**

A push supplier invokes the `push()` operation on its proxy consumer. For example:

**Example 74: Pushing an event message**

```
//proxy consumer and event message already obtained
try{
 proxy->push(event_message);
}
catch (CORBA::SystemException& sysex){
 cerr<< "System exception occurred during push:"<< endl;
 sysex<< endl;
 exit(1);
}
catch (CORBA::Exception&){
 cerr<< "Unknown exception occurred during push"<< endl;
 exit(1);
}
```

**Pull supplier**

A pull supplier sends event messages only on request. Whether a client consumer invokes `pull()` or `try_pull()`, the pull supplier's proxy consumer always invokes `try_pull()` on its supplier.

Pull suppliers are responsible for implementing `try_pull()`, which returns a `CORBA::Any`. This operation is non-blocking; it returns immediately with an output parameter of type boolean to indicate whether the return value actually contains an event.

For example, the following code implements `try_pull()` by attempting to populate an event message with the latest baseball scores.

**Example 75: Pulling events**

```
PullSupplier_i::try_pull(boolean has_event)
throw (CORBA::SystemException)
{
 boolean has_scores = false;
 boolean has_event = false;

 CORBA::Any event_message;
```

**Example 75:** *Pulling events*

```

// check if any baseball scores are available
string scores = get_latest_scores(has_scores);
if (has_scores)
{
 event_m sg < < = scores;
 has_event = true;
}
return(event_m sg);
}

```

**Disconnecting From the Event Channel**

A client supplier can disconnect from the event channel at any time by invoking the disconnect operation on its proxy consumer. This operation terminates the connection between a supplier and its target proxy consumer. The channel then releases all resources allocated to support its connection to the supplier, including destruction of the target proxy consumer.

Each proxy consumer interface supports a disconnect operation. For example, interface `ProxyPushConsumer` defines `disconnect_push_consumer()`.

---

## Implementing a Consumer

---

### Actions

A client consumer program performs the following actions:

1. [Instantiates consumers](#) with the appropriate `CosEventComm` interface.
  2. [Connects consumers to the event channel](#).
  3. [Obtains event messages](#).
  4. [Disconnects from the event channel](#).
- 

### Instantiating a Consumer

You instantiate a push consumer with the `PushConsumer` interface; and a pull consumer with the `PullConsumer` interface. Both are defined in the IDL module `CosEventComm`:

#### Example 76: Consumer interfaces

```
module CosEventComm
{
 exception Disconnected { };

 interface PushConsumer {
 void push(in any data) raises (Disconnected);

 void disconnect_push_consumer ();
 };

 interface PullConsumer {
 void disconnect_pull_consumer ();
 };
};
```

---

### Connecting to the Channel

Consumers receive messages from the event channel through a proxy supplier. Each consumer on the channel has its own proxy supplier. Proxy suppliers use the same delivery method as their consumers and send the appropriate message type.

Consumers connect to the event channel in three steps:

1. [Obtain a ConsumerAdmin](#) object from the event channel.

2. Obtain a proxy supplier in the event channel, to receive supplier-generated event messages.
3. Connect the consumer to a proxy supplier.

### Obtain a ConsumerAdmin

On creation, an event channel instantiates a default `ConsumerAdmin` object, which you obtain by calling `for_consumers()` on the event channel. For example:

```
CosEventChannelAdmin::ConsumerAdmin var ca =
channel-> for_consumers();
```

### Obtain a proxy supplier

A proxy supplier is responsible for distributing event messages that have been sent by the event channel to its consumer. You create one proxy supplier for each client consumer.

The type of proxy supplier that you obtain depends on whether the client consumer uses the push or pull model. The type of proxy supplier must match the type of its client consumer: a push consumer must use a push proxy supplier; and a pull consumer must use a pull proxy supplier.

The `CosEventChannelAdmin` module supports the two proxy supplier object types with the following interfaces:

#### Example 77: Proxy supplier interfaces

```
module CosEventChannelAdmin
{
 exception AlreadyConnected {};
 exception TypeError {};

 interface ProxyPullSupplier : CosEventComm::PullSupplier
 {
 void
 connect_pull_consumer(
 in CosEventComm::PullConsumer pull_consumer
) raises (AlreadyConnected);
 };
};
```

**Example 77:** *Proxy supplier interfaces*

```
interface ProxyPushSupplier : CosEventComm :PushSupplier
{
 void
 connect_push_consumer(
 in CosEventComm :PushConsumerpush_consumer
) raises (AlreadyConnected, TypeError);
};
```

You obtain a proxy supplier by invoking one of the following operations on a consumer admin:

**obtain\_push\_supplier()** returns a push-model proxy supplier.

**obtain\_pull\_supplier()** returns a pull-model proxy supplier.

**Example**

The following code obtains a proxy supplier for a `PushConsumer` by calling `obtain_push_supplier()`.

**Example 78:** *Obtaining a proxy supplier*

```
try
{
 CosEventChannelAdmin :ProxySupplier varpps =
 ca-> obtain_push_supplier();
}
```

**Connect the consumer to a proxy supplier**

After creating a proxy supplier, you can connect it to a compatible client consumer. This establishes the client's connection to the event channel, so it can obtain messages from suppliers.

Each proxy supplier interface supports a connect operation; the operation requires that the client supplier and its proxy support the same push or pull model and event-message type. For example, the `ProxyPushSupplier` interface defines `connect_push_consumer()`, which only accepts an object reference to a `PushConsumer` as input:

```
interface ProxyPushSupplier :
 ProxySupplier,
 CosEventComm :PushSupplier
{
 void connect_push_consumer
 (in CosEventComm :PushConsumer push_consumer)
 raises(CosEventChannelAdmin:AlreadyConnected,
 CosEventChannelAdmin:TypeError);
};
```

### Example

The following example shows how you might implement a `PushConsumer` client that connects itself to a proxy supplier.

#### Example 79: Connecting to a proxy supplier

```
//Proxypps and PushConsumerconsumer obtained previously
try{
 pps-> connect_push_consumer(consumer)
}
catch (CosEventChannelAdmin:AlreadyConnected ac){
 cerr << "Already connecting to channel." << endl;
 exit(1);
}
catch (CORBA::SystemException& event_msg){
 cerr << "System exception occurred during connect: "
 << event_msg << endl;
 exit(1);
}
```

## Obtaining Event Messages

A client consumer obtains event messages in one of two ways:

- A push consumer implements the `push()` operation. As events become available, the proxy supplier pushes them to its client consumer.
- A pull consumer invokes `pull()` or `try_pull()` on its proxy supplier; the proxy supplier returns with the next available event.

**Push consumer**

A push consumer implements the `push()` operation. For example:

**Example 80: Receiving events using `push()`**

```
void NotifyPushConsumer::push (CORBA::Any event)
 throw (CORBA::SystemException)
{
 CORBA::String scores;
 event >> scores;
 cout << "Current " << sports_type << " scores: " << scores
 << endl;
}
}
```

**Pull consumer**

A pull client consumer invokes the `pull()` or `try_pull()` operation on its proxy supplier to solicit event messages; the proxy supplier returns with the next available event.

The proxy supplier interface supports operations `pull()` and `try_pull()`. A pull consumer invokes one of these operations on its `ProxyPullSupplier`. Both operations return a `CORBA::Any` argument; they differ only in their blocking mode:

**pull()** blocks until an event is available.

**try\_pull()** is non-blocking—it returns immediately with a boolean output parameter to indicate whether the return value actually contains an event. The event channel continues to invoke the pull operation on suppliers until one of them supplies an event. When an event becomes available, `try_pull()` sets its boolean `has_event` parameter to true and returns with the event data to the pull consumer.

The following example shows how a pull consumer might invoke `try_pull()` to receive data from its `ProxyPullSupplier`:

**Example 81: Pulling events**

```
//C++
CORBA::Any* event;
const char* scores;
boolean has_data = false;
```

**Example 81:** *Pulling events*

```

try{
 event = proxy-> try_pull(has_data);
}
catch (CosEventCom m :D isconnected&){
 cerr<< "D isconnected exception occurred during pull"<< endl;
 exit(1);
}
catch (CORBA::System Exception& event_m_sj){
 cerr<< "System exception occurred during pull"<< endl;
 exit(1);
}

if (has_data)
{
 if (*event> >= scores)
 {
 cout<< "Received event num ber"<< n<< " using try_pull"
 << endl;
 }
}
}

```

**Disconnecting From the Event Channel**

A client consumer can disconnect from the event channel at any time by invoking the disconnect operation on its proxy supplier. This operation terminates the connection between the consumer and its target proxy supplier. The event channel then releases all resources allocated to support its connection to the consumer, including destruction of the target proxy supplier.

Each proxy supplier interface supports a disconnect operation. For example, interface `ProxyPushSupplier` defines `disconnect_push_supplier()`.

---

# Developing an Application Using Typed Events

---

## Overview

Typed events allow event service clients to use a strongly typed interface to pass events back and forth. Using typed events can increase the performance of event service clients by eliminating the time used for marshalling, encoding, unmarshalling, and decoding of events packaged into `AnyS`. Typed event clients can also use non-typed event communication to send and receive messages.

---

## In this section

This section discusses the following topics:

|                                                 |                          |
|-------------------------------------------------|--------------------------|
| <a href="#">Creating the Interface</a>          | <a href="#">page 625</a> |
| <a href="#">Obtaining a Typed Event Channel</a> | <a href="#">page 626</a> |
| <a href="#">Implementing the Supplier</a>       | <a href="#">page 630</a> |
| <a href="#">Implementing the Consumer</a>       | <a href="#">page 634</a> |

---

## Creating the Interface

---

### Overview

When using typed push event communication, suppliers and consumers use a mutually agreed upon interface to facilitate event forwarding. This interface is defined in IDL and stored in the interface repository.

---

### Interface restrictions

Because typed event communication is strictly from the supplier to the consumer, there are two restrictions on the operations of an interface used for typed event communication:

- They can only have `in` parameters.
- They cannot have a return type other than `void`.

Messages cannot be passed through the event channel from consumer to supplier and these restrictions help reinforce the unidirectional nature of event forwarding.

---

### Example

The interface, `ScorePusher`, in [Example 82](#) shows a simple interface to push a sports score.

#### **Example 82:** *Typed event interface ScorePusher*

```
\\IDL
interface ScorePusher
{
 void push_score(in string team_a, in long score_a,
 in string team_b, in long score_b);
};
```

Once you have written the interface, you must place it into the interface repository using the following command:

```
idl-R filename
```

## Obtaining a Typed Event Channel

### Overview

A typed event channel forwards messages between typed event clients. It provides the same operations as the untyped event channel.

Consumers and suppliers obtain a typed event channel object reference either by creating a channel, or by finding an existing one.

You obtain a typed event channel factory by calling `resolve_initial_references("EventChannelFactory")`. You narrow the returned reference to a typed event channel factory with Orbix extensions.

### Event channel factory

Orbix provides the `TypedEventChannelFactory` interface, which define the operations to create and discover typed event channels:

```
module IT_TypedEventChannelAdmin
{
 struct TypedEventChannelInfo
 {
 string name;
 IT_EventChannelAdmin::ChannelID id;
 CosTypedEventChannelAdmin::TypedEventChannelReference;
 };
 typedef sequence< TypedEventChannelInfo>
 TypedEventChannelInfoList;

 interface TypedEventChannelFactory :
 IT_MessagingAdmin::Manager
 {
 CosTypedEventChannelAdmin::TypedEventChannel
 create_typed_channel(in string name,
 out IT_EventChannelAdmin::ChannelID id)
 raises(IT_EventChannelAdmin::ChannelAlreadyExists);

 CosTypedEventChannelAdmin::TypedEventChannel
 find_typed_channel(in string name,
 out IT_EventChannelAdmin::ChannelID id)
 raises(IT_EventChannelAdmin::ChannelNotFound);
 };
};
```

```

CosTypedEventChannelAdm in::TypedEventChannel
find_typed_channel_by_id(
 in IT_EventChannelAdm in:ChannelID id,
 out string name)
raises(IT_EventChannelAdm in:ChannelNotFound);

TypedEventChannelInfoList list_typed_channels();
};
};

```

### Typed event channel factory operations

You can call one of several operations on an event channel factory to create or find an event channel. By providing both create and find operations, the event service allows any client or supplier to create an event channel, which other clients and suppliers can subsequently discover:

**create\_typed\_channel()** creates a typed event channel and returns an object reference.

**find\_typed\_channel()** returns an object reference to the named typed event channel.

**find\_typed\_channel\_by\_id()** returns an object reference to a typed event channel based on the channel's ID.

**list\_typed\_channels()** returns a list of typed event channels, which provides their names, IDs, and object references.

### Example

The following code can be used by any supplier or consumer to obtain a typed event channel.

#### Example 83: Obtaining a typed event channel

```

CosTypedEventChannelAdm in::TypedEventChannel_vartec;
IT_EventChannelAdm in:ChannelID id;

```

**Example 83:** *Obtaining a typed event channel*

```

1 try
 {
 CORBA::Object_var obj =
 orb->resolve_initial_references("EventService");
 }
 catch (InvalidName)
 {
 //handle the exception
 }
 ITypedEventChannelAdmin::TypedEventChannelFactory_var
 factory =
 ITypedEventChannelAdmin::TypedEventChannelFactory::narrow
 (obj);
2 try
 {
 tec = factory->create_typed_channel("TypedChannel", id);
 }
3 catch (ITypedEventChannelAdmin::ChannelAlreadyExists&)
 {
4 //Channel has been previously created, so find it
 try
 {
 tec = factory->find_typed_channel("TypedChannel", id);
 }
 catch (ITypedEventChannelAdmin::ChannelNotFound&)
 {
 cerr << "Couldn't create or find the event channel!" <<
 endl;
 exit(1);
 }
 catch (CORBA::SystemException& event_msg)
 {
 cerr << "System exception occurred during find_channel: "
 << event_msg << endl;
 exit(1);
 }
 } //catch ChannelAlreadyExists

```

This code executes as follows:

1. Obtains the typed event channel factory.
2. Tries to create a typed event channel by calling `create_typed_channel()`.

3. Catches exception `IT_EventChannelAdmin.ChannelAlreadyExists` if a channel of the specified name already exists.
4. Tries to obtain an existing channel of the same name by calling `find_typed_channel()`.

---

## Implementing the Supplier

---

### Actions

The actions performed by a push supplier for typed event communications are similar to the actions performed by a push supplier for untyped event communication. These actions are:

1. **Instantiate** an instance of the `CosEventComm:PushSupplier` interface.
  2. **Connect** to a typed event channel.
  3. **Push** typed event messages by obtaining the appropriate interfaces and invoking its operations.
  4. **Disconnect** from the typed event channel.
- 

### Instantiate the supplier

Typed push style event communication uses a generic push supplier to supply events to typed push consumers. An application that is intended to push typed events to typed event consumers can instantiate an instance of the `CosEventComm:PushSupplier` interface.

If the supplier does not need to be informed if its proxy disconnects from the channel, the supplier can connect a `CosEventComm:PushSupplier:nil()` reference to the typed proxy consumer.

---

### Connecting to a typed event channel

In order to pass messages to the typed event channel, a supplier must connect to it through a typed proxy consumer that receives events from the supplier. The proxy consumer passes the events down the channel.

A supplier connects to the typed event channel in three steps:

1. **Obtain a TypedSupplierAdmin** from the typed event channel.
2. **Obtain a typed proxy consumer** in the typed event channel, to receive the events generated by the supplier.
3. **Connect a supplier to a typed proxy consumer.**

#### Obtain a TypedSupplierAdmin

On creation, a typed event channel instantiates a default `TypedSupplierAdmin`, which you obtain by calling `for_suppliers()` on the typed event channel. For example:

```
CosTypedEventChannelAdmin::TypedSupplierAdmin var tsa =
tec->for_suppliers();
```

### Obtain a typed proxy consumer

A typed proxy consumer is responsible for receiving typed event messages from its supplier and inserting them into the event channel, where they are forwarded to all interested typed consumers. You obtain one typed proxy consumer for each client supplier.

The `CostypedEventChannelAdmin` module supports the typed proxy push consumer object type with the following interfaces:

```
module CostypedEventChannelAdmin
{
 exception InterfaceNotSupported {};
 exception NoSuchImplementation {};

 interface TypedProxyPushConsumer :
 CostypedEventCommon::TypedPushConsumer,
 CostypedEventChannelAdmin::ProxyPushConsumer
 {
 };
}
```

You obtain a typed proxy consumer by invoking `obtain_typed_push_consumer()` on a typed supplier admin and supplying the interface repository ID of the interface the supplier intends to use to push events. If there are no consumers on the typed event channel which support the specified interface a `InterfaceNotSupported` exception is raised.

### Example

The following code obtains a `TypedProxyPushConsumer` for a `PushSupplier` by calling `obtain_typed_push_consumer()`.

#### Example 84: Obtaining a proxy consumer

```
try
{
 CostypedEventChannelAdmin::TypedProxyConsumer var tpc =
 tsa->obtain_typed_push_consumer("DL.ScorePusher:1.0");
}
catch (CostypedEventChannelAdmin::InterfaceNotSupported)
{
 //handle the exception
}
```

**Connect a supplier to a typed proxy consumer**

After creating a typed proxy consumer, you can connect it to a compatible supplier. This establishes the supplier's connection to the typed event channel so it can send messages.

Typed proxy consumers support the `connect_push_supplier()` operation. The operation requires that the supplier and its proxy support the same interface.

[Example 85](#) shows one way to implement a `PushSupplierClient` that connects itself to a typed proxy consumer.

**Example 85: Connecting a PushSupplier**

```
//proxyppc and PushSupplierSupplierClient obtained previously
try{
 tpc-> connect_push_supplier(supplier)
}
catch (CosEventChannelAdmin::AlreadyConnected& ac){
 //Handle the exception
}
catch (CORBA::SystemException& event_msg){
 cerr << "System exception occurred during connect: " <<
 event_msg << endl;
 exit(1);
}
```

**Pushing typed events**

In typed push event communication the supplier pushes events to the consumers by invoking operations on an interface that has been mutually agreed upon by both the developer responsible for implementing the supplier and the developer responsible for implementing the consumer.

The supplier obtains a reference to the appropriate interface by invoking its associated typed proxy consumer's `get_typed_consumer()` operation. This operation returns a reference to the interface specified when `obtain_typed_push_consumer()` was invoked to obtain the typed proxy consumer. The returned reference is of type `Object` and must be narrowed to the appropriate interface.

**Note:** If the supplier and the client do not support the identical interface the `narrow()` operation will fail.

Example 86 shows how a push supplier would pass typed messages to typed consumers that supported the `ScorePusher` interface defined earlier.

**Example 86:** *Pushing typed events using the `ScorePusher` interface.*

```
//C++
1 CORBA::Object_var obj = tpc->get_typed_consumer();
2 ScorePusher_var pusher = ScorePusher::_narrow(obj);
3 pusher->push_score("Hooligans", 12, "Ruffians", 9);
```

The above code performs the following actions:

1. Obtains a reference to an appropriate typed consumer interface.
2. Narrows the reference.
3. Invokes the `push_score()` operation to forward the event to any typed push consumers that implement the `ScorePusher` interface.

## Disconnecting From the Event Channel

A supplier can disconnect from a typed event channel at any time by invoking the `disconnect_push_consumer()` operation. This operation terminates the connection between a supplier and its target typed proxy consumer. The channel then releases all resources allocated to support its connection to the supplier and destroys the target typed proxy consumer.

---

## Implementing the Consumer

---

### Overview

In typed push style event communication the consumer is responsible for implementing the interface that is used to forward events. Also, the consumer is instantiated using a typed event interface, `CostypedEventComm::TypedPushConsumer`, instead of the generic push consumer interface.

---

### Development tasks

The developer of a typed push consumer must complete the following tasks:

- Implement the mutually agreed upon interface.
  - Instantiate the consumer using the `CostypedEventComm::TypedPushConsumer` interface.
  - Connect the consumer to a typed event channel.
  - Receive event messages from the channel and process them.
  - Disconnect the consumer from the typed event channel.
- 

### Implement the interface

The first step in developing a typed push consumer is to implement the interface that will be used to support the typed events. To do this complete the following steps:

1. Create a new IDL interface that inherits from the interface that will be used for event communication and from `CostEventComm::PushConsumer`. For the `ScorePusher` interface the combined interface for the consumer might look like:

```

\IDL
include < ScorePusher.idl>
include < org.CostEventComm .idl>

interface ScoreConsumer : ScorePusher,
 CostEventComm :PushConsumer
{
};

```

2. Compile the IDL interface into the desired programming language.
3. Implement the operation to be used for forwarding typed events.

4. Implement `push()`. If the consumer participate exclusively in typed event communication, `push()` can do nothing.

For example, the code shown in [Example 87](#) shows one way to implement a typed push consumer that uses the `ScorePusher` interface to forward events.

**Example 87:** *Implementing a typed push consumer*

```
//C++
#include <string>
#include <string>
#include <string>
class ScoreConsumer_i: virtual public POA_ScoreConsumer
{
 //constructor and destructor
 // ...

3 void push_score(char* team_a, CORBA::Long score_a,
 char* team_b, CORBA::Long score_b)
 {
 cout << "Score:" << endl;
 cout << team_a << "\t" << score_a << endl;
 cout << team_b << "\t" << score_b << endl;
 }

4 void push(const CORBA::Any& a)
 {
 }

 void disconnect_push_consumer()
 {
 }
};
```

### Instantiate the consumer

Typed push event communication uses the `CosTypedEventCom::TypedPushConsumer` interface to receive events. Clients wishing to act as consumers in typed push style events must instantiate an instance of this interface or, as above, an interface that inherits from it. Using the example above, the application would instantiate an instance of `ScoreConsumer` which implements both the interface used to forward events and `CosTypedEventCom::TypedPushConsumer`.

## Connecting to the channel

Typed push consumers connect to a typed event channel through a proxy push supplier which receives the events from the channel and forwards them to the consumer.

The steps to connect a typed push consumer to a typed event channel are the same as the steps to connect a generic consumer to an event channel. They are:

1. Obtain a typed consumer admin object from the typed event channel.
2. Obtain a proxy push supplier from the consumer admin.
3. Connect the consumer to the proxy supplier.

### Obtain a typed consumer admin

On creation, a typed event channel instantiates a default

`TypedConsumerAdmin` object, which you obtain by calling `for_consumers()` on the event channel. For example:

```
CostypedEventChannelAdmin::TypedConsumerAdmin var tca =
 tec->for_consumers();
```

### Obtain a proxy supplier

A proxy push supplier is responsible for distributing event messages that have been sent by the typed event channel to its typed consumer. You create one proxy supplier for each client consumer.

You obtain a proxy push supplier by invoking `obtain_typed_push_supplier()` on the typed consumer admin and supplying the interface's interface repository id. For example, to obtain a proxy push supplier for use with the `ScorePusher` interface, you would use the following operation:

```
try
{
 CostypedEventChannelAdmin::ProxyPushSupplierpps =
 tca->obtain_typed_push_supplier("DLScorePusher1.0");
}
catch (CostypedEventChannelAdmin::NoSuchImplementation)
{
 //no push supplier implements the appropriate interface
 //handle the exception
}
```

```

try
{
 org.omg.CosEventChannelAdm in ProxyPushSupplierpps =
 tca.obtain_typed_push_supplier("DL.ScorePusher1.0");
}
catch (CosTypedEventChannelAdm in NoSuchImplementation)
{
 //no supplier implements the interface
 //handle the exception
}

```

### Connect the consumer to a proxy supplier

After creating a proxy push supplier, you can connect it to a client consumer. This establishes the client's connection to the typed event channel, so it can obtain messages from suppliers.

The proxy push supplier interface supports the connect operation `connect_push_consumer()`, which accepts an object reference to a `TypedPushConsumer` as input.

[Example 88](#) shows how you might implement a `TypedPushConsumerClient` that connects itself to a proxy supplier.

### Example 88: Connecting to a proxy supplier

```

//Proxypps and TypedPushConsumerconsumer obtained previously
try{
 pps-> connect_push_consumer(consumer)
}
catch (CosEventChannelAdm in :AlreadyConnected ac){
 cerr << "Already connecting to channel." << endl;
 exit(1);
}
catch (CORBA::SystemException& event_msg){
 cerr << "System exception occurred during connect: "
 << event_msg << endl;
 exit(1);
}

```

## Receiving event messages

Typed push consumers passively receive messages from the channel. As events become available the proxy supplier forwards them to the consumer using one of the operations in the mutually agreed upon interface. The operation, which was implemented previously, is responsible for processing the event.

### **Disconnecting from the event channel**

---

A client consumer can disconnect from the event channel at any time by invoking `disconnect_push_consumer()`. This operation terminates the connection between the consumer and its target proxy supplier. The typed event channel then releases all resources allocated to support its connection to the consumer and destroys the target proxy supplier.

# Portable Interceptors

*Portable interceptors provide hooks, or interception points, which define stages within the request and reply sequence. Services can use these interception points to query request/reply data, and to transfer service contexts between clients and servers.*

---

## Sample application

This chapter shows an application that uses interceptors to secure a server with a password authorization service as follows:

- A password policy is created and set on the server's POA.
- An IOR interceptor adds a *tagged component* to all object references exported from that POA. This tagged component encodes data that indicates whether a password is required.
- A client interceptor checks the profile of each object reference that the client invokes on. It ascertains whether the object is password-protected; if so, it adds to the outgoing request a service context that contains the password data.

- A server interceptor checks the service contexts of incoming requests for password data, and compares it with the server password. The interceptor allows requests to continue only if the client and server passwords match.

**Note:** The password authorization service that is shown here is deliberately simplistic, and intended for illustrative purposes only.

### In this chapter

This chapter contains the following sections:

|                                                               |                          |
|---------------------------------------------------------------|--------------------------|
| <a href="#">Interceptor Components</a>                        | <a href="#">page 641</a> |
| <a href="#">Writing IOR Interceptors</a>                      | <a href="#">page 652</a> |
| <a href="#">Using RequestInfo Objects</a>                     | <a href="#">page 655</a> |
| <a href="#">Writing Client Interceptors</a>                   | <a href="#">page 657</a> |
| <a href="#">Writing Server Interceptors</a>                   | <a href="#">page 671</a> |
| <a href="#">Registering Portable Interceptors</a>             | <a href="#">page 684</a> |
| <a href="#">Setting Up Orbix to Use Portable Interceptors</a> | <a href="#">page 692</a> |

---

# Interceptor Components

Portable interceptors require the following components:

**Interceptor implementations** that are derived from interface

`PortableInterceptor::Interceptor`

**IOP::ServiceContext** supplies the service context data that a client or server needs to identify and access an ORB service.

**PortableInterceptor::Current** (hereafter referred to as *PICurrent*) is a table of slots that are available to application threads and interceptors, to store and access service context data.

**IOP::TaggedComponent** contains information about optional features and ORB services that an IOR interceptor can add to an outgoing object reference. This information is added by server-side IOR interceptors, and is accessible to client interceptors.

**IOP::Codec** can convert data into an octet sequence, so it can be encoded as a service context or tagged component.

**PortableInterceptor::PolicyFactory** enables creation of policy objects that are required by ORB services.

**PortableInterceptor::ORBInitializer** is called on ORB initialization. An ORB initializer obtains the ORB's *PICurrent*, and registers portable interceptors with the ORB. It can also register policy factories.

## Interceptor Types

All portable interceptors are based on the `Interceptor` interface:

```
module PortableInterceptor{
 local interface Interceptor{
 readonly attribute string name;
 };
};
```

An interceptor can be named or unnamed. Among an ORB's interceptors of the same type, all names must be unique. Any number of unnamed, or anonymous interceptors can be registered with an ORB.

**Note:** At present, Orbix provides no mechanism for administering portable interceptors by name.

All interceptors implement one of the interceptor types that inherit from the `Interceptor` interface:

**ClientRequestInterceptor** defines the interception points that client-side interceptors can implement.

**ServerRequestInterceptor** defines the interception points that server-side interceptors can implement.


**IORInterceptor** defines a single interception point, `establish_components`. It is called immediately after a POA is created, and pre-assembles the list of tagged components to add to that POA's object references.

### Interception points

Each interceptor type defines a set of interception points, which represent stages in the request/reply sequence. Interception points are specific to each interceptor type, and are discussed fully in later sections that describe these types. Generally, in a successful request-reply sequence, the ORB calls interception points on each interceptor.

For example, [Figure 40](#) shows client-side interceptors A and B. Each interceptor implements interception points `send_request` and `receive_reply`. As each outgoing request passes through interceptors A and B, their `send_request` implementations add service context data `a` and `b` to

the request before it is transported to the server. The same interceptors' `receive_reply` implementations evaluate the reply's service context data before the reply returns to the client.



**Figure 40:** Client interceptors allow services to access outgoing requests and incoming replies.

### Interception point data

For each interception point, the ORB supplies an object that enables the interceptor to evaluate the request or reply data at its current stage of flow:

- A `PortableInterceptor::DRInfo` object is supplied to an IOR interceptor's single interception point `establish_components` (see page 652).
- A `PortableInterceptor::ClientRequestInfo` object is supplied to all `ClientRequestInterceptor` interception points (see page 664).
- A `PortableInterceptor::ServerRequestInfo` object is supplied to all `ServerRequestInterceptor` interception points (see page 673).

Much of the information that client and server interceptors require is similar; so `ClientRequestInfo` and `ServerRequestInfo` both inherit from interface `PortableInterceptor::RequestInfo`. For more information on `RequestInfo`, see page 655.

---

## Service Contexts

Service contexts supply the information a client or server needs to identify and access an ORB service. The IOP module defines the `ServiceContext` structure as follows:

### Example 89: `ServiceContext` structure

```
module DP
{
 // ...
 typedef unsigned long ServiceId;


 struct ServiceContext {
 ServiceId context_id;
 sequence < octet> context_data;
 };
};
```

A service context has two member components:

- Service-context IDs are user-defined unsigned long types. The high-order 20 bits of a service-context ID contain a 20-bit vendor service context codeset ID, or *VSCID*; the low-order 12 bits contain the rest of the service context ID. To define a set of service context IDs:
  - i. Obtain a unique VSCID from the OMG
  - ii. Define the service context IDs, using the VSCID for the high-order bits.
- Service context data is encoded and decoded by an `DP::Codec` (see [“Codec” on page 648](#)).

# PICurrent

PICurrent is a table of slots that different services can use to transfer their data to request or reply service contexts. For example, in order to send a request to a password-protected server, a client application can set the required password in PICurrent. On each client invocation, a client interceptor's `send_request` interception point obtains the password from PICurrent and attaches it as service context data to the request.



**Figure 41:** PICurrent facilitates transfer of thread context data to a request or reply.

## Interface definition

The `PortableInterceptor` module defines the interface for PICurrent as follows:

**Example 90:** *PortableInterceptor:Current (PICurrent) interface*

```
module PortableInterceptor
{
 // ...
 typedef unsigned long SlotId;
 exception InvalidSlot {};
```

**Example 90:** *PortableInterceptor:Current (PICurrent) interface*

```
local interface Current : CORBA::Current {
 any
 get_slot(in SlotId id
) raises (InvalidSlot);

 void
 set_slot(in SlotId id, in any data
) raises (InvalidSlot);
};
};
```

---

## Tagged Components

Object references that support an interoperability protocol such as IIOP or SIOOP can include one or more tagged components, which supply information about optional IIOP features and ORB services. A tagged component contains an identifier, or *tag*, and component data, defined as follows:

### Example 91: *TaggedComponent* structure

```
typedef unsigned long ComponentID;
struct TaggedComponent {
 ComponentID tag;
 sequence< octet> component_data;
};
```

An IOR interceptor can define tagged components and add these to an object reference's profile by calling `add_ior_component()` (see ["Writing IOR Interceptors" on page 652](#)). A client interceptor can evaluate tagged components in a request's object reference by calling `get_effective_component()` or `get_effective_components()` (see ["Evaluating tagged components" on page 668](#)).

**Note:** The OMG is responsible for allocating and registering the tag IDs of tagged components. Requests to allocate tag IDs can be sent to `tag_request@omg.org`.

---

## Codec

### Interface definition

The data of service contexts and tagged components must be encoded as a CDR encapsulation. Therefore, the IOP module defines the `Codec` interface, so interceptors can encode and decode octet sequences:

#### Example 92: *Codec interface*

```
local interface Codec {
 exception InvalidTypeForEncoding {};
 exception FormatMismatch {};
 exception TypeMismatch {};

 CORBA::OctetSeq
 encode(in any data
) raises (InvalidTypeForEncoding);

 any
 decode(in CORBA::OctetSeq data
) raises (FormatMismatch);

 CORBA::OctetSeq
 encode_value(in any data
) raises (InvalidTypeForEncoding);

 any
 decode_value(
 in CORBA::OctetSeq data,
 in CORBA::TypeCode tc
) raises (FormatMismatch, TypeMismatch);
};
```

### Codec operations

The `Codec` interface defines the following operations:

**encode** converts the supplied `any` into an octet sequence, based on the encoding format effective for this `Codec`. The returned octet sequence contains both the `TypeCode` and the data of the type.

**decode** decodes the given octet sequence into an `any`, based on the encoding format effective for this `Codec`.

**encode\_value** converts the given `any` into an octet sequence, based on the encoding format effective for this `Codec`. Only the data from the `any` is encoded.

**decode\_value** decodes the given octet sequence into an `any` based on the given `TypeCode` and the encoding format effective for this `Codec`.

---

## Creating a codec

The `ORBInitInfo::codec_factory` attribute returns a `Codec` factory, so you can provide `Codec` objects to interceptors. This operation must be called during ORB initialization, through the ORB initializer.

---

## Policy Factory

An ORB service can be associated with a user-defined policy. The `PortableInterceptor` module provides the `PolicyFactory` interface, which applications can use to implement their own policy factories:

```
local interface PolicyFactory {
 CORBA::Policy
 create_policy(
 in CORBA::PolicyType type,
 in any value
) raises (CORBA::PolicyError);
};
```

Policy factories are created during ORB initialization, and registered through the ORB initializer (see [“Create and register policy factories” on page 688](#)).

---

## ORB Initializer

ORB initializers implement interface

`PortableInterceptor:OrbInitializer`

**Example 93:** *ORBInitializer* interface

```
local interface ORBInitializer {
 void
 pre_init(in ORBInitInfo info);

 void
 post_init(in ORBInitInfo info);
};
```

As it initializes, the ORB calls the ORB initializer's `pre_init()` and `post_init()` operations. `pre_init()` and `post_init()` both receive an `ORBInitInfo` argument, which enables implementations to perform these tasks:

- Instantiate a `PICurrent` and allocates its slots for service data.
- Register policy factories for specified policy types.
- Create `Codec` objects, which enable interceptors to encode service context data as octet sequences, and vice versa.
- Register interceptors with the ORB.

# Writing IOR Interceptors

IOR interceptors give an application the opportunity to evaluate a server's effective policies, and modify an object reference's profiles before the server exports it. For example, if a server is secured by a password policy, the object references that it exports should contain information that signals to potential clients that they must supply a password along with requests on those objects.

The IDL interface for IOR interceptors is defined as follows:

```
local interface DR_Interceptor : Interceptor {
 void
 establish_components(in DR_Info info);
};
```

## Interception point

An IOR interceptor has a single interception point, `establish_components()`. The server-side ORB calls `establish_components()` once for each POA on all registered IOR interceptors. A typical implementation of `establish_components()` assembles the list of components to include in the profile of all object references that a POA exports.

An implementation of `establish_components()` must not throw exceptions. If it does, the ORB ignores the exception.

## IORInfo

`establish_components()` gets an `DR_Info` object, which has the following interface:

### Example 94: IORInfo interface

```
local interface DR_Info {

 CORBA:Policy
 get_effective_policy(in CORBA:PolicyType type);

 void
 add_ior_component(in DP:TaggedComponent component);
```

**Example 94:** *IORInfo interface*

```

add_ior_component_to_profile (
 in DP::TaggedComponent component,
 in DP::ProfileId profile_id
);
};

```

**Note:** `add_ior_component_to_profile()` is currently unimplemented.

The sample application's IOR interceptor implements `establish_components()` to perform the following tasks on an object reference's profile:

- Get its password policy.
- Set a `TAG_REQUIRES_PASSWORD` component accordingly.

**Example 95:** *Implementing `establish_components()`*

```

ACL_DRIInterceptorImpl::ACL_DRIInterceptorImpl(
 DP::Codec_ptr codec
) IT_THROW_DECL():
 m_codec(DP::Codec::duplicate(codec))
{
}

void
ACL_DRIInterceptorImpl::establish_components(
 PortableInterceptor::DRInfo_ptr ior_info
) IT_THROW_DECL((CORBA::SystemException))
{
 CORBA::Boolean requires_password = IT_FALSE;

1 try {

 CORBA::Policy_var policy =
 ior_info->get_effective_policy(
 AccessControl::PASSWORD_POLICY_ID);
 AccessControl::PasswordPolicy_var password_policy =
 AccessControl::PasswordPolicy::narrow(policy);
 assert(CORBA::is_nil(password_policy));
 }
}

```

**Example 95:** *Implementing establish\_components()*

```

2 requires_password = password_policy->requires_password();
 }
 catch (const CORBA::INV_POLICY&) {
 //Policy wasn't set..dont add component
 }

 CORBA::Any component_data_as_any;
 component_data_as_any << =
 CORBA::Any::from_boolean(requires_password);

3 CORBA::OctetSeq_var octets =
 m_codec->encode_value(component_data_as_any);

4 DP::TaggedComponent component;
 component.tag = AccessControlService::TAG_REQUIRES_PASSWORD;
 component.component_data.replace(octets->length(),
 octets->length(),
 octets->get_buffer(),
 IT_FALSE);

5 ir_info->add_ir_component(component);
 }

```

The sample application's implementation of `establish_components()` executes as follows:

1. Gets the effective password policy object for the POA by calling `get_effective_policy()` on the `DRInfo`.
2. Gets the password policy value by calling `requires_password()` on the policy object.
3. Encodes the password policy value as an octet.
4. Instantiates a tagged component (`DP::TaggedComponent`) and initializes it with the `TAG_REQUIRES_PASSWORD` tag and encoded password policy value.
5. Adds the tagged component to the object reference's profile by calling `add_ir_component()`.

---

# Using RequestInfo Objects

Interception points for client and server interceptors receive `ClientRequestInfo` and `ServerRequestInfo` objects, respectively. These derive from `PortableInterceptorRequestInfo`, which defines operations and attributes common to both.

## Interface definition

The `RequestInfo` interface is defined as follows:

### Example 96: *RequestInfo* interface

```
local interface RequestInfo {
 readonly attribute unsigned long request_id;
 readonly attribute string operation;
 readonly attribute Dynamic<ParameterList> arguments;
 readonly attribute Dynamic<ExceptionList> exceptions;
 readonly attribute Dynamic<ContextList> contexts;
 readonly attribute Dynamic<RequestContext operation_context>;
 readonly attribute any result;
 readonly attribute boolean response_expected;
 readonly attribute Messaging::SyncScope sync_scope;
 readonly attribute ReplyStatus reply_status;
 readonly attribute Object forward_reference;
 any get_sbt (in SbtId id) raises (InvalidSbt);
 DP::ServiceContext get_request_service_context (
 in DP::ServiceId id);
 DP::ServiceContext get_reply_service_context (
 in DP::ServiceId id);
};
```

A `RequestInfo` object provides access to much of the information that an interceptor requires to evaluate a request and its service context data. For a full description of all attributes and operations, see the *CORBA Programmer's Reference*.

The validity of any given `RequestInfo` operation and attribute varies among client and server interception points. For example, the `result` attribute is valid only for interception points `receive_reply` on a client interceptor; and `send_reply` on a server interceptor. It is invalid for all other interception

points. [Table 26 on page 664](#) and [Table 27 on page 678](#) show which `RequestInfo` operations and attributes are valid for a given interception point.

## Timeout attributes

A client might specify one or more timeout policies on request or reply delivery. If portable interceptors are present in the bindings, these interceptors must be aware of the relevant timeouts so that they can bound any potentially blocking activities that they undertake.

The current OMG specification for portable interceptors does not account for timeout policy constraints; consequently, Orbix provides its own derivation of the `RequestInfo` interface, `IT_PortableInterceptor::RequestInfo`, which adds two attributes:

### Example 97: `IT_PortableInterceptor::RequestInfo` interface attributes

```
module IT_PortableInterceptor
{
 local interface RequestInfo : PortableInterceptor::RequestInfo
 {
 readonly attribute TimeBase:U toT request_end_time;
 readonly attribute TimeBase:U toT reply_end_time;
 };
};
```

To access timeout constraints, interception point implementations can narrow their `ClientRequestInfo` or `ServerRequestInfo` objects to this interface. The two attributes apply to different interception points, as follows:

| Timeout attribute             | Relevant interception points                                                                                                                                                    |
|-------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>request_end_time</code> | <code>send_request</code><br><code>send_poll</code><br><code>receive_request_service_contexts</code><br><code>receive_request</code>                                            |
| <code>reply_end_time</code>   | <code>send_reply</code><br><code>send_exception</code><br><code>send_other</code><br><code>receive_reply</code><br><code>receive_exception</code><br><code>receive_other</code> |

---

# Writing Client Interceptors

---

## Interception point definitions

Client interceptors implement the `ClientRequestInterceptor` interface, which defines five interception points:

### Example 98: *ClientRequestInterceptor* interface

```
local interface ClientRequestInterceptor : Interceptor {
 void send_request (in ClientRequestInfo ri)
 raises (ForwardRequest);
 void send_poll (in ClientRequestInfo ri);
 void receive_reply (in ClientRequestInfo ri);
 void receive_exception (in ClientRequestInfo ri)
 raises (ForwardRequest);
 void receive_other (in ClientRequestInfo ri)
 raises (ForwardRequest);
};
```

A client interceptor implements one or more of these operations.

In the password service example, the client interceptor provides an implementation for `send_request`, which encodes the required password in a service context and adds the service context to the object reference. For implementation details, see [“Client Interceptor Tasks” on page 667](#).

---

## Client interceptor constructor

As noted earlier, the ORB initializer instantiates and registers the client interceptor. This interceptor’s constructor is implemented as follows:

### Example 99: *Client interceptor constructor*

```
//Client interceptor constructor
ACL_ClientInterceptor in pl:ACL_ClientInterceptor in pl(
 PortableInterceptor::SbtId password_sbt,
 DP::Codec_ptr codec
) IT_THROW_DECL():
 m_password_sbt(password_sbt),
 m_codec(DP::Codec::duplicate(codec))
{
}
```

### Client interceptor arguments

The client interceptor takes two arguments:

- The `PICurrent` slot allocated by the ORB initializer to store password data.
- An `DP:Codec`, which is used to encode password data for service context data.

---

## Interception Points

A client interceptor implements one or more interception points. During a successful request-reply sequence, each client-side interceptor executes one starting interception point and one ending interception point.

---

### Starting interception points

Depending on the nature of the request, the ORB calls one of the following starting interception points:

**send\_request** lets an interceptor query a synchronously invoked request, and modify its service context data before the request is sent to the server.

**send\_poll** lets an interceptor query an asynchronously invoked request, where the client polls for a reply. This interception point currently applies only to deferred synchronous operation calls (see [“Invoking Deferred Synchronous Requests” on page 448](#))

---

### Ending interception points

Before the client receives a reply to a given request, the ORB executes one of the following ending interception points on that reply:

**receive\_reply** lets an interceptor query information on a reply after it is returned from the server and before control returns to the client.

**receive\_exception** is called when an exception occurs. It lets an interceptor query exception data before it is thrown to the client.

**receive\_other** lets an interceptor query information that is available when a request results in something other than a normal reply or an exception. For example: a request can result in a retry, as when a GIOP reply with a `LOCATION_FORWARD` status is received; `receive_other` is also called on asynchronous calls, where the client resumes control before it receives a reply on a given request and an ending interception point is called.


## Interception Point Flow

For each request-reply sequence, only one starting interception point and one ending point is called on a client interceptor. Each completed starting point is paired to an ending point. For example, if `send_request` executes to completion without throwing an exception, the ORB calls one of its ending interception points—`receive_reply`, `receive_exception`, or `receive_other`.

If multiple interceptors are registered on a client, the interceptors are traversed in order for outgoing requests, and in reverse order for incoming replies.

### Scenario 1: Request-reply sequence is successful

Interception points A and B are registered with the server ORB. The interception point flow shown in [Figure 42](#) depicts a successful reply-request sequence, where the server returns a normal reply:




**Figure 42:** Client interceptors process a normal reply.

**Scenario 2: Client receives**

LOCATION\_FORWARD

If the server throws an exception or returns some other reply, such as `LOCATION_FORWARD`, the ORB directs the reply flow to the appropriate interception points, as shown in [Figure 43](#):




**Figure 43:** Client interceptors process a `LOCATION_FORWARD` reply.

**Scenario 3: Exception aborts interception flow**

Any number of events can abort or shorten the interception flow. [Figure 44](#) shows the following interception flow:

1. Interceptor B's `send_request` throws an exception.

- Because interceptor B's start point does not complete, no end point is called on it, and interceptor C is never called. Instead, the request flow returns to interceptor A's `receive_exception` end point.




**Figure 44:** `send_request` throws an exception in a client-side interceptor

#### Scenario 4: Interceptor changes reply

An interceptor can change a normal reply to a system exception; it can also change the exception it receives, whether user or system exception to a different system exception. Figure 45 shows the following interception flow:

- The server returns a normal reply.
- The ORB calls `receive_reply` on interceptor C.
- Interceptor A's `receive_reply` raises exception `foo_x`, which the ORB delivers to interceptor B's `receive_exception`.
- Interceptor B's `receive_exception` changes exception `foo_x` to exception `foo_y`.
- Interceptor A's `receive_exception` receives exception `foo_y` and returns it to the client.



**Figure 45:** Client interceptors can change the nature of the reply.

**Note:** Interceptors must never change the CompletionStatus of the received exception.

## ClientRequestInfo

Each client interception point gets a single `ClientRequestInfo` argument, which provides the necessary hooks to access and modify client request data:

### Example 100: `ClientRequestInfo` interface

```
local interface ClientRequestInfo : RequestInfo {
 readonly attribute Object target;
 readonly attribute Object effective_target;
 readonly attribute DP::TaggedProfile effective_profile;
 readonly attribute any received_exception;
 readonly attribute CORBA::RepositoryId received_exception_id;

 DP::TaggedComponent
 get_effective_component(in DP::ComponentId id);

 DP::TaggedComponentSeq
 get_effective_components(in DP::ComponentId id);

 CORBA::Policy
 get_request_policy(in CORBA::PolicyType type);

 void
 add_request_service_context(
 in DP::ServiceContext service_context,
 in boolean replace
);
};
```

Table 26 shows which `ClientRequestInfo` operations and attributes are accessible to each client interception point. In general, attempts to access an attribute or operation that is invalid for a given interception point throw an exception of `BAD_INV_ORDER` with a standard minor code of 10.

**Table 26:** *Client Interception Point Access to `ClientRequestInfo`*

| ClientRequestInfo: | s_req | s_poll | r_reply | r_exep | r_other |
|--------------------|-------|--------|---------|--------|---------|
| request_id         | y     | y      | y       | y      | y       |
| operation          | y     | y      | y       | y      | y       |

**Table 26:** *Client Interception Point Access to ClientRequestInfo*

| <b>ClientRequestInfo:</b>   | <b>s_req</b>   | <b>s_poll</b> | <b>r_reply</b> | <b>r_exep</b> | <b>r_other</b> |
|-----------------------------|----------------|---------------|----------------|---------------|----------------|
| arguments                   | y <sup>a</sup> |               | y              |               |                |
| exceptions                  | y              |               | y              | y             | y              |
| contexts                    | y              |               | y              | y             | y              |
| operation_context           | y              |               | y              | y             | y              |
| result                      |                |               | y              |               |                |
| response_expected           | y              | y             | y              | y             | y              |
| sync_scope                  | y              |               | y              | y             | y              |
| reply_status                |                |               | y              | y             | y              |
| forward_reference           |                |               |                |               | y <sup>b</sup> |
| get_slot                    | y              | y             | y              | y             | y              |
| get_request_service_context | y              |               | y              | y             | y              |
| get_reply_service_context   |                |               | y              | y             | y              |
| target                      | y              | y             | y              | y             | y              |
| effective_target            | y              | y             | y              | y             | y              |
| effective_profile           | y              | y             | y              | y             | y              |
| received_exception          |                |               |                | y             |                |
| received_exception_id       |                |               |                | y             |                |
| get_effective_component     | y              |               | y              | y             | y              |
| get_effective_components    | y              |               | y              | y             | y              |
| get_request_policy          | y              |               | y              | y             | y              |
| add_request_service_context | y              |               |                |               |                |

a. When `ClientRequestInfo` is passed to `send_request`, the `arguments` list contains an entry for all arguments, but only in and inout arguments are available.

b. Access to `forward_reference` is valid only if `reply_status` is set to `LOCATION_FORWARD` or `LOCATION_FORWARD_PERMANENT`.

---

## Client Interceptor Tasks

A client interceptor typically uses a `ClientRequestInfo` to perform the following tasks:

- Evaluate an object reference's tagged components to determine an outgoing request's service requirements.
- Obtain service data from `PICurrent`.
- Encode service data as a service context.
- Add service contexts to a request.

These tasks are usually implemented in `send_request`. Interceptors have a much wider range of potential actions available to them—for example, client interceptors can call `get_request_service_context()`, to evaluate the service contexts that preceding interceptors added to a request. Other operations are specific to reply data or exceptions, and therefore can be invoked only by the appropriate `receive_` interception points.

This discussion confines itself to `send_request` and the tasks that it typically performs. For a full description of other `ClientRequestInfo` operations and attributes, see the *CORBA Programmer's Reference*.

In the sample application, the client interceptor provides an implementation for `send_request`, which performs these tasks:

- Evaluates each outgoing request for this tagged component to determine whether the request requires a password.
- Obtains service data from `PICurrent`
- Encodes the required password in a service context
- Adds the service context to the object reference:

**Evaluating tagged components**

The sample application's implementation of `send_request` checks each outgoing request for tagged component `TAG_REQRES_PASSWORD` by calling `get_effective_component()` on the interceptor's `ClientRequestInfo`:

**Example 101: Using `get_effective_component()`**

```

void
ACL_ClientInterceptor::pl::send_request(
 PortableInterceptor::ClientRequestInfo_ptr request
) IT_THROW_DECL((
 CORBA::SystemException,
 PortableInterceptor::ForwardRequest
))

try {
//Check if the object requires a password
1 if (requires_password(request))
 { // ...
 }
}

// ...

CORBA::Boolean
ACL_ClientInterceptor::pl::requires_password(
 PortableInterceptor::ClientRequestInfo_ptr request
) IT_THROW_DECL((CORBA::SystemException))
{
 try {
2 DP::TaggedComponent_var password_required_component =
 request->get_effective_component(
 AccessControlService::TAG_REQRES_PASSWORD
);

3 DP::TaggedComponent::component_data_seq& component_data =
 password_required_component->component_data;
 CORBA::OctetSeq octets(component_data.length(),
 component_data.length(),
 component_data.get_buffer(),
 IT_FALSE);

```

**Example 101:** *Using get\_effective\_component()*

```

4 CORBA:Any var password_required_as_any =
 m_codec-> decode_value(octets, CORBA::to_boolean);

CORBA:Boolean password_required;

5 if (password_required_as_any >=
 CORBA:Any::to_boolean(password_required))
 {
 return password_required;
 }

catch (const CORBA::BAD_PARAM &)
 {
 //Component does not exist; treat as not requiring a
 password
 }

return II_FALSE;
}

```

The interception point executes as follows:

1. Calls the subroutine `require_password()` to determine whether a password is required.
2. `get_effective_component()` returns tagged component `TAG_REQUIRES_PASSWORD` from the request's object reference.
3. `component_data()` returns the tagged component's data as an octet sequence.
4. `decode_value()` is called on the interceptor's `Codec` to decode the octet sequence into a `CORBA:Any`. The call extracts the Boolean data that is embedded in the octet sequence.
5. The `Any` is evaluated to determine whether the component data of `TAG_REQUIRES_PASSWORD` is set to true.

**Obtaining service data**

After the client interceptor verifies that the request requires a password, it calls `RequestInfo::get_slot()` to obtain the client password from the appropriate slot:

**Example 102: Calling `RequestInfo::get_slot()`**

```
//Get the specified password
CORBA::Any_var password =
 request-> get_slot(m_password_slot);
// ...
}
```

**Encoding service context data**

After the client interceptor gets the password string, it must convert the string and related data into a CDR encapsulation, so it can be embedded in a service context that is added to the request. To perform the data conversion, it calls `encode_value` on an `DP::Codec`:

**Example 103: Calling `DP::Codec::encode_value()`**

```
//Encode the password as a service context
CORBA::OctetSeq_var octets =
 m_codec-> encode_value(password);
DP::ServiceContext::context_data_seq seq(
 octets-> length(),
 octets-> length(),
 octets-> get_buffer(),
 II_FALSE);
```

**Adding service contexts to a request**

After initializing the service context, the client interceptor adds it to the outgoing request by calling `add_request_service_context()`:

**Example 104: Calling `add_request_service_context()`**

```
DP::ServiceContext service_context;
service_context.context_id =
 AccessControlService::PASSW_ORD_SERVICE_ID;
service_context.context_data = seq;

request-> add_request_service_context(
 service_context, II_TRUE);
```

---

# Writing Server Interceptors

Server interceptors implement the `ServerRequestInterceptor` interface:

## Example 105: `ServerRequestInterceptor` interface

```
local interface ServerRequestInterceptor : Interceptor {
 void
 receive_request_service_contexts(in ServerRequestInfo ri
) raises (ForwardRequest);

 void
 receive_request(in ServerRequestInfo ri
) raises (ForwardRequest);

 void
 send_reply(in ServerRequestInfo ri);

 void
 send_exception(in ServerRequestInfo ri
) raises (ForwardRequest);

 void
 send_other(in ServerRequestInfo ri
) raises (ForwardRequest);
};
```

---

## Interception Points

During a successful request-reply sequence, each server interceptor executes one starting interception point and one intermediate interception point for incoming requests. For outgoing replies, a server interceptor executes an ending interception point.

---

### Starting interception point

A server interceptor has a single starting interception point:

**receive\_request\_service\_contexts** lets interceptors get service context information from an incoming request and transfer it to PICurrent slots. This interception point is called before the servant manager is called. Operation parameters are not yet available at this point.

---

### Intermediate interception point

A server interceptor has a single intermediate interception point:

**receive\_request** lets an interceptor query request information after all information, including operation parameters, is available.

---

### Ending interception points

An ending interception point is called after the target operation is invoked, and before the reply returns to the client. The ORB executes one of the following ending interception points, depending on the nature of the reply:

**send\_reply** lets an interceptor query reply information and modify the reply service context after the target operation is invoked and before the reply returns to the client.

**send\_exception** is called when an exception occurs. An interceptor can query exception information and modify the reply service context before the exception is thrown to the client.

**send\_other** lets an interceptor query the information available when a request results in something other than a normal reply or an exception. For example, a request can result in a retry, as when a GIOP reply with a `LOCATION_FORWARD` status is received.

---

## Interception Point Flow

For a given server interceptor, the flow of execution follows one of these paths:

- `receive_request_service_contexts` completes execution without throwing an exception. The ORB calls that interceptor's intermediate and ending interception points. If the intermediate point throws an exception, the ending point for that interceptor is called with the exception.
- `receive_request_service_contexts` throws an exception. The interceptor's intermediate and ending points are not called.

If multiple interceptors are registered on a server, the interceptors are traversed in order for incoming requests, and in reverse order for outgoing replies. If one interceptor in the chain throws an exception in either its starting or intermediate points, no other interceptors in the chain are called; and the appropriate ending points for that interceptor and all preceding interceptors are called.


---

### Scenario 1: Target object throws exception

Interceptors A and B are registered with the server ORB. [Figure 46](#) shows the following interception flow:

1. The interception point `receive_request_server_contexts` processes an incoming request on interceptor A, then B. Neither interception point throws an exception.
2. Intermediate interception point `receive_request` processes the request first on interceptor A, then B. Neither interception point throws an exception.
3. The ORB delivers the request to the target object. The object throws an exception.
4. The ORB calls interception point `send_exception`, first on interceptor B., then A, to handle the exception.

- The ORB returns the exception to the client.




**Figure 46:** Server interceptors receive request and send exception thrown by target object.

### Scenario 2: Exception aborts interception flow

Any number of events can abort interception flow. [Figure 47](#) shows the following interception flow.

- A request starts server-side interceptor processing, starting with interceptor A's `receive_request_service_contexts`. The request is passed on to interceptor B.
- Interceptor B's `receive_request_service_contexts` throws an exception. The ORB aborts interceptor flow and returns the exception to interceptor A's end interception point `send_exception`.
- The exception is returned to the client.

Because interceptor B's start point does not complete execution, its intermediate and end points are not called. Interceptor A's intermediate point `receive_request` also is not called.




**Figure 47:** `receive_request_service_contexts` throws an exception and interception flow is aborted.

### Scenario 3: Interceptors change reply type

An interceptor can change a normal reply to a system exception; it can also change the exception it receives, whether user or system exception to a different system exception. Figure 48 shows the following interception flow:

1. The target object returns a normal reply.
2. The ORB calls `send_reply` on server interceptor C.
3. Interceptor C's `send_reply` interception point throws exception `foo_x`, which the ORB delivers to interceptor B's `send_exception`.
4. Interceptor B's `send_exception` changes exception `foo_x` to exception `foo_y`, which the ORB delivers to interceptor A's `send_exception`.
5. Interceptor A's `send_exception` returns exception `foo_y` to the client.



**Figure 48:** Server interceptors can change the reply type.

**Note:** Interceptors must never change the CompletionStatus of the received exception.

---

## ServerRequestInfo

Each server interception point gets a single `ServerRequestInfo` argument, which provides the necessary hooks to access and modify server request data:

### Example 106: `ServerRequestInfo` interface

```
local interface ServerRequestInfo : RequestInfo {
 readonly attribute any sending_exception;
 readonly attribute CORBA::OctetSeq object_id;
 readonly attribute CORBA::OctetSeq adapter_id;
 readonly attribute CORBA::RepositoryId
 target_in_out_derived_interface;

 CORBA::Policy
 get_server_policy(in CORBA::PolicyType type);

 void
 set_sbt(
 in SbtId id,
 in any data
) raises (InvalidSbt);

 boolean
 target_is_a(in CORBA::RepositoryId id);

 void
 add_reply_service_context(
 in DP::ServiceContext service_context,
 in boolean release
);
};
```

Table 27 shows which `ServerRequestInfo` operations and attributes are accessible to server interception points. In general, attempts to access an attribute or operation that is invalid for a given interception point raise an exception of `BAD_INV_ORDER` with a standard minor code of 10.

**Table 27:** *Server Interception Point Access to ServerRequestInfo*

| <b>ServerRequestInfo:</b>     | <b>r_req_serv_cxts</b> | <b>r_req</b> | <b>s_reply</b> | <b>s_except</b> | <b>s_other</b> |
|-------------------------------|------------------------|--------------|----------------|-----------------|----------------|
| request_id                    | y                      | y            | y              | y               | y              |
| operation                     | y                      | y            | y              | y               | y              |
| arguments <sup>a</sup>        | y                      | y            | y              |                 |                |
| exceptions                    |                        | y            | y              | y               | y              |
| contexts                      |                        | y            | y              | y               | y              |
| operation_context             |                        | y            | y              |                 |                |
| result                        |                        |              | y              |                 |                |
| response_expected             | y                      | y            | y              | y               | y              |
| sync_scope                    | y                      | y            | y              | y               | y              |
| reply_status                  |                        |              | y              | y               | y              |
| forward_reference             |                        |              |                |                 | y              |
| get_slot                      | y                      | y            | y              | y               | y              |
| get_request_service_context   | y                      | y            | y              | y               | y              |
| get_reply_service_context     |                        |              | y              | y               | y              |
| sending_exception             |                        |              |                | y               |                |
| object_id                     |                        | y            |                |                 |                |
| adapter_id                    |                        | y            |                |                 |                |
| target_most_derived_interface |                        | y            |                |                 |                |
| get_server_policy             | y                      | y            | y              | y               | y              |

**Table 27:** *Server Interception Point Access to ServerRequestInfo*

| <b>ServerRequestInfo:</b> | <b>r_req_<br/>serv_cxts</b> | <b>r_req</b> | <b>s_reply</b> | <b>s_except</b> | <b>s_other</b> |
|---------------------------|-----------------------------|--------------|----------------|-----------------|----------------|
| set_slot                  | y                           | y            | y              | y               | y              |
| target_is_a               |                             | y            |                |                 |                |
| add_reply_service_context | y                           | y            | y              | y               | y              |

a. When a `ServerRequestInfo` is passed to `receive_request()`, the arguments list contains an entry for all arguments, but only in and inout arguments are available.

## Server Interceptor Tasks

A server interceptor typically uses a `ServerRequestInfo` to perform the following tasks:

- Get server policies.
- Get service contexts from an incoming request and extract their data.

The sample application implements `receive_request_server_contexts` only. The requisite service context data is available at this interception point, so it is capable of executing authorizing or disqualifying incoming requests. Also, unnecessary overhead is avoided for unauthorized requests: by throwing an exception in `receive_request_server_contexts`, the starting interception point fails to complete and all other server interception points are bypassed.

This discussion confines itself to `receive_request_server_contexts` and the tasks that it typically performs. For a description of other `ServerRequestInfo` operations and attributes, see the *CORBA Programmer's Reference*.

### Get server policies

The sample application's `receive_request_server_contexts` implementation obtains the server's password policy in order to compare it to the password that accompanies each request. In order to do so, it calls `get_server_policy()` on the interception point's `ServerRequestInfo`:

#### Example 107: Calling `get_server_policy()`

```
void
ACL_ServerInterceptorIn pl:receive_request_service_contexts(
 PortableInterceptor::ServerRequestInfo ptrrequest
) IT_THROW_DECL((
 CORBA::SystemException,
 PortableInterceptor::ForwardRequest
))
{
 //Determine whether password protection is required.
 AccessControl::PasswordPolicy varpassword_policy =
 get_password_policy(request);
 // ...
}
```

**Example 107:** *Calling `get_server_policy()`*

```

AccessControl:PasswordPolicy_ptr
ACL_ServerInterceptor::in pl: get_password_policy(
 PortableInterceptor:ServerRequestInfo_ptr request
) IT_THROW _DECL((CORBA::SystemException))
{
 try {
 CORBA::Policy_var policy = request-> get_server_policy(
 AccessControl:PASSWORD_POLICY_D);
 return AccessControl:PasswordPolicy::_narrow(policy);
 }
 catch (const CORBA::NV_POLICY&) {
 //Policy not specified
 }

 return AccessControl:PasswordPolicy::_nil();
}

// ...

```

**Get service contexts**

After `receive_request_server_contexts` gets the server's password policy, it needs to compare it to the client password that accompanies the request. The password is encoded as a service context, which is accessed through its identifier `PASSWORD_SERVICE_D`:

**Example 108:**

```

// ...
if ((CORBA::is_nil(password_policy) &&
 password_policy-> requires_password())
 {
 CORBA::String_var server_password =
 password_policy-> password();
 if (check_password(request, server_password))
 {
 throw CORBA::NO_PERMISSION(0xDEADBEEF);
 }
}
// ...

```

**Example 108:**

```

CORBA::Boolean
ACL_ServerInterceptor::check_password(
 PortableInterceptor::ServerRequestInfo_ptr request,
 const char* expected_password
) IT_THROW _DECL((CORBA::SystemException))
{
 try {
 //Get the password service context...
1 DP::ServiceContext_var password_service_context =
 request-> get_request_service_context(
 AccessControlService::PASSWORD_SERVICE_ID
);

 // ...convert it into string form at...
2 DP::ServiceContext::_context_data_seq& context_data =
 password_service_context-> context_data;
3 CORBA::OctetSeq octets(context_data.length(),
 context_data.length(),
 context_data.get_buffer(),
 IT_FALSE);

4 CORBA::Any_var password_as_any =
 m_codec-> decode_value(octets, CORBA::_tc_string);
 const char* password;
 password_as_any > = password;

 // ...and compare the passwords
5 return (strcmp(password, expected_password) == 0);
 }
 catch (const CORBA::BAD_PARAM &)
 {
 //Service context was not specified
 return IT_FALSE;
 }
}

```

The interception point executes as follows:

1. Calls `get_request_service_context()` with an argument of `AccessControlService::PASSWORD_SERVICE_ID`. If successful, the call returns with a service context that contains the client password.
2. `context_data()` returns the service context data as an octet sequence (see “Service Contexts” on page 644).
3. Initializes an octet sequence with the context data.

4. Calls `decode_value()` on the interceptor's `Codec` to decode the octet sequence into a `CORBA:Any`. The call specifies to extract the string data that is embedded in the octet sequence.
5. Extracts the `Any`'s string value and compares it to the server password. If the two strings match, the request passes authorization and is allowed to proceed; otherwise, an exception is thrown back to the client.

## Registering Portable Interceptors

Portable interceptors and their components are instantiated and registered during ORB initialization, through an ORB initializer. An ORB initializer implements its `pre_init()` or `post_init()` operation, or both. The client and server applications must register the ORB initializer before calling `ORB_init()`.

## Implementing an ORB\_INITIALIZER

The sample application's ORB initializer implements `pre_init()` to perform these tasks:

- [Obtain PICurrent](#) and allocate a slot for password data.
- [Encapsulate PICurrent](#) and the password slot identifier in an `AccessControl::Cument` object, and register this object with the ORB as an initial reference.
- [Register a password policy factory](#).
- [Create Codec objects for the application's interceptors](#), so they can encode and decode service context data and tagged components.
- [Register interceptors with the ORB](#).

### Obtain PICurrent

In the sample application, the client application and client interceptor use PICurrent to exchange password data:

- The client thread places the password in the specified PICurrent slot.
- The client interceptor accesses the slot to obtain the client password and add it to outgoing requests.

In the sample application, `pre_init()` calls the following operations on `ORB_InitialInfo`:

1. `allocate_sbt_id()` allocates a slot and returns the slot's identifier.
2. `resolve_initial_references("PICurrent")` returns PICurrent.

### Example 109: Obtaining PICurrent

```

void
ACL_ORB_Initializer::pre_init(
 PortableInterceptor::ORB_InitialInfo_ptr info
) IT_THROW_DECL((CORBA::SystemException))
{
 //Reserve a sbt for the password cument
 PortableInterceptor::SbtId password_sbt =
 info->allocate_sbt_id();

 PortableInterceptor::Cument_var pi_cument;

 //getPICurrent
 try {

```

**Example 109: Obtaining PICurrent**

```

2 CORBA::Object var init_ref =
 info-> resolve_initial_references("PICurrent");
 pi_current =
 PortableInterceptor::Current::narrow (init_ref);
 } catch
 (const PortableInterceptor::ORBInitInfo::InvalidName &) {
 throw CORBA::INITIALIZE();
 }
 // ...
}

```

**Register an initial reference**

After the ORB initializer obtains PICurrent and a password slot, it must make this information available to the client thread. To do so, it instantiates an `AccessControl::Current` object. This object encapsulates:

- PICurrent and its password slot
- Operations that access slot data

The `AccessControl::Current` object has the following IDL definition:

**Example 110: AccessControl::Current interface**

```

module AccessControl {
 // ...
 local interface Current : CORBA::Current {
 attribute string password;
 };
};

```

The application defines its implementation of `AccessControl::Current` as follows:

**Example 111: Implementing an AccessControl::Current object**

```

#include <omg/PortableInterceptor.h>
#include <orbis/corba.h>
#include "access_control.h"

class ACL_CurrentImpl :
 public AccessControl::Current,
 public II_CORBA::RefCountedLocalObject

```

**Example 111:** *Implementing an AccessControl::Current object*

```

{
public:
 ACL_CurrentImpl(
 PortableInterceptor::Current_ptr pi_current,
 PortableInterceptor::SbtId password_sbt
) IT_THROW_DECL();

 char*
 password() IT_THROW_DECL((CORBA::SystemException));

 void
 password(const char* the_password
) IT_THROW_DECL((CORBA::SystemException));
 // ...
}

```

With `AccessControl::Current` thus defined, the ORB initializer performs these tasks:

1. Instantiates the `AccessControl::Current` object.
2. Registers it as an initial reference.

**Example 112:** *Registering AccessControl::Current as an initial reference*

```

1 try {
2 AccessControl::Current_ptr current =
 new ACL_CurrentImpl(pi_current, password_sbt);
 info->register_initial_reference(
 "AccessControl::Current", current);
}
catch (const
 PortableInterceptor::ORBInitInfo::DuplicateName&)
{
 throw CORBA::INITIALIZE();
}

```

## Create and register policy factories

The sample application's IDL defines the following password policy to provide password protection for the server's POAs.

### Example 113: Defining a password policy

```
module AccessControl {
 const CORBA::PolicyType PASSW ORD_POLICY_ID = 0xBEEF;

 struct PasswordPolicyValue {
 boolean requires_password;
 string password;
 };

 local interface PasswordPolicy : CORBA::Policy {
 readonly attribute boolean requires_password;
 readonly attribute string password;
 };

 local interface Cument : CORBA::Cument {
 attribute string password;
 };
};
```

During ORB initialization, the ORB initializer instantiates and registers a factory for password policy creation:

```
PortableInterceptor::PolicyFactory_var passwd_policy_factory =
 new ACL_PasswordPolicyFactoryIn pl();
info-> register_policy_factory(
 AccessControl::PASSW ORD_POLICY_ID,
 passwd_policy_factory
);
```

For example, a server-side ORB initializer can register a factory to create a password policy, to provide password protection for the server's POAs.

## Create Codec objects

Each portable interceptor in the sample application requires a `PortableInterceptor::Codec` in order to encode and decode octet data for service contexts or tagged components. The ORB initializer obtains a `Codec` factory by calling `ORB::Info::codec_factory`, then creates a `Codec`:

### Example 114: Creating a Codec object

```
DP::CodecFactory_var codec_factory = info-> codec_factory();
DP::Encoding cdr_encoding = { DP::ENCODING_CDR_ENCAPS, 1, 2 };
DP::Codec_var cdr_codec =
 codec_factory-> create_codec(cdr_encoding);
```

When the ORB initializer instantiates portable interceptors, it supplies this `Codec` to the interceptor constructors.

## Register interceptors

The sample application relies on three interceptors:

- An IOR interceptor that adds a `TAG_PASSWORD_REQUIRED` component to IOR's that are generated by the server application.
- A client interceptor that attaches a password as a service context to outgoing requests.
- A server interceptor that checks a request's password before allowing it to continue.

**Note:** The order in which the ORB initializer registers interceptors has no effect on their runtime ordering. The order in which portable initializers are called is determined by their order in the client and server binding lists (see [“Setting Up Orbix to Use Portable Interceptors” on page 692](#))

The ORB initializer instantiates and registers these interceptors as follows:

### Example 115: Registering interceptors

```
//Register DR interceptor
PortableInterceptor::DRInterceptor_var ior_icp =
 new ACL_DR_InterceptorImpl(cdr_codec);
info-> add_ior_interceptor(ior_icp);
```

**Example 115:** *Registering interceptors*

```
//Register client interceptor
PortableInterceptor:ClientRequestInterceptor var client_ip =
new ACL_ClientInterceptor in pl(password_sbt, cdr_codec);
info-> add_client_request_interceptor(client_ip);

//Register server interceptor
PortableInterceptor:ServerRequestInterceptor var server_ip =
new ACL_ServerInterceptor in pl(cdr_codec);
info-> add_server_request_interceptor(server_ip);
```

---

## Registering an ORBInitializer

An application registers an ORB initializer by calling `register_orb_initializer`, which is defined in the `PortableInterceptor` name space as follows:

```
namespace PortableInterceptor {
 static void register_orb_initializer(
 PortableInterceptor::ORB_Initializer_ptr init);
};
```

Each service that implements interceptors provides an instance of an ORB initializer. To use a service, an application follows these steps:

1. Calls `register_orb_initializer` and supplies the service's ORB initializer.
2. Instantiates a new ORB by calling `ORB_init()` with a new ORB identifier.

An ORB initializer is called by all new ORBs that are instantiated after its registration.

---

# Setting Up Orbix to Use Portable Interceptors

The following setup requirements apply to registering portable interceptors with the Orbix configuration. At the appropriate scope, add:

- `portable_interceptor` plugin to `orb_plugins`.
- Client interceptor names to `client_binding_list`.
- Server interceptor names to `server_binding_list`.

You can only register portable interceptors for ORBs created in programs that are linked with the shared library `it_portable_interceptor`. If an application has unnamed (anonymous) portable interceptors, add `AnonymousPortableInterceptor` to the client and server binding lists. All unnamed portable interceptors insert themselves at that location in the list.

**Note:** The binding lists determine the order in which interceptors are called during request processing.

For more information about Orbix configuration, see the *Application Server Platform Administrator's Guide*.

# Orbix IDL Compiler Options

The IDL compiler compiles the contents of an IDL module into header and source files for client and server processes, in the specified implementation language. You invoke the `idlcompiler` with the following command syntax:

```
idl-plugin[...] [-switch]... idlModule
```

**Note:** You must specify at least one plugin switch, such as `-poa` or `-base`, unless you modify the IDL configuration file to set `Default` for one or more plugins to Yes. (see page 700). As distributed, the configuration file sets `Default` for all plugins to No.

## Command Line Switches

You can qualify the `idl` command with one or more of the following switches. Multiple switches are colon-delimited.

| Switch                                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|----------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>-Dname [ value ]</code>          | Defines the preprocessor's name.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <code>-E</code>                        | Runs preprocessor only, prints on <code>stdout</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| <code>-Dir</code>                      | Includes <code>dir</code> in search path for preprocessor.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| <code>-R[-v]</code>                    | Populates the interface repository (IFR). The <code>-v</code> modifier specifies verbose mode.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| <code>-Uname</code>                    | Undefines name for preprocessor.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <code>-V</code>                        | Prints version information and exits.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| <code>-u</code>                        | Prints usage message and exits.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <code>-w</code>                        | Suppresses warning messages.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| <code>-plugin<br/>[modifier]...</code> | <p>Specifies to load the IDL plug-in specified by <code>plugin</code> to generate code that is specific to a language or ART plug-in. You must specify at least one plugin to the <code>idl</code> compiler</p> <p>Use one of these values for <code>plugin</code>:</p> <ul style="list-style-type: none"> <li><code>base</code>: Generate C++ header and stub code.</li> <li><code>base</code>: Generate Java stub code</li> <li><code>poa</code>: Generate POA code for C++ servers.</li> <li><code>poa</code>: Generate POA code for Java servers.</li> <li><code>psdl</code>: Generate C++ code that maps to abstract PSDL constructs.</li> <li><code>ps_r</code>: Generate C++ code that maps concrete PSDL constructs to relational and relational-like database back-end drivers.</li> </ul> <p>Each <code>plugin</code> switch can be qualified with one or more colon-delimited modifiers.</p> |

## Plug-in Switch Modifiers

The following tables describe the modifiers that you can supply to plug-in switches such as `-base` or `-poa`.

**Table 28:** *Modifiers for all C++ plug-in switches*

| Modifier                   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|----------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>-d[decl-spec]</code> | <p>Creates NT declspecs for <code>dlexport</code> and <code>dimport</code>. If you omit <code>decl-spec</code>, <code>idl</code> uses the stripped IDL module's name.</p> <p>For example, the following command:</p> <pre>idl -dIT_ART_API foo.idl</pre> <p>yields this code:</p> <pre># if defined(IT_ART_API) # if defined(IT_ART_API_EXPORT) # define IT_ART_API_DECLSPEC_EXPORT # else # define IT_ART_API_DECLSPEC_IMPORT # endif # endif</pre> <p>If you compile and link a DLL with the <code>idl</code>-generated code within it, <code>IT_ART_API_EXPORT</code> must be a defined preprocessor symbol so that <code>IT_ART_API</code> is set to <code>dlexport</code>. All methods and variables in the generated code can be exported from the DLL and used by other applications. If <code>IT_ART_API_EXPORT</code> is not defined as a preprocessor symbol, <code>IT_ART_API</code> is set to <code>dimport</code>; methods and variables that are defined in the generated code are imported from a DLL.</p> |
| <code>-path-prefix</code>  | <p>Prepends <code>path-prefix</code> to generated <code>include</code> statements. For example, if the IDL file contains the following statement:</p> <pre># include "foo.idl"</pre> <p><code>idl</code> generates this statement in the header file:</p> <pre># include path-prefix/foo.h</pre>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |

**Table 28:** *Modifiers for all C++ plug-in switches*

| Modifier                       | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|--------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>-h[suffix.]ext</code>    | <p>Sets header file extensions. The default setting is <code>hh</code>.</p> <p>For example, the following command:</p> <pre>idl-base:hh foo.idl</pre> <p>yields a header file with this name:</p> <pre>foo.h</pre> <p>If the argument embeds a period (<code>.</code>), the string to the left of the period is appended to the IDL file name; the string to the right of the period specifies the file extension. For example, the following command:</p> <pre>idl-base:h_client.h foo.idl</pre> <p>yields the following header file name:</p> <pre>foo_client.h</pre> <p>If you use the <code>-h</code> to modify the <code>-base</code> switch, also use <code>-b</code> to modify the <code>-pca</code> switch (see <a href="#">Table 31</a>).</p> |
| <code>-Oopath</code>           | Sets the output directory for header files.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| <code>-Oopath</code>           | Sets the output directory for client stub ( <code>.xxx</code> ) files.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| <code>-&gt;AM Callbacks</code> | Generates stub code that enables asynchronous method invocations (AMI).                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |

**Table 29:** *Modifier for -base, -psdl, and -pss\_r plugin switches*

| Modifier                    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|-----------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>-c[suffix.]ext</code> | <p>Specifies the format for stub file names. The default name is <code>idl-name.cxx</code>.</p> <p>For example, the following command:</p> <pre>idl-base:cc foo.idl</pre> <p>yields a server skeleton file with this name:</p> <pre>foo.c</pre> <p>If the argument embeds a period (<code>.</code>), the string to the left of the period is appended to the IDL file name; the string to the right of the period specifies the file extension. For example, the following command:</p> <pre>idl-base:c_client.c foo.idl</pre> <p>yields the following stub file name:</p> <pre>foo_client.c</pre> |

**Table 29:** Modifier for `-base`, `-psdl`, and `-pss_r` plugin switches

| Modifier           | Description                                                                        |
|--------------------|------------------------------------------------------------------------------------|
| <code>-xOBV</code> | Generates object-by-value default <code>valuetype</code> implementations in files. |

**Table 30:** Modifiers for `-jbase` and `-jpoa` switches

| Modifier                                         | Description                                                                                                                                        |
|--------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>-Ppackage</code>                           | Use <code>package</code> as the root scope to package all unspecified modules. By default, all Java output is packaged in the IDL module names.    |
| <code>-Pmodule= package</code>                   | Use <code>package</code> as the root scope for the specified module.                                                                               |
| <code>-Odir</code>                               | Output all java code to <code>dir</code> . The default is the current directory.                                                                   |
| <code>-Gdsi</code><br><code>-Gstream</code>      | Output DSI or stream-based code. The default is <code>stream</code> .                                                                              |
| <code>-Mreflect</code><br><code>-Mcascade</code> | Specifies the POA dispatch model to use either reflection or cascading <code>if-then-else</code> statements. The default is <code>reflect</code> . |
| <code>-J1.1</code><br><code>-J1.2</code>         | Specifies the JDK version. The default is 1.2.                                                                                                     |
| <code>-VTRUE</code><br><code>-VFALSE</code>      | Generate native implementation for valuetypes. The default is <code>FALSE</code> .                                                                 |
| <code>-FTRUE</code><br><code>-FFALSE</code>      | Generate factory implementation for valuetypes. The default is <code>FALSE</code> .                                                                |

**Table 31:** *Modifiers for -poa switch*

| Modifier                                  | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|-------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>-s[<i>suffix</i>.]<i>ext</i></code> | <p>Specifies the skeleton file name. The default name is <code>idl-nameS.cxx</code> for skeleton files.</p> <p>For example, the following command:</p> <pre>idl-poa-sc foo.idl</pre> <p>yields a server skeleton file with this name:</p> <pre>fooS.c</pre> <p>If the argument embeds a period (<code>.</code>), the string to the left of the period is appended to the IDL file name; the string to the right of the period specifies the file extension. For example, the following command:</p> <pre>idl-poa-s_server.h foo.idl</pre> <p>yields the following skeleton file name:</p> <pre>foo_server.c</pre>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| <code>-b[<i>suffix</i>.]<i>ext</i></code> | <p>Specifies the format of the header file names in generated <code># include</code> statements. Use this modifier if you also use the <code>-h</code> modifier with the <code>-base</code> plugin switch.</p> <p>For example, if you specify a <code>h</code> extension for <code>-base</code>-generated header files, specify the same extension in <code>-poa</code>-generated <code># include</code> statements, as in the following commands:</p> <pre>idl-base-hh foo.idl idl-poa-bh foo.idl</pre> <p>These commands generate header file <code>foo.h</code>, and include in skeleton file <code>fooS.cxx</code> a header file of the same name:</p> <pre># include "foo.h"</pre> <p>If the argument embeds a period (<code>.</code>), the string to the left of the period is appended to the IDL file name; the string to the right of the period specifies the file extension. For example, the following command:</p> <pre>idl-poa-b_client.h foo.idl</pre> <p>yields in the generated skeleton file the following <code># include</code> statement:</p> <pre># include "foo_client.h"</pre> |

**Table 31:** *Modifiers for -poa switch*

| Modifier                         | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|----------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>-m <i>incl-mask</i></code> | <p><code># include</code> statements with file names that match <i>mask</i> are ignored in the generated skeleton header file. This lets the code generator ignore files that it does not need. For example, the following switch:</p> <pre data-bbox="501 430 596 453"><code>-m <i>an glob</i></code></pre> <p>directs the <code>idl</code> compiler to ignore this <code># include</code> statement in the IDL/PSDL:</p> <pre data-bbox="501 508 705 531"><code># include &lt;<i>an glob.idl</i>&gt;</code></pre> |
| <code>-p <i>multiple</i></code>  | <p>Sets the dispatch table to be 2 to the power of <i>multiple</i>. The default value of <i>multiple</i> is 1. Larger dispatch tables can facilitate operation dispatching, but also increase code size and memory usage.</p>                                                                                                                                                                                                                                                                                       |
| <code>-xTIE</code>               | <p>Generates POA TIE classes.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |

## IDL Configuration File

The IDL configuration file defines valid `idlplugin` switches such as `-base` and `-poa` and specifies how to execute them. For example, the default IDL configuration file defines the `base` and `poa` switches, the path to their respective libraries, and command line options to use for compiling C++ header and client stub code and POA code.

IDL configuration files have the following format:

**Figure 49:** Configuration file format

```
IDLPlugins= "plugin-type[,plugin-type].."

plugin-type
{
 Switch= switch-name;
 ShlibName= path;
 ShlibMajorVersion= version
 EDefault= "{ YES / NO }";
 PresetOptions= "plugin-modifier[,plugin-modifier]..."

plugin-specific settings...
...
}
```

`plugin-type` can be one of the following literals:

```
Java
POAJava
Cplusplus
POACxx
FR
PSSDLCxx
PSSRCxx
```

The `idl` command can supply additional switch modifiers; these are appended to the switch modifiers that are defined in the configuration file. You can comment out any line by beginning it with the `#` character.

The distributed IDL configuration file looks like this:

**Figure 50:** Distributed IDL configuration file

```
IDL Configuration File

DL_CPP_LOCATION configures the C-Preprocessor for the IDL
Compiler
It can be the fully qualified path with the executable name or
just the executable name
DL_CPP_LOCATION = % PRODUCT_BIN_DIR_PATH % /idl_cpp";
DL_CPP_ARGUMENTS = "";
tmp_dir= "c:\temp";

DPLugins= "Java, POAJava, Cplusplus, POACxx, FR, PSSDICxx,
PSSRCxx";

Cplusplus
{
 Switch = "base";
 ShlibName = "t_cxx_be";
 ShlibMajorVersion = "1";
 BDefault = "NO";
 PresetOptions = "t";

Header and StubExtension set the generated files
extension
The Default is .cxx and .hh
#
StubExtension = ".cxx";
HeaderExtension = ".hh";
};
```

**Figure 50:** Distributed IDL configuration file

```

POACxx
{
 Switch = "poa";
 ShlibName = "t_poa_cxx_ibe";
 ShlibMajorVersion = "1";
 BDefault = "NO";
 PresetOptions = "t";

Header and StubExtension set the generated files
extension
The Default is .cxx and .hh
#
StubExtension = "cxx";
HeaderExtension = "hh";
};

IFR
{
 Switch = "R";
 ShlibName = "t_ifr_ibe";
 ShlibMajorVersion = "1";
 BDefault = "NO";
 PresetOptions = "";
};

PSSDLCxx
{
 Switch = "psdl";
 ShlibName = "t_pss_cxx_ibe";
 ShlibMajorVersion = "1";
 BDefault = "NO";
 PresetOptions = "t";
 UsePSSDLGrammar = "YES";

Header and StubExtension set the generated files
extension
The Default is .cxx and .hh
#
StubExtension = "cxx";
HeaderExtension = "hh";
};

```

**Figure 50:** Distributed IDL configuration file

```

PSSRCxx
{
 Switch = "pss_r";
 ShlibName = "it_pss_r_cxx_obe";
 ShlibMajorVersion = "1";
 ISDefault = "NO";
 PresetOptions = "-t";
 UsePSSDiagram = "YES";

Header and StubExtension set the generated files
extension
The Default is .cxx and .hh
#
StubExtension = "cxx";
HeaderExtension = "hh";
};

Java Config Information
Java
{
 Switch = "jbase";
 ShlibName = "itl_java";
 ShlibMajorVersion = "1";
 ISDefault = "NO";
};

POAJava
{
 Switch = "jpoa";
 ShlibName = "jpoa";
 ShlibMajorVersion = "1";
 ISDefault = "NO";
};

```

Given this configuration, you can issue the following idl commands on the IDL file `foo.idl`

|                                     |                                                                   |
|-------------------------------------|-------------------------------------------------------------------|
| <code>idl -base foo.idl</code>      | Generates client stub and header code.                            |
| <code>idl -poa foo.idl</code>       | Generates POA code.                                               |
| <code>idl -base -poa foo.idl</code> | Generates code for both client stub and header code and POA code. |

---

## Providing Arguments to the IDL Compiler

---

### Overview

The Orbix IDL compiler configuration can be used to provide arguments to the IDL compiler. Normally, IDL compiler arguments are supplied to the `ORXIDL` procedure via the `IDLPARM` JCL symbolic, which comprises part of the JCL PARM. The JCL PARM has a 100-character limit imposed by the operating system. Large IDL compiler arguments, coupled with locale environment variables, tend to easily approach or exceed the 100-character limit. To help avoid problems with the 100-character limit, IDL compiler arguments can be provided via a data set containing IDL compiler configuration statements.

---

### IDL compiler argument input to ORXIDL

The `ORXIDL` procedure accepts IDL compiler arguments from three sources:

- The `orbixhlq.CONFIG(IDL)` data set—This is the main Orbix IDL compiler configuration data set. See "IDL Configuration File" on page 700 for an example of the `Cplusplus` and `POACxx` configuration scopes. The `Cplusplus` and `POACxx` configuration scopes used by the IDL compiler are in `orbixhlq.CONFIG(IDL)`. IDL compiler arguments are specified in the `PresetOptions` variable.
- The `IDLARGS` data set—This data set can extend or override what is defined in the main Orbix IDL compiler configuration data set. The `IDLARGS` data set defines a `PresetOptions` variable for each configuration scope. This variable overrides what is defined in the main Orbix IDL compiler configuration data set.
- The `IDLPARM` symbolic of the `ORXIDL` procedure—This is the usual source of IDL compiler arguments.

Because the `IDLPARM` symbolic is the usual source for IDL compiler arguments, it might lead to problems with the 100-character JCL PARM limit. Providing IDL compiler arguments in the `IDLARGS` data set can help to avoid problems with the 100-character limit. If the same IDL compiler arguments are supplied in more than one input source, the order of precedence is as follows:

- IDL compiler arguments specified in the `IDLPARM` symbolic take precedence over identical arguments specified in the `IDLARGS` data set and the main Orbix IDL compiler configuration data set.
- The `PresetOptions` variable in the `IDLARGS` data set overrides the `PresetOptions` variable in the main Orbix IDL compiler configuration data set. If a value is specified in the `PresetOptions` variable in the main Orbix IDL compiler configuration data set, it should be defined (along with any additional IDL compiler arguments) in the `PresetOptions` variable in the `IDLARGS` data set.

### Using the IDLARGS data set

The `IDLARGS` data set can help when IDL compiles are failing due to the 100-character limit of the JCL PARM. Consider the following JCL:

```
//IDL EXEC ORXIDL ,
// SOURCE=BANK ,
// IDL=&ORBIX..DEMOS.IDL ,
// HH=&ORBIX..DEMOS.CPP.HH ,
// COPYLIB= ,
// STUBS=&ORBIX..DEMOS.CPP.GEN ,
// IMPL= ,
// IDLPARM=' -base -poa:-xTIE'
```

In the preceding example, all the IDL compiler arguments are provided in the `IDLPARM` JCL symbolic, which is part of the JCL PARM. The JCL PARM can also be comprised of an environment variable that specifies locale information. Locale environment variables tend to be large and use up many of the 100 available characters in the JCL PARM. If the 100-character limit

is exceeded, some of the data in the `IDLPARM` JCL symbolic can be moved to the `IDLARGS` data set to reclaim some of the JCL PARM space. The preceding example can be recoded as follows:

```
//IDL EXEC ORXIDL,
// SOURCE=BANK,
// IDL=&ORBIX..DEMOS.IDL,
// HH=&ORBIX..DEMOS.CPP.HH,
// COPYLIB=,
// STUBS=&ORBIX..DEMOS.CPP.GEN,
// IMPL=,
// IDLPARM=' -base -poa '
//IDLARGS DD *
POACxx {PresetOptions = "-xTIE:-xRTTI:-xEnforceRaisesOn:-xBug319On:-xB\
rokenAccessDeclsOn";};
/*
```

The `IDLPARM` JCL symbolic retains the `-base` and `-poa` switches. The rest of the `IDLPARM` data is now provided in the `IDLARGS` data set, freeing up six characters of JCL PARM space.

The `IDLARGS` data set contains IDL configuration file scopes. These are a reopening of the scopes defined in the main IDL configuration file. In the preceding example, the `IDLPARM` JCL symbolic contains a `-poa` switch. This instructs the IDL compiler to look in the `POACxx` scope of the `IDLARGS` dataset for any IDL compiler arguments that might be defined in the `PresetOptions` variable. Based on the preceding example, it finds `-xTIE:-xRTTI:-xEnforceRaisesOn:-xBug319On:-XB rokenAccessDeclsOn`.

The `-xTIE` compiler argument is what was originally removed from the `IDLPARM` symbolic. However, because the main Orbix IDL compiler configuration data set contains a `POACxx` scope with a `PresetOptions` variable that has `-xRTTI:-xEnforceRaisesOn:-xBug319On:-xB rokenAccessDeclsOn` defined in it, this value is overwritten unless it is also defined in the `PresetOptions` variable in the `POACxx` scope of the `IDLARGS` data set.

The `IDLARGS` data set must be coded according to the syntax rules for the main Orbix IDL compiler configuration data set. See "IDL Configuration File" for an example of the `Cplusplus` and `POACxx` configuration scopes..

**Note:** A long entry can be continued by coding a backslash character (that is, `\`) in column 72, and starting the next line in column 1.

### Defining multiple scopes in the IDLARGS data set

The IDLARGS data set can contain multiple scopes. Consider the following JCL:

```
//IDL EXEC ORXIDL,
// SOURCE=TYPETES,
// IDL=&ORBIX..DEMOS.IDL,
// HH=&ORBIX..DEMOS.CPP.HH,
// COPYLIB=,
// STUBS=&ORBIX..DEMOS.CPP.GEN,
// IMPL=,
// IDLPARM=' -base:-xOBV:-xAMICallbacks -poa:-xAMICallbacks '
```

The IDLPARM JCL symbolic contains both a `-base` and `-poa` switch. The preceding example can be recoded as follows:

```
//IDL EXEC ORXIDL,
// SOURCE=TYPETES,
// IDL=&ORBIX..DEMOS.IDL,
// HH=&ORBIX..DEMOS.CPP.HH,
// COPYLIB=,
// STUBS=&ORBIX..DEMOS.CPP.GEN,
// IMPL=,
// IDLPARM=' -base -poa '
//IDLARGS DD *
Cplusplus {PresetOptions = "-xOBV:-xAMICallbacks:-xRTTI:-xEnforceRaise\
sOn:-xBug319On:-xBrokenAccessDeclsOn";};
Cplusplus {PresetOptions = "-xAMICallbacks:-xRTTI:-xEnforceRaisesOn:xBug\
319On:-xBrokenAccessDeclsOn";};
/*
```

The IDLPARM JCL symbolic retains the `-base` and `-poa` IDL compiler switches. The IDL compiler looks for `-base` switch arguments in the `Cplusplus` scope, and for `-poa` switch arguments in the `POACxx` scope.



# IONA Foundation Classes Library

For each platform, IONA distributes several variants of its IONA foundation classes (IFC) shared library, which provides a number of proprietary features, such as a threading abstraction. For each IFC library, IONA provides checked and unchecked variants:

- Checked variants are suitable for development and testing: extra checking is built into the code—for example, it throws an exception when a thread attempts to lock a mutex that it has already locked.
- Unchecked variants are suitable for deployed applications, which have been tested for thread safety.

Each UNIX distribution provides IFC libraries that support the POSIX thread package. The following platforms have multiple IFC libraries, which support different thread packages:

| Platform      | Thread package support |
|---------------|------------------------|
| HPUX 32       | POSIX, DCE/CMA         |
| Solaris 32/64 | POSIX, UI              |

---

## Installed IFC Directories

Each Orbix installation makes IFC variants available in directories with this format:

### Unix:

Unchecked `$IT_PRODUCT_DR/$lib/native-thread-pkg/lib_ifc_compiler-spec`

Checked `$IT_PRODUCT_DR/$lib/native-thread-pkg/checked/lib_ifc_compiler-spec`

### Windows:

Unchecked `% IT_PRODUCT_DR% \bin\windows\it_ifc3_vc60.dll`

Checked `% IT_PRODUCT_DR% \bin\windows\checked\it_ifc3_vc60.dll`

Further, each installation provides a default IFC directory, which contains an unchecked variant. On UNIX platforms, the default directory contains a symbolic link to an unchecked variant of UI or POSIX; on Windows, it contains a copy of the unchecked variant of the Windows IFC library:

### UNIX:

`$IT_PRODUCT_DR/$lib/default/ifc-lib-sym-link`

### Windows:

`% IT_PRODUCT_DR% \bin\it_ifc3_vc60.dll`

---

# Selecting an IFC Library

Options for setting a given program's IFC library are platform-dependent.

---

## Unix

On UNIX systems, you can set a program's IFC library in two ways:

- (Recommended) When linking the program, use the linker's run path feature, and set it to the desired IFC library directory. For example, set the `-R` option with the Sun compiler.
  - Set the program's environment variable (`ID_LIBRARY_PATH` or `SHLIB_PATH`). Keep in mind that other services such as the Locator also might use this environment and can be affected by this setting.
- 

## Windows

Set `PATH` to the desired IFC library directory.



# Orbix C++ Libraries

| Library Name     | Function                                                                                                           |
|------------------|--------------------------------------------------------------------------------------------------------------------|
| it_art.lib       | The main ART library. This lib is <b>always</b> needed when linking projects.                                      |
| it_dynany.lib    | Provides DynAny support. This lib must be linked for any project that uses Dynamic Anys.                           |
| it_event.lib     | Event service stub code. This lib must be linked into any project that uses the event or notification service.     |
| it_event_psk.lib | Event service skeleton code. This lib must be linked into any project that uses the event or notification service. |
| it_genie.lib     | Provides support for the boiler plate code generated by the <code>itgen</code> genie.                              |
| it_ifc.lib       | IONA foundation classes. This lib must be linked into all projects.                                                |
| it_lease.lib     | Session Management stub code. Required by CORBA servers using the Orbix Leasing Plug-In.                           |

| Library Name                | Function                                                                                                          |
|-----------------------------|-------------------------------------------------------------------------------------------------------------------|
| it_load_balancing.lib       | Naming Service load balancing stub code. Only required by projects that use the IT_LoadBalancing module.          |
| it_location.lib             | Locator stub code. This lib is only needed by projects that need to directly communicate with the locator daemon. |
| it_message_routing.lib      | Provide support for AMI message routing. Required by all projects that use the MessageRouting module.             |
| it_message_routing_psk.lib  | Provide support for AMI message routing. Required by all servers that use the MessageRouting module.              |
| it_naming.lib               | Naming service stub code. Required by any project using the CosNaming module.                                     |
| it_naming_admin.lib         | Naming service admin interfaces stub code. Required by any project using the CosNaming module.                    |
| it_notify.lib               | Notification service stub code. Required by any project using the notification service.                           |
| it_notify_psk.lib           | Notification skeletons. Required by any project using the notification service.                                   |
| it_ots.lib                  | OTS stub code. Required by any project that uses OTS.                                                             |
| it_ots_psk.lib              | OTS skeletons. Required by any CORBA server that uses OTS.                                                        |
| it_poa.lib                  | POA stub code. This lib is needed for all CORBA applications that have a POA.                                     |
| it_portable_interceptor.lib | Portable Interceptor stub code. Required by any project that uses portable interceptors.                          |
| it_pss.lib                  | PSS stub code. Required by any projects using the Orbix Persistent State Service.                                 |

| Library Name      | Function                                                                              |
|-------------------|---------------------------------------------------------------------------------------|
| it_pss_r.lib      | PSS stub code. Required by any projects using the Orbix persistent state service.     |
| it_trader.lib     | Trader stub code. Required by any project that needs to access the Orbix Trader.      |
| it_trader_psk.lib | Trader skeletons. Required by any CORBA server that needs to access the Orbix Trader. |
| it_xa.lib         | XA skeletons. Required by projects using the Orbix XA Plug-In.                        |



# IONA Policies

*Orbix supports a number of proprietary policies in addition to the OMG policies. To create a policy of the proper type you must know the policy's tag.*

---

**In this appendix**

This appendix contains the following sections:

|                                         |                          |
|-----------------------------------------|--------------------------|
| <a href="#">Client Side Policies</a>    | <a href="#">page 714</a> |
| <a href="#">POA Policies</a>            | <a href="#">page 717</a> |
| <a href="#">Security Policies</a>       | <a href="#">page 719</a> |
| <a href="#">Firewall Proxy Policies</a> | <a href="#">page 721</a> |

---

# Client Side Policies

---

## BindingEstablishmentPolicy

### Policy Tag

IT\_CORBA:BINDING\_ESTABLISHMENT\_POLICY\_D

### Data Values

A client's `BindingEstablishmentPolicy` is determined by the members of its `BindingEstablishmentPolicyValue`, which is defined as follows:

```
struct BindingEstablishmentPolicyValue
{
 TimeBase:TimeT relative_expiry;
 unsigned short max_binding_iterations;
 unsigned short max_forwards;
 TimeBase:TimeT initial_iteration_delay;
 float backoff_ratio;
};
```

### See Also

[“BindingEstablishmentPolicy” on page 239](#)

---

## RelativeBindingExclusiveRoundtripTimeoutPolicy

### Policy Tag

IT\_CORBA:RELATIVE\_BINDING\_EXCLUSIVE\_ROUNDTRIP\_TIMEOUT\_POLICY\_D

### Data Values

This policy's value is set in 100-nanosecond units.

### See Also

[“RelativeBindingExclusiveRoundtripTimeoutPolicy” on page 242](#)

---

## RelativeBindingExclusiveRequestTimeoutPolicy

**Policy Tag**

IT\_CORBA:RELATIVE\_BINDING\_EXCLUSIVE\_REQUEST\_TIMEOUT\_POLICY\_D

**Data Values**

This policy's value is set in 100-nanosecond units.

**See Also**

[“RelativeBindingExclusiveRequestTimeoutPolicy” on page 242](#)

---

## RelativeConnectionCreationTimeoutPolicy

**Policy Tag**

IT\_CORBA:RELATIVE\_CONNECTION\_CREATION\_TIMEOUT\_POLICY\_D

**Data Values**

The policy's value is set in 100-nanosecond units.

**See Also**

[“RelativeConnectionCreationTimeoutPolicy” on page 242](#)

---

## InvocationRetryPolicy

**Policy Tag**

IT\_CORBA:INVOCATION\_RETRY\_POLICY\_D

**Data Values**

A client's `InvocationRetryPolicy` is determined by the members of its `InvocationRetryPolicyValue`, which is defined as follows:

```
struct InvocationRetryPolicyValue
{
 unsigned short max_retries;
 unsigned short max_rebinds;
 unsigned short max_forwards;
 TimeBase::Time_t initial_retry_delay;
 float backoff_ratio;
};
```

**See Also**

[“InvocationRetryPolicy” on page 242](#)

---

# POA Policies

---

## ObjectDeactivationPolicy

### Policy Tag

`IT_PortableServer::OBJECT_DEACTIVATION_POLICY_D`

### Data Values

Three settings are valid for this policy:

- |                                |                                                                                                                                                                                                                       |
|--------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>DELIVER (default)</code> | The object deactivates only after processing all pending requests, including any requests that arrive while the object is deactivating.                                                                               |
| <code>DISCARD</code>           | The POA rejects incoming requests with an exception of <code>TRANSIENT</code> . Clients should be able to reissue discarded requests.                                                                                 |
| <code>HOLD</code>              | Requests block until the object deactivates. A POA with a <code>HOLD</code> policy maintains all requests until the object reactivates. However, this policy can cause deadlock if the object calls back into itself. |

### See Also

[“Setting deactivation policies” on page 333](#)

---

## PersistentModePolicy

### Policy Tag

`IT_PortableServer::PERSISTENCE_MODE_POLICY_D`

### Data Values

The only valid value for this policy is

`IT_PortableServer::DIRECT_PERSISTENCE.`

### See Also

[“Direct persistence” on page 298](#)

---

## WellKnownAddressingPolicy

### Policy Tag

IT\_CORBA:WELL\_KNOWN\_ADDRESSING\_POLICY\_ID

### Data Values

This policy takes a string that maps to the prefix of the configuration variable listing the well known address.

### See Also

[“Direct persistence” on page 298](#)

---

## WorkQueuePolicy

### Policy Tag

IT\_WorkQueue:WORK\_QUEUE\_POLICY\_ID

### Data Values

This policy takes a `WorkQueue` object.

### See Also

[“Creating the WorkQueue” on page 320](#)

---

# Security Policies

For more detailed information on the following policies see the *CORBA SSL/TLS Guide*.

---

## SessionCachingPolicy

### Policy Tag

`IT_TLS_API:TLS_SESSION_CACHING_POLICY`

### Data Values

The following settings are valid for this policy:

|                                            |                                                                                         |
|--------------------------------------------|-----------------------------------------------------------------------------------------|
| <code>CACHE_NONE</code> ( <b>default</b> ) | The ORB does not cache session data.                                                    |
| <code>CACHE_CLIENT</code>                  | The ORB will cache session data for client side of a connection.                        |
| <code>CACHE_SERVER</code>                  | The ORB will cache session data for server side of a connection.                        |
| <code>CACHE_SERVER_AND_CLIENT</code>       | The ORB stores session information for both the client and server side of a connection. |

---

## MaxChainLengthPolicy

### Policy Tag

`IT_TLS_API:TLS_MAX_CHAIN_LENGTH_POLICY`

### Data Values

This policy takes an integer.

---

## CertConstraintsPolicy

### Policy Tag

`IT_TLS_API:TLS_CERT_CONSTRAINTS_POLICY`

### Data Values

This policy takes an `IT_TLS_API:CertConstraints` object.

---

## CertValidatorPolicy

### Policy Tag

`IT_TLS_API:TLS_CERT_VALIDATOR_POLICY`

### Data Values

This policy takes a `IT_TLS:CertValidator` object.

---

# Firewall Proxy Policies

For more information on the firewall proxy service see the *Application Server Platform Administrator's Guide*.

---

## InterdictionPolicy

### Policy Tag

`IT_FPS::INTERDICTION_POLICY_D`

### Data Values

- `PROCEED` (**default**) This is the default behavior of the firewall proxy service plug-in. A POA with its `INTERDICTION` policy set to `PROCEED` will be proxified.
- `PREVENT` This setting tells the firewall proxy service plug-in to not proxify the POA. POAs with their `INTERDICTION` policy set to `PREVENT` will not use the firewall proxy service and requests made on objects under its control will come directly from the requesting clients.



# Index

## A

- Abstract storage home
    - defined 543
    - defining 546
    - factory operation 549
    - forward declaration 550
    - inheritance 550
    - keys 547
    - operations 549
  - Abstract storage type
    - defined 543
    - defining 544
    - definition syntax 544
    - forward declaration 545
    - inheritance 544
      - from storage object 545
    - operations 545
    - state members 544
  - activate()
    - calling on POAManager 84, 311
  - activate\_object() 81, 258, 303, 305
  - activate\_object\_with\_id() 258, 303, 305
  - Active object map 286
    - disabling 295
    - enabling 295
    - using with servant activator 327
  - add\_ior\_component() 654
  - addMember() 525
  - \_add\_ref() 273
  - AliasDef 461
  - allocate\_slot\_id() 685
  - ant 54
  - Any type 393–433
    - extracting user-defined types 399
    - extracting values from 398
      - alias 407
      - array 402
      - Boolean 401
      - bounded string alias 406
      - Char 401
      - Octet 401
      - string 404
      - WChar 401
      - wstring 404
    - extraction operators 398
    - inserting user-defined types 396
    - inserting values 395
      - alias 406
      - array 402
      - Boolean 401
      - bounded string alias 406
      - Char 401
      - Octet 401
      - string 403
      - WChar 401
      - wstring 403
    - insertion operators 395
    - memory management 396, 398
    - querying type code 408
  - Application
    - running 32, 38
  - arguments() 447
  - Arithmetic operators 132
  - ArrayDef 462
  - Array type
    - \_forany 402
  - Association
    - constructors 562
    - operations 563
  - Asynchronous method invocations 347–357
    - client implementation 355
    - implied IDL 350
    - reply handlers 351
  - Attribute
    - client-side C++ mapping for 210
    - genie-generated 62
    - in IDL 103
    - readonly 51
- ## B
- BAD\_TYPECODE 407
  - base flag 55
  - Binding
    - setting delay between tries 240
    - timing out on 240
    - timing out on forward tries 240

- timing out on IP address resolution 242
  - timing out on retries 240
- BindingEstablishmentPolicy 239
- Binding iterator 507
- Binding list 506
- Boolean
  - constant in IDL 130
- Bounded strings 403
- build.xml 54

## C

- CannotProceed exception 505
- CDR encapsulation 648
- ChannelAlreadyExists exception 611, 629
- Character
  - constant in IDL 130
- Client
  - asynchronous method invocations 347
  - building 32
  - developing 66, 187
  - dummy implementation 54
  - exception handling 365
  - generating 29, 36, 53
  - implementing 31, 37, 66
  - initializing ORB runtime 164, 209
  - interceptors, see Client interceptors
  - invoking operations 190, 210–232
  - quality of service policies 233
    - creating PolicyList 173
    - effective policy 171
    - getting policy overrides 176
    - object management 178, 180
    - ORB PolicyManager 175, 180
    - setting policy overrides 176
    - thread management 175, 180
  - reply handlers for asynchronous method invocations 355
  - timeout policies 236
- Client interceptors
  - aborting request 661
  - changing reply 662
  - evaluating tagged component 668
  - interception point flow 660
  - interception points 657, 659, 664
  - location forwarding 661
  - normal reply processing 660
  - registering 689
  - tasks 667
- Client policies

- RebindPolicy 234
  - SyncScopePolicy 235
  - timeout 236
- Client proxy 69, 188
  - class definition 189
  - deallocating 193
  - reference counting 192
- ClientRequestInfo 643
  - interface 664
- ClientRequestInterceptor 642
  - interface 657
- Client-side C++ mapping
  - attributes 210
  - operations 210
  - parameter passing 211
    - rules 229
  - parameters
    - fixed-length array 215
    - fixed-length complex 213
    - object reference 227
    - \_out-type 220
    - simple 212
    - string 217
    - variable-length array 225
    - variable-length complex 223
- Codec
  - creating 649, 689
  - decoding service context 648
  - encoding service context 648
  - interface 648
  - operations 648
- Codec factory 649
  - obtaining 689
- codec\_factory() 649, 689
- Code generation toolkit
  - See also Genie-generated application
  - idlgen utility 36
  - packaged genies 135
  - wizard 25
- Command-line arguments 76
- Compiling
  - application 71
  - IDL 55
  - PSDL 543
- completed() 369
- component\_count() 422
- Configuration 12
- Connector object 566
- Constant definition

- boolean 130
- character 130
- enumeration 131
- fixed-point 131
- floating point 129
- in IDL 129
- integer 129
- octet 131
- string 130
- wide character 130
- wide string 130
- Constant expressions
  - in IDL 132
- consumer
  - connecting to event channel 618
  - connecting to proxy supplier 620
  - disconnecting from event channel 623, 638
  - implementing 618
  - instantiating 612
- consumer admin
  - obtaining default 619
- Contained interface 467
  - Description structure 471
- Container interface 469
  - operations 474
- contents() 476
- corbaloc 207
- corbaname 503
- CORBA object, see Object
- CosNotifyChannelAdmin module 613
- CosTypedEventChannelAdmin module 631
- cpp\_poa\_genie.tcl 36, 53
- cpp\_poa\_genie.tcl genie 161
  - all option 140
  - complete/-incomplete options 154
  - default\_poa option 146
  - defined 135
  - dir option 158
  - include option 143
  - interface specification 142
  - refcount/-norefcoun options 147
  - servant/-noservant options 146
  - servant option 144
  - server option 148
  - strategy options 149
  - syntax 138
  - threads/-nothreads options 149
  - tie option 145
  - v/-s options 158

- cpp\_poa\_op.tcl genie 161
  - defined 135
- \_create() 80
- create\_active() 525
- create\_channel() 610
- create\_id\_assignment\_policy() 301
- create\_id\_uniqueness\_policy() 302
- create\_lifespan\_policy() 298
- create\_policy()
  - calling on client ORB 173
- create\_random() 525
- create\_reference() 344
- create\_reference\_with\_id() 344
- \_create\_request 443
- create\_round\_robin() 525, 535
- create\_transactional\_session() 567
- create\_typed\_channel() 627
- ctx() function 442
- Current, in portable interceptors
  - See PICurrent
- current\_component() 422
- current\_member\_kind() 427, 432
- current\_member\_name() 427, 432

## D

- DCE UID repository ID format 480
- deactivate()
  - calling on POAManager 312
- decode() 648
- decode\_value() 649
- \_default\_POA() 308
  - overriding 309
- Default servant 286, 340–343
  - registering with POA 297, 343
- default\_supplier\_admin() 613
- Deferred synchronous request 448
- def\_kind 455
- describe() 471
- describe\_contents() 476
- destroy() 86, 166, 455
- DII 437
  - See also Request object
  - creating request object 439
  - deferred synchronous request 448
  - invoking request 446
- DIRECT\_PERSISTENCE policy 298
- discard\_requests()
  - calling on POAManager 312
- disconnect operation

- consumer 623
    - supplier 617, 633
  - disconnect\_structured\_push\_supplier() 623
  - discriminator\_kind() 429
  - DSI 449
    - dynamic implementation routine 451
  - Dynamic Any, see DynAny
  - Dynamic implementation routine 451
  - Dynamic invocation interface, see DII
  - Dynamic skeleton interface, see DSI
  - DynAny 409
    - assignment 410
    - comparing 410
    - conversion to Any 410
    - copying 410
    - creating 412
    - destroying 410
    - DynArray interface 429
    - DynEnum interface 424
    - DynFixed interface 431
    - DynSequence interface 429
    - DynStruct interface 426
    - DynUnion interface 428
    - DynValueBox interface 433
    - DynValue interface 431
    - extraction operations 420
    - factory operations 412
    - initializing from another 410
    - insertion operations 418
    - iterating over components 422
    - obtaining type code 411
  - DynAnyFactory interface 412
- E**
- encode() 648
  - encode\_value() 649
  - EndOfAssociationCallback 568
  - enum data type 122
  - EnumDef 461
  - Enumeration
    - constant in IDL 131
  - equal() 384
  - equivalent() 384
  - establish\_components() 652
  - etherealize() 332
  - event
    - obtaining 621
      - pull consumer 622
      - push consumer 622
    - sending 615
      - pull supplier 616
      - push supplier 616
  - event channel
    - connecting consumer 618
    - connecting supplier 612
    - creating 610
    - disconnecting consumer 623
    - disconnecting supplier 617, 633
    - finding by id 610
    - finding by name 610
    - listing all by names 610
    - obtaining 609
  - event channel factory
    - OMG operations 610
  - event communication
    - mixing push and pull models 605
    - pull model 605
  - Event handling
    - in server 279
  - Exceptions 359–377
    - handling in clients 365
    - in IDL 104
    - specification in server skeleton class 253
    - system 367
    - system codes 369
    - throwing in server 373
  - Explicit object activation 258, 305
    - policy 303
- F**
- Factory operation
    - in PSDL 549
  - find\_channel() 610
  - find\_channel\_by\_id() 610
  - find\_group() 526, 535
  - find\_typed\_channel() 627
  - find\_typed\_channel\_by\_id() 627
  - FixedDef 462
  - Fixed-point
    - constant in IDL 131
  - Floating point
    - constant in IDL 129
  - for\_consumers() 619, 636
  - for\_suppliers() 630
  - Forward declaration
    - abstract storage home 550
    - abstract storage type 545
    - in IDL 110

**G**

Genie-generated application 12, 135–161  
 See also `cpp_poa_genie.tcl` `genie`, `cpp_poa_op.tcl`  
`genie`  
 compiling 159  
 completeness of code 154  
 component specification  
   all 140  
   included files 143  
   servant classes only 144  
   server only 148  
`_create()` 64  
 directing output 158  
 generated attribute 62  
 interface selection 142  
 object mapping policy  
   servant locator 150  
   use active object map only 150  
   use servant activator 150  
 overriding `_default_POA()` 146  
 POA thread policy 149  
 reference counting 147  
 servant class inheritance 146  
 signature 160  
 tie-based servants 145  
 verbosity settings 158  
`get_association_status()` 572  
`get_boxed_value()` 433  
`get_boxed_value_as_dyn_any()` 433  
`get_client_policy()` 182  
`get_compact_typecode()` 385  
`get_discriminator()` 428  
`get_effective_component()` 668  
`get_effective_policy()` 653  
`_get_interface()` 474  
`get_length()` 430  
`get_members()` 426, 432  
`get_members_as_dyn_any()` 427, 432  
`get_policy()` 182  
`get_policy_overrides()` 183  
   calling on ORB PolicyManager 176  
   calling on thread PolicyCurrent 176  
`get_response()` 448  
`get_typed_consumer()` 632  
`get_value()` 431

**H**

`hash()` 197

`has_no_active_member()` 429  
 Hello World! example 23  
`hold_requests()`  
   calling on POAManager 311

**I**

IDL 93  
 attribute in 51  
 attributes in 103  
 compiling 55  
 constant expressions in 132  
 empty interfaces 105  
 exceptions 359–377  
 exceptions in 104  
 interface definition 97  
 interface repository definitions 453  
   object types 457  
 module definition 95  
 name scoping 95  
 one-way operations in 101  
 operation in 51, 100  
 parameters in 100  
 pragma directives 482  
 precedence of operators 132  
 prefix pragma 483  
 user-defined types 128  
 version pragma 483  
 IDL compiler 55  
   generated files 55  
   generating implied IDL 350  
   options  
     `-base` 55  
     `-flags` 55  
     `-poa` 55  
   output 55  
   populating interface repository 454  
 idlgen utility 53  
 IMPLICIT\_ACTIVATION policy 303, 306  
 Implicit object activation 257, 306  
   overriding default POA 309  
   policy 303  
 Implied IDL 350  
   attribute mapping 350  
   operation mapping 350  
   `sendc_get` operation 350  
   `sendc_operation` 350  
 Inheritance  
   implementing by 61  
   in abstract storage home 550

- in interfaces 106
    - in servant classes 276, 277
    - storage home 553
  - Initial naming context
    - obtaining 494
  - Initial reference
    - registering 686
  - inout parameters 101
  - in parameters 101
  - Integer
    - constant in IDL 129
  - Interception points 642
    - client flow 660
    - client interceptors 657, 659, 664
    - client-side data 643, 664
    - IOR data 643
    - IOR interceptors 652
    - request data 643, 655
    - server flow 673
    - server interceptors 672, 678
    - server-side data 643, 677
    - timeout constraints 656
  - Interceptor interface 642
  - Interceptors, see Portable interceptors
  - Interface
    - client proxy for 188
    - components 99
    - defined in IDL 97
    - dynamic generation 435
    - empty 105
    - forward declaration of 110
    - inheritance 106
    - inheritance from Object interface 108
    - multiple inheritance 107
    - overriding inherited definitions 108
  - Interface, in IDL definition 51
  - InterfaceDef 461
  - Interface Definition Language, see IDL
  - InterfaceNotSupported exception 631
  - Interface repository 453–484
    - abstract base interfaces 456
    - browsing 474
    - Contained interface 467
    - Container interface 469
    - containment 464
    - destroying object 455
    - finding objects by ID 477
    - getting information from 474
      - object interface 474
      - getting object's IDL type 462
    - object descriptions 471
      - getting 476
    - objects in 455
    - object types 455
      - named 461
      - unnamed 462
    - populating 454
    - repository IDs 480
      - setting prefixes 482
      - setting version number 483
  - Interoperable Object Reference, see IOR
  - InvalidName exception 505
  - InvocationRetryPolicy 242
  - IOR 285
    - string format 205
    - usage 207
  - IORInfo 643
    - interface 652
  - IORInterceptor 642
    - See also IOR interceptors
    - interface 652
  - IOR interceptors 652
    - adding tagged components 647, 654
    - interception point 652
    - registering 689
  - IRObjcet interface 455
    - \_is\_a() 196
    - \_is\_equivalent() 196
  - Isolation level
    - specifying for session 567
  - item() 447
  - IT\_ServantBaseOverrides class 310
  - IT\_THROW\_DECL macro 61
- ## K
- Key
    - defined in abstract storage home 547
      - composite 547
      - simple 547
    - primary declaration in storage home 553
  - kind() 385
- ## L
- list\_channels() 610
  - list\_typed\_channels() 627
  - Load balancing 521
    - active selection 527

- example of 528
- selection algorithms 521
- Local repository ID format 481
- Logging 12
- lookup() 474
- lookup\_id() 477
- lookup\_name() 474

## M

- member() 429
- member\_kind() 429
- member\_name() 429
- Memory management
  - string type 37
- minor() 369
- Module
  - in IDL 95
- MULTIPLE\_ID policy 302

## N

- Name binding
  - creating for application object 500
  - creating for naming context 496
  - dangling 510
  - listing for naming context 506
  - removing 510
- NameComponent
  - defined 489
- NamedValue pseudo object type 127
- Name scoping
  - in IDL 95
- Name sequence
  - converting to StringName 493
  - defined 489
  - initializing 492
  - resolving to object 489, 502
  - setting from StringName 492
  - setting name components 492
  - string format 491
- Naming context
  - binding application object to 500
  - binding to another naming context 496
  - destroying 510
  - listing bindings 506
  - orphan 497
  - rebinding application object to 501
  - rebinding to naming context 501
- Naming graph

- binding application object to context 500
- binding iterator 507
- binding naming context to 496
- building programmatically 495
- defined 487
- defining Name sequences 489
- destroying naming context 510
- federating with other naming graphs 512
- iterating over naming context bindings 507
- listing name bindings 506
- obtaining initial naming context 494
- obtaining object reference 502
- rebinding application object to context 501
- rebinding naming context 501
- removing bindings 510
- resolving name 489, 503
- resolving name with corbaname 503
- Naming service 485
  - AlreadyBound exception 501
  - binding iterator 507
  - CannotProceed exception 505
  - defining names 489
  - exceptions 505
  - initializing name sequence 492
  - InvalidName exception 505
  - name binding 487
  - naming context 487
  - NotEmpty exception 510
  - NotFound exception 505
  - representing names as strings 491
  - string conversion operations 491
- Narrowing
  - initial references 77
  - object reference 69
  - \_ptr 198
    - type-safe 200
  - \_var 202
- NativeDef 461
- next() 423
- \_nil()
  - Nil reference 68, 76
- Nil reference 194
- NO\_IMPLICIT\_ACTIVATION policy 303, 305
- \_non\_existent() 196
- NON\_RETAIN policy 295
  - and servant locator 327
- NotFound exception 505

**O**

- Object
  - activating 81, 257
    - activating on demand
      - with servant activator 329
      - with servant locator 335, 338
  - base class 57
  - binding to naming context 500
  - client proxy for 188
  - creating inactive 344
  - deactivating
    - with servant activator 332
    - with servant locator 339
  - defined in CORBA 4
  - explicit activation 258, 305
  - getting interface description 474
  - ID assignment 81, 301
  - implicit activation 257, 306
  - mapping to servant 285
    - options 286
  - rebinding to naming context 501
  - removing from object groups 526
  - request processing policies 296
  - test for equivalence 196
  - test for existence 196
  - test for interface 196
- Object binding
  - transparent rebinding 234
- ObjectDeactivationPolicy 291
- Object group 521
  - accessing from clients 537
  - adding objects to 526, 530
  - creating 525, 530
  - factories 525
  - finding 535
  - group identifiers 525
  - member identifiers 525
  - member structure 536
  - removing 526
  - removing objects from 526
  - selection algorithms 521, 525
- Object pseudo-interface
  - hash() 197
  - inheritance from 108
  - is\_a() 196
  - \_is\_equivalent() 196
  - \_non\_existent() 196
  - operations 195
- Object reference 4
  - adding tagged components 647, 654
  - creating for inactive object 344
  - IOR 285
  - lifespan 298
  - narrowing 69
  - nil 194
  - obtaining with create\_reference() 344
  - obtaining with id\_to\_reference() 82
  - obtaining with \_this() 306
  - operations 195
    - passing as a string 24
    - passing as parameter
      - C++ mapping in client 227
    - persistent 298
    - string conversion 205
      - format 205
    - transient 298
    - \_var type 190
  - object\_to\_string() 83, 205
  - obtain\_notification\_pull\_consumer() 614, 620
  - obtain\_notification\_push\_consumer() 614, 620, 631, 636
  - obtain\_push\_consumer() 614
  - obtain\_typed\_push\_consumer() 631, 632
  - Octet
    - constant in IDL 131
  - og\_factory() 535
  - OMG IDL repository ID format 480
  - One-way requests
    - SyncScopePolicy 235
  - Operation
    - client-side C++ mapping for 210
    - defined in abstract storage home 549
    - defined in abstract storage type 545
    - defined in IDL 100
    - interface repository description 471
    - one-way, defined in IDL 101
  - OperationDef interface 471
  - Operators
    - arithmetic 132
    - precedence of, in IDL 132
  - ORB
    - getting object reference to 164, 209
    - role of 6
  - ORB\_CTRL\_MODEL policy 273, 304
  - ORB flags 76
  - ORB\_init() 68
    - calling in client 164, 209
  - ORB\_init() function 68

- calling in server 76
- ORB initializer 641
  - creating and registering PolicyFactory 688
  - creating Codec objects 649, 689
  - interface 651
  - obtaining Codec factory 649, 689
  - registering initial reference 686
  - registering portable interceptors 684, 689
  - registering with application 691
  - tasks 651, 685
- ORBInitInfo 651
- ORB PolicyManager 178
- ORB runtime
  - destroying 166
  - event handling 279
  - initializing in client 66, 164, 209
  - initializing in server 76
  - polling for incoming requests 279
  - shutting down 85, 166
- Orphaned naming context 497
- out parameters 101
- \_out-type parameters
  - C++ mapping in client 220

## P

- ParameterList
  - settings for transaction session 568
- Parameters
  - C++ mapping in client 211
    - fixed-length array 215
    - fixed-length complex 213
    - object reference 227
    - \_out types 220
    - rules for passing 229
    - simple 212
    - string 217
    - variable-length array 225
    - variable-length complex 223
  - C++ mapping in server 259–272
    - fixed-length array 263
    - fixed-length complex 261
    - object reference 271
    - simple 260
    - string 265
    - variable-length array 269
    - variable-length complex 267
  - defined in IDL 51, 100
  - direction 100
  - inout types 101
    - in types 101
    - out types 101
    - setting for request object 440
  - perform\_work() 279
  - PersistenceModePolicy 292
  - PERSISTENT policy 298
  - Persistent State Definition Language, see PSDL
  - Persistent State Service, see PSS
  - PICurrent 641
    - allocating slot 685
    - defined 645
    - interface 645
    - obtaining 685
  - Plug-in 10
  - POA 283–312
    - activating object in 81, 257
    - active object map 286, 295
    - attaching PolicyList 179, 289
    - creating 77, 78, 287
    - default servant 286, 340–343
    - genie-generated
      - active object map 150
      - servant activator 150
      - use servant locator 150
    - mapping object to servant through inheritance 251–253
    - POAManager 78, 84, 311
    - registering default servant 297, 343
    - registering servant activator 334
    - registering servant locator 339
    - registering servant manager 297
    - root POA 77, 287
    - servant manager 286
    - skeleton class 249
  - POA manager 78, 311
    - states 84, 311
  - POA policies
    - attaching to new POA 179, 289
    - constants
      - DIRECT\_PERSISTENCE 298
      - IMPLICIT\_ACTIVATION 303
      - MULTIPLE\_ID 302
      - NO\_IMPLICIT\_ACTIVATION 303
      - NON\_RETAIN 295
      - ORB\_CTRL\_MODEL 304
      - PERSISTENT 298
      - RETAIN 295
      - SINGLE\_THREAD\_MODEL 304
      - SYSTEM\_ID 301

- TRANSIENT 298
- UNIQUE\_ID 302
- USE\_ACTIVE\_OBJECT\_MAP\_ONLY 296
- USE\_DEFAULT\_SERVANT 297
- USER\_ID 301
- USE\_SERVANT\_MANAGER 297
- factories for Policy objects 290
- ID assignment 301
- ID uniqueness 302
- object activation 303
- ObjectDeactivationPolicy 291
- object lifespan 298
- ORB\_CTRL\_MODEL 273
- PersistenceModePolicy 292
- proprietary 291
- request processing 296
- root POA 293
- servant retention 295
- setting 79, 289
- threading 304
- WellKnownAddressingPolicy 292
- Policies
  - creating PolicyFactory 650
  - getting 185
- PolicyCurrent 180
  - interface operations 175
- PolicyFactory 641
  - creating and registering 688
  - interface 650
- PolicyList
  - attaching to POA 179, 289
  - creating for client 173
  - creating for POA 289
- PolicyManager 180
  - interface operations 175
  - setting ORB policies 178
- poll\_response 448
- Portable interceptors 13, 639
  - client interceptors, see Client interceptors
  - components 641
  - interception points, see Interception points
  - IOR interceptors, see IOR interceptors
  - ORB initializer, see ORB initializer
  - PICurrent, see PICurrent
  - policy factory, see PolicyFactory
  - registering 684, 689
  - registering with Orbix configuration 692
  - server interceptors, see Server interceptors
  - service context, see Service context
  - tagged component, see Tagged component
  - types 642
- Portable Object Adapter, see POA
- post\_init() 684
- postinvoke() 337, 339
- Pragma directives, in IDL 482
- Prefix pragma 483
- pre\_init() 684
- preinvoke() 337, 338
- PrimitiveDef 462
- Proxy, see Client proxy
- proxy consumer
  - connecting supplier 614
  - creating 613
  - interfaces 613
- proxy supplier 615
  - connecting consumer 620
  - creating 619
  - pull operations 622
- PSDL 540–554
  - abstract storage home 546
  - abstract storage type 544
  - C++ mapping 585–600
    - abstract storagetype 588
    - operation parameters 595
    - Ref\_var class 592
    - state members 593
    - storagehome 598
    - storagetype 596
  - compiling 543
  - keywords 540
  - language mappings
    - equivalent local interfaces 587
  - storage home 541
  - storage type
    - defined 541
- Pseudo object types
  - in IDL definition 127
- PSS 539–600
  - accessing storage objects 555
  - defining data 540
    - see also PSDL
  - querying data 577
- \_ptr object reference type 190, 198–200
  - duplicating 198
  - narrowing 198
    - type-safe 200
  - releasing 198
  - widening 198

- pull() 622
- pull consumer
  - obtaining messages 621, 622
- pull model 605
- pull supplier
  - obtaining proxy consumer 614, 620
- push() 616, 622
- push and pull model mixed 604
- push consumer
  - obtaining messages 622
- push model 604
- push supplier
  - obtaining a typed proxy consumer 631
  - obtaining proxy consumer 614, 620, 636

**Q**

- Quality of service policies 233
  - creating PolicyList 173
  - effective policy 171, 233
  - getting overrides
    - for ORB 176
    - for thread 176
  - managing
    - object 182
    - ORB 175
    - thread 175
  - object management 178, 180
  - ORB PolicyManager 175, 180
  - setting overrides
    - for ORB 176
    - for thread 176
  - thread management 175, 180
- Querying data 577

**R**

- RebindPolicy 234
- receive\_exception() 659
- receive\_other() 659
- receive\_reply() 659
- receive\_request() 672
- receive\_request\_service\_contexts() 672
- RefCountServantBase 273
- Reference counting 273
  - genie-generated 147
- Reference representation 551
- Ref\_var Classes 592
- register\_orb\_initializer() 691
- RelativeBindingExclusiveRequestTimeoutPolicy 242

- RelativeBindingExclusiveRoundtripTimeoutPolicy 24
  - 2
- RelativeConnectionCreationTimeoutPolicy 242
- RelativeRequestTimeoutPolicy 238
- RelativeRoundtripTimeoutPolicy 237
- remove\_member() 526
- \_remove\_ref() 273
- ReplyEndTimePolicy 238
- Reply handlers 351
  - exceptional replies 353
  - implementing on client 355
  - normal replies 353
- \_request 440
- RequestEndTimePolicy 239
- RequestInfo 643
  - interface 655
- Request object
  - creating 439
    - context parameter 442
    - operation parameters 440
    - return type 440
    - with\_create\_request 443
    - with\_request 440
  - invoking 446
  - obtaining results 447
- resolve\_initial\_references()
  - InterfaceRepository 474
  - NameService 494
  - PICurrent 685
  - POA 77
  - PSS 556
  - TransactionCurrent 556
- resolve\_str() 491
- RETAIN policy 295
  - and servant activator 327
- return\_value() 447
- rewind() 423
- Root POA
  - policies 293
- run() 84
- Running an application 72

**S**

- seek() 423
- sendc\_get\_operation 350
- send\_c operation 350
- send\_deferred 448
- send\_exception() 672
- send\_other() 672

- send\_poll() 659
- send\_reply() 672
- send\_request() 659
- sequence data type 125
- SequenceDef 462
- Servant
  - caching 336
  - etherealized
    - by servant activator 332
    - by servant locator 339
  - genie-generated
    - overriding default POA 146
    - reference counting 147
  - implementation class 62, 254
  - incarnated
    - by servant locator 338
  - incarnating multiple objects 302
  - inheritance from POA skeleton class 249
  - inheritance from ServantBase 252
  - instantiating 257
  - mapping to object 285
    - options 286
  - reference counting 273
  - tie-based 274
- Servant activator 329–335
  - deactivating objects 332
  - etherealizing servants 332
  - registering with POA 334
  - required policies 297
- ServantBase 252
- Servant class
  - creating 254–255
  - genie-generated 144
    - inheritance 146
  - inheritance 276
  - interface inheritance 277
  - multiple inheritance 278
- Servant locator 335–339
  - activating objects 338
  - caching servants 336
  - deactivating objects 339
  - etherealizing servants 339
  - incarnating servants 338
  - registering with POA 339
  - required policies 297
- Servant manager 286, 325–344
  - registering with POA 297, 327
  - set for POA 297
- Server
  - building 29
  - compiling 282
  - defined in CORBA 8
  - dummy implementation 54
  - event handling 279
  - generating 26, 36, 53
  - genie-generated 148
    - object mapping options 150
    - POA thread policy 149
  - implementing 28, 36, 59
  - initialization 74
  - processing requests, see POA
  - servant reference counting 273
  - shutting down 85
  - termination handler 85, 280
  - throwing exceptions 373
- Server interceptors 671
  - aborting request 674
  - changing reply 675
  - getting server policy 680
  - getting service contexts 681
  - interception point flow 673
  - interception points 672, 678
  - registering 689
  - tasks 680
  - throwing exception 673
- ServerRequestInfo 643
  - interface 677
- ServerRequestInterceptor 642
  - interface 671
- ServerRequest pseudo-object 451
- Server-side C++ mapping
  - fixed-length array parameters 263
  - fixed-length complex parameters 261
  - object reference parameters 271
  - parameter passing 259–272
  - POA skeleton class 249, 251–253
  - simple parameters 260
  - skeleton class
    - method signatures 253
  - string parameters 265
  - variable-length array parameters 269
  - variable-length complex parameters 267
- Service context 641, 644
  - decoding data 648
  - encoding data 641, 648
  - IDs 644
- Services 32, 34, 39, 40, 72
  - encapsulating ORB service data 644

- Session
    - management operations 574
  - SessionManager 559
    - parameters 561
  - set\_boxed\_value() 433
  - set\_boxed\_value\_as\_dyn\_any() 433
  - set\_discriminator() 428
  - set\_length() 430
  - set\_members() 426, 432
  - set\_members\_as\_dyn\_any() 427, 432
  - set\_member\_timeout() 527
  - set\_policy\_overrides() 183
    - calling on ORB PolicyManager 176
    - calling on thread PolicyCurrent 176
  - set\_return\_type 440
  - set\_servant() 297
  - set\_servant\_manager() 297
  - set\_to\_default\_member() 428
  - set\_to\_no\_active\_member() 428
  - set\_value() 431
  - shutdown() 69, 85, 166
  - Signal handling 280
  - SINGLE\_THREAD\_MODEL policy 304
  - Skeleton class
    - dynamic generation 451
    - method signatures 253
    - naming convention 252
  - Skeleton code 55
  - Smart pointers 190
  - State member
    - in abstract storage type 544
    - in storage type 551
  - Storage home
    - defined 541
    - implementing 543, 553
    - inheritance 553
    - instance 555
    - primary key declaration 553
  - Storage object
    - accessing 555, 564
    - associating with CORBA object 578
    - defining 544
    - incarnation 555
    - thread safety 579
  - Storage type
    - defined 541
    - implementing 543, 551
    - reference representation 551
    - state members 551
  - String
    - constant in IDL 130
  - StringDef 462
  - string\_dup() 37, 65
  - StringName
    - converting to Name 492
    - using to resolve Name sequence 503
  - string\_to\_object() 68, 205
  - String\_var 38
  - struct data type 123
  - StructDef 461
  - Stub code 55
  - supplier
    - connecting to proxy consumer 615
    - connecting to typed proxy consumer 632
    - disconnecting from event channel 617, 633
    - implementing 612
  - supplier admin
    - obtaining 613, 630
    - obtaining default 613
  - SyncScopePolicy 235
  - System exceptions 367
    - codes 369
    - throwing 377
  - SYSTEM\_ID policy 301
- ## T
- Tagged component 641
    - adding to object reference 647, 654
    - defined 647
    - evaluated by client 668
  - \_tc\_<type> 391
  - TCKind enumerators 380
  - Termination handler
    - in server 280
  - \_this() 257, 303, 306–309
    - overriding default POA 309
  - Threading 12
    - POA policy 304
    - with storage objects 579
  - Tie-based servants 274
    - compared to inheritance approach 275
    - creating 274
    - genie-generated 145
    - removing from memory 275
  - Timeout policies 236
    - absolute times 236
    - binding retries 240
    - binding time limits 240

- delay between binding tries 240
  - forwards during binding 240
  - invocation retries 242
    - delay between 243
    - maximum 243
    - maximum forwards 243
    - maximum rebinds 243
  - propagating to portable interceptors 656
  - reply deadline 238
  - request and reply time 242
    - excluding binding 237
  - request delivery 238
    - excluding binding 242
    - resolving IP addresses 242
  - request delivery deadline 239
  - to\_name() 491
  - to\_string() 491
  - Transactional session
    - activating 569
    - creating 566
      - access mode 567
      - callback object 568
      - isolation level 567
      - ParameterList settings 568
    - EndOfAssociationCallback 568
    - managing 566, 571
  - Transaction resource
    - associating with SessionManager 562
  - TRANSIENT policy 298
  - try\_pull() 616, 622
  - try\_pull\_structured\_event() 616
  - TxSessionAssociation interface 562
  - type() 406
  - Type code
    - getting from any type 408
    - getting from DynAny 411
  - TypeCode interface 462
  - TypeCode pseudo object type 127
  - Type codes 379–391
    - compacting 385
    - comparing 384
    - constants 390
    - getting TCKind of 386
    - operations 383
    - TCKind enumerators 380
    - type-specific operations 386
    - user-defined 390
  - typed consumer
    - connecting to proxy supplier 637
  - typed consumer admin
    - obtaining default 636
  - typedef 128
  - TypedDef 461
  - Type definition
    - in IDL 128
  - typed event channel
    - connecting supplier 630
    - creating 627
    - disconnecting consumer 638
    - finding by id 627
    - finding by name 627
    - listing all by names 627
    - obtaining 626
  - typed event channel factory
    - Orbix operations 627
  - typed proxy consumer
    - connecting supplier 631
    - creating 631
    - interfaces 631
  - typed proxy supplier
    - connecting consumer 637
    - creating 636
  - typed push model 606
  - typed supplier admin
    - obtaining default 630
- ## U
- Union
    - in IDL definition 123
  - UnionDef 461
  - UNIQUE\_ID policy 302
  - update\_member\_load() 527
  - USE\_ACTIVE\_OBJECT\_MAP\_ONLY policy 296
  - USE\_DEFAULT\_SERVANT policy 297
  - USER\_ID policy 301
  - USE\_SERVANT\_MANAGER policy 297
- ## V
- validate\_connections() 183
  - value() 447
  - ValueBoxDef 461
  - ValueDef 461
  - \_var object reference type 190, 201–204
    - assignment operator 202
    - class members 201
    - constructors 201
    - conversion operator 202

- default constructor 201
- destructor 202
- explicit conversion operator 202
- in() 202
- indirection operator 202
- inout() 202
- narrowing 202
- out() 202
- widening 202

Version pragma 483

## **W**

- WellKnownAddressingPolicy 292
- Wide character
  - constant in IDL 130
- Widening
  - \_ptr 198
  - assignment 198
  - \_var 202
- Wide string
  - constant in IDL 130
- Wizard
  - for code generation 25
- work\_pending() 279
- WorkQueuePolicy 313
- WStringDef 462

