



CORBA Session Management
Guide, C++

Version 6.1, December 2003

IONA, IONA Technologies, the IONA logo, Orbix, Orbix/E, Orbacus, Artix, Orchestrator, Mobile Orchestrator, Enterprise Integrator, Adaptive Runtime Technology, Transparent Enterprise Deployment, and Total Business Integration are trademarks or registered trademarks of IONA Technologies PLC and/or its subsidiaries.

Java and J2EE are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and other countries.

CORBA is a trademark or registered trademark of the Object Management Group, Inc. in the United States and other countries. All other trademarks that appear herein are the property of their respective owners.

While the information in this publication is believed to be accurate, IONA Technologies PLC makes no warranty of any kind to this material including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. IONA Technologies PLC shall not be liable for errors contained herein, or for incidental or consequential damages in connection with the furnishing, performance or use of this material.

COPYRIGHT NOTICE

No part of this publication may be reproduced, stored in a retrieval system or transmitted, in any form or by any means, photocopying, recording or otherwise, without prior written consent of IONA Technologies PLC. No third party intellectual property right liability is assumed with respect to the use of the information contained herein. IONA Technologies PLC assumes no responsibility for errors or omissions contained in this book. This publication and features described herein are subject to change without notice.

Copyright © 2001–2003 IONA Technologies PLC. All rights reserved.

All products or services mentioned in this manual are covered by the trademarks, service marks, or product names as designated by the companies who market those products.

Updated: 23-Oct-2003

M 3 1 5 6

Contents

Preface	v
Chapter 1 Using the Leasing Plug-In	1
The Leasing Framework	2
A Sample Leasing Application	6
Using the Leasing Plug-In on the Client Side	8
Using the Leasing Plug-In on the Server Side	10
Implement the LeaseCallback Interface	12
Use IT_Leasing::Current to Track Client Sessions	15
Advertise the Lease	19
Configure the Server-Side Plug-In	21
Appendix A Leasing Plug-In Configuration Variables	23
Common Variables	24
Server-Side Variables	25
Appendix B Sample Leasing Plug-In Configuration	27
Appendix C Leasing IDL Interfaces	31
Index	35

CONTENTS

Preface

This book describes the Orbix session management capability, which is based on the Orbix leasing plug-in.

Audience

This guide is aimed at developers of Orbix applications. Before reading this guide, you should be familiar with the Object Management Group IDL and the C++ language.

Additional resources

The [IONA knowledge base](http://www.iona.com/support/knowledge_base/index.xml) (http://www.iona.com/support/knowledge_base/index.xml) contains helpful articles, written by IONA experts, about the Orbix and other products. You can access the knowledge base at the following location:

The [IONA update center](http://www.iona.com/support/updates/index.xml) (<http://www.iona.com/support/updates/index.xml>) contains the latest releases and patches for IONA products:

If you need help with this or any other IONA products, contact IONA at support@iona.com. Comments on IONA documentation can be sent to docs-support@iona.com.

Typographical conventions

This guide uses the following typographical conventions:

Constant width Constant width (courier font) in normal text represents portions of code and literal names of items such as classes, functions, variables, and data structures. For example, text might refer to the `CORBA::Object` class.

Constant width paragraphs represent code examples or information a system displays on the screen. For example:

```
#include <stdio.h>
```

Italic Italic words in normal text represent *emphasis* and *new terms*.

Italic words or characters in code and commands represent variable values you must supply, such as arguments to commands or path names for your particular system. For example:

```
% cd /users/your_name
```

Note: Some command examples may use angle brackets to represent variable values you must supply. This is an older convention that is replaced with *italic* words or characters.

Keying conventions

This guide may use the following keying conventions:

No prompt	When a command's format is the same for multiple platforms, a prompt is not used.
%	A percent sign represents the UNIX command shell prompt for a command that does not require root privileges.
#	A number sign represents the UNIX command shell prompt for a command that requires root privileges.
>	The notation > represents the DOS or Windows command prompt.
.	Horizontal or vertical ellipses in format and syntax descriptions indicate that material has been eliminated to simplify a discussion.
[]	Brackets enclose optional items in format and syntax descriptions.
{ }	Braces enclose a list from which you must choose an item in format and syntax descriptions.
	A vertical bar separates items in a list of choices enclosed in { } (braces) in format and syntax descriptions.

PREFACE

Using the Leasing Plug-In

This chapter describes what the leasing plug-in does and how to use the leasing plug-in on the client-side and the server-side of your application.

In this chapter

The following topics are discussed in this chapter:

The Leasing Framework	page 2
A Sample Leasing Application	page 6
Using the Leasing Plug-In on the Client Side	page 8
Using the Leasing Plug-In on the Server Side	page 10

The Leasing Framework

Overview

The leasing plug-in is an add-on feature for Orbix that manages server-side resources by detecting when client processes have ceased using a server. This is done using a leasing framework. When a client starts up, it can acquire a *lease* for a particular server, renewing it periodically. When the client terminates, it automatically releases the lease. If the client crashes, the server later detects that the lease has expired. In this manner, both graceful and ungraceful client process terminations are detected.

What is session management?

It is a common requirement in many CORBA systems to know when a client process terminates, in order to clean up resources that are used only by that client. On the server side, session-based applications allocate resources to cater for client requests. To prevent servers from bloating, it is necessary to detect when clients are finished dealing with the server. CORBA does not provide a native solution to this problem.

Features

The leasing framework has the following features:

- Zero impact on client application code.
 - Zero impact on existing application IDL interfaces.
 - Easy to implement.
 - CORBA compliant.
 - Completely configurable.
-

Server side behavior

On the server side, the leasing framework operates as follows:

Stage	Description
1	When a server starts up, it automatically loads the leasing plug-in.
2	During initialization, the server advertises the lease, which causes a <code>LeaseCallback</code> object to be bound in the naming service.

Stage	Description
3	Whenever the server exports object references (IORs), the plug-in automatically adds leasing information to the IOR in a CORBA-compliant manner.

Client side behavior

On the client side, the leasing framework operates as follows:

Stage	Description
1	When the client starts up, it automatically loads the leasing plug-in.
2	If the plug-in detects that the client is going to invoke on an object using an IOR containing leasing details, the plug-in automatically initiates a session with the target server by acquiring a lease.
3	The plug-in automatically renews the lease when needed.
4	Upon client shut down: <ul style="list-style-type: none"> • If the client shuts down gracefully, the plug-in automatically releases the lease with the server. • If the client crashes, the server side plug-in later realizes that the client has not recently renewed the lease. The lease expires, allowing the server to clean up appropriately.

Lease acquisition

A client initiates a session by acquiring a lease from a leasing server, as shown in [Figure 1](#).




Figure 1: *The Client Acquires a Lease*

The client session is initiated by the leasing plug-in, as follows:

1. The client's leasing plug-in obtains an `IT_Leasing::LeaseCallback` object reference by resolving a name in the CORBA naming service.
2. The client's leasing plug-in initiates a session by calling `acquire_lease()` on the `LeaseCallback` object.

Lease renewal

After acquiring a lease, the client renews the lease at regular intervals, as shown in [Figure 2](#)




Figure 2: *The Client Renews the Lease*

The period between lease renewals is specified by the `plugins:lease:lease_ping_time` configuration variable.

Client shutdown

When the client shuts down, the lease is released as shown in [Figure 3](#)




Figure 3: *The Lease is Released When the Client Shuts Down*

The following shutdown scenarios can occur:

- *Graceful client shutdown*—if the client shuts down gracefully, the plug-in automatically calls `lease_release()` to end the session.
- *Client crashes*—if the client crashes, the server-side plug-in calls `lease_expired()` on the LeaseCallback object after a period of time specified by the `plugins:lease:lease_reap_time` configuration variable.

A Sample Leasing Application

Location

Source code and build instructions for a sample leasing application are located in the `asp/6.1/demos/corba/standard/session_management` directory of your Orbix installation.

The LeaseTest IDL module

The sample leasing application is based on a server that supports a simple factory pattern for creating transient `Person` objects:

```
//IDL
module LeaseTest {
    exception PersonAlreadyExists { };

    interface Person {
        string name();
    };

    interface PersonFactory {
        Person create_person(in string name)
            raises (PersonAlreadyExists);
    };
};
```

Purpose

The purpose of this example is to show that no matter how many clients create `Person` objects, and no matter how those client processes terminate, the server is notified when it can safely clean up the objects. Therefore, the server is able to keep its memory usage down.

Client-server interaction

Clients interact with the `LeaseTest` server as follows:

Stage	Description
1	A client creates new <code>Person</code> objects by calling the <code>create_person()</code> operation, with unique <code>name</code> arguments for each <code>Person</code> .

Stage	Description
2	When a client terminates, the <code>Person</code> objects it created no longer need to be held inside the server memory and are deleted.

Using the Leasing Plug-In on the Client Side

Prerequisites

The client plug-in makes periodic `resolve()` calls to the Naming Service during its lifetime. Therefore, your Orbix domain should have a properly configured locator, activator, and naming service ready before running a leasing client.

How to use the plug-in

The only thing that needs to be changed in a client deployment that uses the leasing framework is its configuration. Specifically, the plug-in must be added to the list of ORB plug-ins and be configured to participate in bindings.

Configuration variables

The following basic configuration variables are needed to configure and activate the client-side plug-in:

Table 1: *Configuration Variables Used on the Client Side*

Configuration Variable	Purpose
<code>plugins:lease:shlib_name</code>	Identifies the shared library that contains the plug-in code.
<code>orb_plugins</code>	The ORB plug-in list is modified to ensure that the lease plug-in is automatically loaded when the client ORB is initialized.
<code>binding:client_binding_list</code>	The client binding list is modified to ensure that the plug-in can participate in request processing.

The complete set of leasing plug-in configuration variables is given in [“Leasing Plug-In Configuration Variables” on page 23](#).

Configuring for colocated CORBA objects

In the `client_binding_list`, a binding description containing the `POA_Coloc` interceptor name *must* appear before the first binding description that contains a `LEASE` interceptor name. This is to ensure that a leasing application does not attempt to lease a colocated CORBA object.

Example configuration

In an Orbix file-based configuration, the client-side plug-in might be configured as follows:

```
# Orbix Configuration File
plugins:lease:shlib_name = "it_lease";
orb_plugins = ["local_log_stream", "lease", "iiop_profile",
              "giop", "iiop"];
binding:client_binding_list = ["POA_Coloc", "LEASE+GIOP+IIOP",
                               "GIOP+IIOP"];
```

Using the Leasing Plug-In on the Server Side

The IT_Leasing module

Servers wishing to act as leasing servers interact with the plug-in to advertise leases. The interfaces used by leasing servers are declared in the `IT_Leasing` module, which is defined in the `leasing.idl` file:

```
//IDL
module IT_Leasing
{
    ...
    interface LeaseCallback
    {
        LeaseID acquire_lease()
        raises (CouldNotAcquireLease);
        void lease_expired(in LeaseID lease_id);
        void lease_released(in LeaseID lease_id);
        void renew_lease(in LeaseID lease_id)
            raises (LeaseHasExpired);
    };
    local interface ServerLeaseAgent
    {
        void advertise_lease(
            in LeaseCallback lease_callback
        ) raises (CouldNotAdvertiseLease);
        LeaseID manufacture_lease_id();
        void withdraw_lease();
        void lease_acquired(in LeaseID lease_id);
        void lease_released(in LeaseID lease_id);
    };
    local interface Current : CORBA::Current
    {
        exception NoContext {};
        LeaseID get_lease_id() raises (NoContext);
    };
    ...
};
```

The complete listing for the `IT_Leasing` module is in [“Leasing IDL Interfaces” on page 31](#).

The LeaseCallback interface

Your server must provide an implementation of the `IT_Leasing::LeaseCallback` interface to receive notifications of lease-related events from the leasing plug-in. For example, when leases expire, the plug-in calls `IT_Leasing::LeaseCallback::lease_expired()`.

The server lease agent interface

The implementation of the `ServerLeaseAgent` interface is provided by the leasing plug-in. Your server communicates with the leasing plug-in by calling the operations defined on this interface. For example, the server can initialize the leasing plug-in by calling `IT_Leasing::ServerLeaseAgent::advertise_lease()`.

The Current interface

For a leasing server to react correctly to the *ending* of a lease, it must know which resources are relevant to that lease. In other words, the server must maintain an association between the resources that it has created and the clients that are currently using them.

This problem is solved as follows. When your server needs to figure out which leasing client invoked a particular operation, you can extract lease information from an object of `IT_Leasing::Current` type, which is derived from `CORBA::Current`, an interface specifically used for retrieving meta-information about CORBA invocations. Once the `IT_Leasing::Current` object is obtained, you can call `get_lease_id()` on it to find the lease ID relevant to that call.

If the call is made from a non-leasing client (or a non-Orbix client), the `IT_Leasing::Current::NoContext` user exception is thrown.

Implementing the server

To use the plug-in on the server side, perform the following steps:

Step	Action
1	Implement the LeaseCallback Interface.
2	Use IT_Leasing::Current to Track Client Sessions.
3	Advertise the Lease.
4	Configure the Server-Side Plug-In.

Implement the LeaseCallback Interface

Overview

You must implement the `LeaseCallback` interface to receive notification of leasing events from the plug-in.

The following example shows a code extract from the `LeaseTest` demonstration, where the `LeaseCallback` interface is implemented by the `LeaseCallbackImpl` class.

Object instances

The following two object instances are used by the `LeaseCallbackImpl` class:

Table 2: *Object Instances Used in the LeaseCallbackImpl Class*

Object Instance	Description
<code>leaseObj</code>	An <code>IT_Leasing::ServerLeaseAgent</code> object reference. This object is used to communicate with the leasing plug-in.
<code>m_factory</code>	A pointer to a <code>PersonFactoryImpl</code> object. This object is used to create new instances of <code>Person</code> CORBA objects.

Implementation code

The `IT_Leasing::LeaseCallback` interface is implemented by the `LeaseCallbackImpl` C++ class, as shown in [Example 1](#).

Example 1: *The LeaseCallbackImpl Class*

```

//C++
char*
1 LeaseCallbackImpl::acquire_lease()
  IT_THROW_DECL((CORBA::SystemException,
                IT_Leasing::CouldNotAcquireLease))
  {
    CORBA::String_var new_lease =
      leaseObj->manufacture_lease_id();
    // inform the plugin that it should monitor the lifecycle
    // and status of this new lease
    leaseObj->lease_acquired(new_lease);
    return new_lease._retn();
  }
2 void LeaseCallbackImpl::lease_expired(const char* lease_id)
  IT_THROW_DECL((CORBA::SystemException))
  {
    m_factory->owner_has_gone_away(lease_id);
  }
3 void LeaseCallbackImpl::lease_released(const char* lease_id)
  IT_THROW_DECL((CORBA::SystemException))
  {
    leaseObj->lease_released(lease_id);
    m_factory->owner_has_gone_away(lease_id);
  }
4 void LeaseCallbackImpl::renew_lease(const char* lease_id)
  IT_THROW_DECL((CORBA::SystemException,
                IT_Leasing::LeaseHasExpired))
  {
    // Nothing to do, since the plugin has already intercepted
    // this request and knows that the lease has been renewed.
  }

```

The code can be explained as follows:

1. The `LeaseCallbackImpl::acquire_lease()` function is called by client lease plug-ins when they need to acquire a lease with your server. The sample implementation asks the lease plug-in for a new unique lease ID, and then informs the plug-in that it has accepted the lease acquisition request by calling `lease_acquired()` on the

`ServerLeaseAgent` object. You could also create the lease ID yourself—however, you are then required to ensure its uniqueness within the server process.

2. The `LeaseCallbackImpl::lease_expired()` function is called by the plug-in when a particular lease has expired—that is, if the lease has not been renewed within the configured reap time (see [“Leasing Plug-In Configuration Variables” on page 23](#)). This can occur if the client crashes or if the network link is lost between the client and the server.

The sample implementation informs the `Person` factory that a particular owner of `Person` objects has disappeared, by calling `owner_has_gone_away()`. The `Person` factory is then free to remove any `Person` objects belonging to that client. The sample `PersonFactory` deletes the `Person` objects completely at this point. Alternatively, a server could *evict* the transient objects by persisting their data before physically deleting them from memory.

3. The `LeaseCallbackImpl::lease_released()` function is called by client lease plug-ins when the client shuts down gracefully. The implementation of this method is typically almost identical to the implementation of `lease_expired()`, because they are both caused by client terminations. The sample code delegates to the `PersonFactory` servant, informing it that a particular client has shut down.

There is one important difference between `lease_released()` and `lease_expired()`, however. When `lease_released()` is invoked, you should inform the plug-in of the event, so that it stops managing that particular lease and checking for its expiration. Do this by calling `ServerLeaseAgent::lease_released()`, as in the example code.

4. The `LeaseCallbackImpl::renew_lease()` function is the ping method that the client plug-ins call periodically to renew their leases. You can leave this function body empty. By virtue of the call reaching this point, it has already been intercepted and examined by the server side plug-in. During the interception, the lease is timestamped with the current time as its *last renewed time*. You might want to perform some logging here.

Use IT_Leasing::Current to Track Client Sessions

Overview

The server has to track the resources associated with each client and this is done with the help of the `IT_Leasing::Current` interface. In the `LeaseTest` example, the associated resources are `Person` objects. Whenever a `Person` object is created (using the `LeaseTest::PersonFactory` interface) the server associates the new `Person` object with the current client session.

The current client session is identified by the current lease ID, which is obtained from the `IT_Leasing::Current` interface.

Implementation code

The `LeaseTest::PersonFactory` interface is implemented by the `PersonFactoryImpl` C++ class as shown in [Example 2](#).

Example 2: *The PersonFactoryImpl Class (Sheet 1 of 3)*

```
// C++
LeaseTest::Person_ptr
PersonFactoryImpl::create_person(const char* name)
IT_THROW_DECL((CORBA::SystemException,
              LeaseTest::PersonAlreadyExists))
{
    LeaseTest::Person_var result = LeaseTest::Person::_nil();
    try
    {
1       CORBA::String_var owner = CORBA::string_dup("<unknown>");
        try
2       {
            CORBA::Object_var objref =
                global_orb->resolve_initial_references(
                    "LeaseCurrent"
                );
            if (!CORBA::is_nil(objref))
            {
                IT_Leasing::Current_var current =
                    IT_Leasing::Current::_narrow(objref);
                if (!CORBA::is_nil(current))
                {
```

Example 2: *The PersonFactoryImpl Class (Sheet 2 of 3)*

```

3         owner = current->get_lease_id();
        }
    }
}
catch (IT_Leasing::Current::NoContext &)
{
    cerr << "Couldn't find the relevant "
        << "ServiceContext data." << endl;
}
catch (...)
{
    cerr << "An unknown exception occurred while "
        << "getting ServiceContext data." << endl;
}

// Create a new Person servant and activate it
PersonImpl*          newPersonServant;
PortableServer::ObjectId_var oid;
CORBA::Object_var   tmp_ref;
...
// Assume that we have already checked that the
// person does not exist, so it is created and
// stored with the others, indexed by its name
//
4 newPersonServant = new PersonImpl(name, owner);
oid = m_poa->activate_object(newPersonServant);
tmp_ref = m_poa->id_to_reference(oid);
result = LeaseTest::Person::_narrow(tmp_ref);
assert(!CORBA::is_nil(result));
// Store the new servant with the others
IT_String temp_string(name);
5 m_People[temp_string] = newPersonServant;
dump_people_to_screen();
}
catch (const CORBA::SystemException &se)
{
    cerr << se << endl;
}
catch (...)
{
    cerr << "Unknown exception within create_person()"
        << endl;
}
6 return result._retn();
}

```

Example 2: *The PersonFactoryImpl Class (Sheet 3 of 3)*

```

7 void PersonFactoryImpl::owner_has_gone_away(const char* owner)
  {
    // Iterate through the people map and evict any people
    // who were created by 'owner'.
    //
    IT_Locker <IT_Mutex> lock(m_mutex);
    IT_String current_name;
    People::iterator theIter = m_People.begin();
    while (theIter != m_People.end())
    {
      8     current_name = (*theIter).second->owner();
        if (current_name == owner)
          {
            // deactivate the servant before deleting it
            PortableServer::ObjectId_var oid =
              m_poa->servant_to_id((*theIter).second);
            // deactivate the servant with the corresponding
            // id on the POA
            9     m_poa->deactivate_object(oid);
            cout << "Deleting: " << (*theIter).first << endl;
            10     delete (*theIter).second;
              m_People.erase(theIter);
              theIter = m_People.begin(); //iterator is invalidated
              continue;
            }
            theIter++;
          }
        dump_people_to_screen();
      }
    ...

```

The code can be explained as follows:

1. If the factory cannot figure out the relevant lease ID, it assigns a default ID of `<unknown>` as the owner of the object. This happens if a non-leasing client (either a non-Orbix client or an Orbix client that did not load the plug-in) invokes the factory.
2. The factory checks to see if it can contact the `LeaseCurrent` object.
3. If a reference to a `LeaseCurrent` object can be obtained, the `get_lease_id()` function is called to get the lease ID (of string type) for this invocation.

4. A new `Person` object is created and activated. The `result` variable is set equal to the corresponding `Person` object reference.
5. The factory stores the new `Person` object in its own internal table of `Person` objects, `m_People`, using the lease ID, `temp_string`, as a key.
6. The `Person` object reference, `result`, is returned to the calling code.
7. The `owner_has_gone_away()` function is called by
`LeaseCallback::lease_expired()` or
`LeaseCallback::lease_released()` to clean up the resources (`Person` objects) associated with a client session identified by the `owner` string. The code iterates over all of the entries in the `m_Person` table, searching for entries associated with the `owner` session.
8. String comparison between `current_name` and `owner` can be performed using `==` because `current_name` is declared to be of `IT_String` type, which has similar properties to the `std::string` type from the C++ standard template library.
9. Before deleting a `Person` object, the corresponding servant must be deactivated by calling `PortableServer::POA::deactivate_object()`.
10. The servant object and its corresponding `m_People` entry are deleted in this and the following lines of code.

Advertise the Lease

Prerequisites

Advertising the lease causes the `LeaseCallback` object reference to be bound into the naming service. Therefore, you must have your Orbix locator, node daemon, and naming service properly configured and ready to run.

Where to advertise

Lease advertisement is an initialization step that is performed in the server `main()` function. This should be done before the server starts to process incoming CORBA requests (that is, before the server calls `ORB::run()` or `ORB::perform_work()`).

Implementation code

The code shown in [Example 3](#) should be added to your server's `main()` function to advertise the lease:

Example 3: *Advertising the Lease in the main() Function (Sheet 1 of 2)*

```
// C++
...
int
main(int argc, char **argv)
{
    // Assume that we have already created and activated a
    // LeaseCallback servant and created a reference for it
    // called theLeaseCallbackObj.
    ...
    // Contact the lease plugin and advertise a lease
    try
    {
1      CORBA::Object_var tmp_ref =
        global_orb->resolve_initial_references("IT_ServerLeaseAgent");
        leaseObj =
            IT_Leasing::ServerLeaseAgent::_narrow(tmp_ref);
    }
```

Example 3: *Advertising the Lease in the main() Function (Sheet 2 of 2)*

```
2 leaseObj->advertise_lease(theLeaseCallbackObj);
    }
    catch (IT_Leasing::CouldNotAdvertiseLease &ex)
    {
        // process the exception
    }
    catch (CORBA::Exception &e)
    {
        // ...
    }
    ...
};
```

The code can be explained as follows:

1. The server obtains an initial reference to a `ServerLeaseAgent` object, which is created by the leasing plug-in.
2. The leasing plug-in is initialized by calling `advertise_lease()` on the `ServerLeaseAgent` object. The `advertise_lease()` operation takes a single parameter, `theLeaseCallbackObj`, which causes the `LeaseCallback` object to be registered with the plug-in.

Configure the Server-Side Plug-In

Overview

Server-side configuration variables are used to initialize the server-side plug-in and to customize the behavior of the leasing plug-in. Some of these configuration variables are communicated to clients by inserting the information into IORs generated by the server.

Configuration variables

In addition to the client-side configuration variables, the following basic configuration variables are needed to configure the server-side plug-in:

Table 3: *Configuration Variables Used on the Client Side*

Configuration Variable	Purpose
<code>binding:server_binding_list</code>	The server binding list is modified, instructing the ORB to insert <code>LEASE</code> interceptors into server-side bindings.
<code>plugins:lease: lease_name_to_advertise</code>	The name under which the <code>LeaseCallback</code> object is bound in the naming service. This name must be unique per server.
<code>plugins:lease:lease_ping_time</code>	The time interval (in milliseconds) between successive ping messages sent by client-side plug-ins to renew the lease.
<code>plugins:lease:lease_reap_time</code>	If a particular client's lease is not pinged within <code>lease_reap_time</code> , the server resources associated with the client are released.

The complete set of leasing plug-in configuration variables is given in [“Leasing Plug-In Configuration Variables” on page 23](#).

Example configuration

For a complete example of a client-side and server-side configuration, see [“Sample Leasing Plug-In Configuration” on page 27](#).

Leasing Plug-In Configuration Variables

The following list describes the leasing plug-in configuration variables and their allowed values, ranges, and defaults.

In this appendix

This appendix contains the following sections:

Common Variables	page 24
Server-Side Variables	page 25

Common Variables

List of variables

The following configuration variables apply to both clients and servers:

event_log:filters Specifies a list of logging filters. You can configure the plug-in to write to a log stream by appending the plug-in log stream to the list of filters (see the *CORBA Administrator's Guide* for more information on log stream configuration). The plug-in's log stream object is `IT_LEASE`. For example, to get full diagnostic output from the plug-in, set the variable `event_log:filters` equal to `["IT_LEASE=*"]`.

plugins:lease:lease_ns_context Identifies the naming service `NamingContext` where the leasing plug-in registers the `LeaseCallback` object. The name should be a valid `NamingContext` id (see the CORBA Naming Service specification). Since both leasing clients and leasing servers use this value, it should be set to the same value across your entire domain. The default is `IT_Leases`.

plugins:lease:shlib_name Identifies the base name of the leasing plug-in shared library. The `shlib_name` variable should be set to `it_lease`.

Server-Side Variables

List of Variables

The following configuration variables apply only to servers:

plugins:lease:allow_advertisement_overwrites Determines whether the server can re-advertise the same lease when it comes back up after a crash or disorderly shutdown. Internally, the plug-in uses

`NamingContext::rebind()` if set to `true`, or `NamingContext::bind()` if set to `false`, when binding the `LeaseCallback` object in the naming service.

The default is `false`, but in a real deployment scenario the recommended setting is `true`.

plugins:lease:lease_name_to_advertise Determines the lease name used when registering the `LeaseCallback` object in the naming service. This name should be configured to be unique among all your leasing servers. The name should be a valid `NamingContext` id (see the CORBA naming service specification). The default value is `default_lease_name`.

plugins:lease:lease_ping_time Determines the value inserted into `TAG_IONA_LEASE` IOR components for the lease ping time. Leasing clients using that IOR automatically renew the lease by pinging every `N` ms, where `N` is the value specified in this variable. The default value is 900,000 ms (15 minutes). Legal values are unsigned longs > 1 . In addition, if the ping time is specified to be greater than the reap time, `lease_reap_time`, it is automatically changed to half the reap time.

plugins:lease:lease_reap_time Determines how often the server-side plug-in checks whether leases have expired. The value is specified in ms. If a particular lease has not been renewed (pinged) by its client in this amount of time, the lease expires. Legal values are unsigned longs > 2 . The default value is 1,800,000 ms (30 minutes).

Sample Leasing Plug-In Configuration

This appendix shows the leasing plug-in configuration used in the session management demonstration.

Configuration file extract

The following listing is a sample valid configuration for a set of applications, `Server1`, `Server2`, and clients, using the leasing plug-in. This configuration is included in generated Orbix domains, `OrbixInstallDir/etc/domains/domain_name.cfg`, where `domain_name` is the name of your domain.

Example 4: Configuration File Extract for Leasing Plug-In

```
# Orbix Configuration File
...
demos {
  ...
  session_management
  {
    plugins:lease:shlib_name = "it_lease";
    plugins:lease:ClassName =
      "com.iona.corba.plugin.lease.LeasePlugIn";
    orb_plugins = ["local_log_stream", "lease",
      "iiop_profile", "giop", "iiop"];
    binding:client_binding_list = ["POA_Coloc",
      "LEASE+GIOP+IIOP",
      "GIOP+IIOP"];
    binding:server_binding_list = ["LEASE", ""];
    plugins:lease:allow_advertisement_overwrites = "true";
    # default is false
    event_log:filters = ["IT_LEASE=*"];
    server1 {
      # client must ping every 10 seconds
      plugins:lease:lease_ping_time = "10000";
      # leases will expire after 20 seconds of inactivity
      plugins:lease:lease_reap_time = "20000";
      plugins:lease:lease_name_to_advertise
        = "PersonFactorySrv1";
    };
    server2 {
      # client must ping every 20 seconds
      plugins:lease:lease_ping_time = "20000";
      # leases will expire after 40 seconds of inactivity
      plugins:lease:lease_reap_time = "40000";
      plugins:lease:lease_name_to_advertise
        = "PersonFactorySrv2";
    };
  };
  ...
};
```


Leasing IDL Interfaces

The complete IDL for the leasing plug-in.

The IT_Leasing IDL module

The IT_Leasing module is defined as follows:

Example 5: *The IT_Leasing IDL Module (Sheet 1 of 3)*

```
//IDL
#ifndef __IT_LEASING_IDL_
#define __IT_LEASING_IDL_
//
// @Copyright (c) 2000 IONA Technologies PLC. All Rights
// Reserved.

#include <omg/orb.idl>
#include <omg/IOP.idl>
#pragma prefix "iona.com"
module IT_Leasing
{
    // Type definitions
    typedef string LeaseID;

    // Possible error conditions
    exception LeaseHasExpired {};
};
```

Example 5: *The IT_Leasing IDL Module (Sheet 2 of 3)*

```

enum LeaseAdvertisementError {
    NAMING_SERVICE_UNREACHABLE,
    LEASE_ALREADY_ADVERTISED,
    LEASE_ALREADY_BOUND_IN_NS,
    UNKNOWN_ERROR
};
exception CouldNotAdvertiseLease
{
    LeaseAdvertisementError reason;
};
exception CouldNotAcquireLease {};

// This is the maximum amount of time that a client leasing
// plugin will wait before automatically renewing a
// particular lease. The value is set in the server plugins'
// configuration.
typedef unsigned long IdleTimeBeforePing; // milliseconds
// This interface must be implemented by servers that
// wish to advertise leases.
interface LeaseCallback
{
    // Informs the server that a client wants a new lease.
    LeaseID acquire_lease()
    raises (CouldNotAcquireLease);
    // Informs the server that a lease not been renewed
    // (usually because the client has gone away)
    void lease_expired(
        in LeaseID lease_id
    );
    // Informs the server that a client has explicitly
    // released a lease
    void lease_released(in LeaseID lease_id);

    // renew_lease() is called by leasing plugins on the
    // client side to renew leases after some idle time.
    // This is semantically equivalent to a 'keepalive'
    // or 'heartbeat' method.
    void renew_lease(in LeaseID lease_id)
    raises (LeaseHasExpired);
};
// This is the interface that leasing plugins will
// expose on the server side. Server programmers must
// interact with this interface to advertise leases.
local interface ServerLeaseAgent
{

```

Example 5: *The IT_Leasing IDL Module (Sheet 3 of 3)*

```
// advertise_lease() is called by the server
// to start the lease advertisement. The ping time
// and ServerID values for the lease are obtained
// from configuration.
void advertise_lease(in LeaseCallback lease_callback)
raises (CouldNotAdvertiseLease);
// Helper function that generates a system defined
// lease id, in case the server does not need to attach
// any specific meaning to incoming leases.
LeaseID manufacture_lease_id();
// You may call this method at any time to withdraw your
// lease, but note that the plugin will automatically
// withdraw your lease at ORB shutdown time, so you
// typically never need to call this method.
void withdraw_lease();
// Call this method if you wish the plugin to
// detect that a particular lease has expired (usually
// due to non-graceful client termination).
// The typical place to call this is from your
// implementation of LeaseCallback::acquire_lease().
void lease_acquired(in LeaseID lease_id);
// Call this method when you wish the plugin to stop
// detecting that a particular lease has expired, usually
// because a client has terminated gracefully and
// released the lease themselves.
// The typical place to call this is from your
// implementation of LeaseCallback::lease_released().
void lease_released(in LeaseID lease_id);
};
// This interface represents the lease details that will
// be added to requests by leasing clients. The information
// will be added as a ServiceContext and be available within
// the servant implementations through the Current interface.
local interface Current :
CORBA::Current
{
    exception NoContext {};
    LeaseID get_lease_id()
    raises (NoContext);
};
const IOP::ServiceId SERVICE_ID = 0x49545F43;
};
#endif /*__IT_LEASING_IDL__*/
```


Index

Symbols

<unknown> lease ID 17

A

acquire_lease() 13
advertise_lease() 11, 20
allow_advertisement_overwrites variable 25

C

callbacks 12
client_binding_list 8
colocation, and the leasing plug-in 8
configuration
 of leasing client 9
 of leasing plug-in 24, 28
 of leasing server 21
CORBA::Current 11
Current interface
 in IT_Leasing module 11
 using IT_Leasing::Current 15

D

deactivate_object() 18

E

event_log:filters variable 24

F

filters variable 24

G

get_lease_id() 11, 17

I

initial references 20
IT_Leasing module 10, 31
IT_ServerLeaseAgent 20
IT_String type 18

L

lease, advertising 19
lease_acquired() 13
LeaseCallbackImpl class 13
LeaseCallback interface 11, 12
lease_expired() 18
 and client shut down 5
 implementing 14
lease ID 15, 17
lease_name_to_advertise 21
lease_name_to_advertise variable 25
lease_ns_context variable 24
lease_ping_time variable 4, 21, 25
lease_reap_time variable 5, 21, 25
lease_release() 5
lease_released() 14, 18
LeaseTest module 6
leasing demonstration 6
leasing plug-in
 client configuration 8
 client-side behavior 3
 client-side usage 8
 colocated CORBA objects 8
 common variables 24
 configuration example 28
 features 2
 framework 2
 implementing the server 11
 lease acquisition 4
 lease renewal 4
 prerequisites 8
 server-side behavior 2
 server-side configuration 21
 server-side variables 25
 shutdown 5
 tracking client sessions 15
logging filters 24

N

naming service
 and advertising a lease 19
 and lease_ns_context variable 24
 and the leasing plug-in 8

INDEX

NoContext user exception 11

O

orb_plugins variable 8

owner_has_gone_away() 18

P

PersonFactoryImpl class 15

plugins:lease:allow_advertisement_overwrites
variable 25

plugins:lease:lease_name_to_advertise variable 25

plugins:lease:lease_ns_context variable 24

plugins:lease:lease_ping_time variable 25

plugins:lease:lease_reap_time variable 25

POA_Coloc interceptor 8

R

renew_lease() 14

S

server_binding_list 21

ServerLeaseAgent interface 11

session management

 demonstration location 6

 overview 2

shlib_name 8

standard template library 18

std::string 18

T

TAG_IONA_LEASE tag 25

