

# **Orbix C++ Administrator's Guide**

**Orbix is a Registered Trademark of IONA Technologies PLC.**

While the information in this publication is believed to be accurate, IONA Technologies PLC makes no warranty of any kind to this material including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. IONA Technologies PLC shall not be liable for errors contained herein, or for incidental or consequential damages in connection with the furnishing, performance or use of this material.

Java is a trademark of Sun Microsystems, Inc.

---

**COPYRIGHT NOTICE**

No part of this publication may be reproduced, stored in a retrieval system or transmitted, in any form or by any means, photocopying, recording or otherwise, without prior written consent of IONA Technologies PLC. No third party intellectual property right liability is assumed with respect to the use of the information contained herein. IONA Technologies PLC assumes no responsibility for errors or omissions contained in this book. This publication and features described herein are subject to change without notice.

Copyright © 1991-1999 by IONA Technologies PLC. All rights reserved.

All products or services mentioned in this manual are covered by the trademarks, service marks, or product names as designated by the companies who market those products.

**M 2 2 3 0**

---

# Contents

<b>Preface</b>	<b>vii</b>
Audience	vii
Organization of this Guide	viii
Document Conventions	xi

## Part I Orbix Administration

<b>Chapter 1 Overview of Orbix Administration</b>	<b>3</b>
<b>Components of the Orbix Architecture</b>	<b>4</b>
Servers and the Implementation Repository	4
Clients and the Server Locator	5
The Interface Repository	7
<b>Administration of Orbix Components</b>	<b>7</b>
<b>Chapter 2 Getting Started</b>	<b>9</b>
<b>Basic Orbix Configuration</b>	<b>10</b>
The Orbix Configuration Files	10
Locating the Configuration Files	13
Locating the Orbix Library Directory on UNIX Platforms	14
Setting the Orbix Daemon Port	14
Locating the Implementation Repository	15
Specifying Your Local Internet Domain	15
<b>Starting The Orbix Daemon</b>	<b>16</b>
<b>Registering a Server</b>	<b>17</b>
<b>Checking for an Orbix Daemon</b>	<b>18</b>
<b>Checking for Running Servers</b>	<b>18</b>
<b>Chapter 3 Managing the Implementation Repository</b>	<b>21</b>
<b>Implementation Repository Entries</b>	<b>22</b>
<b>Basic Implementation Repository Usage</b>	<b>23</b>
Registering a Server on a Remote Host	23
Organizing Servers Into Hierarchies	23

Removing a Registered Server	24
Listing Registered Servers	25
Displaying A Server Entry	25
<b>Starting Servers Manually</b>	<b>26</b>
Registering a Manual Server	26
Starting the Orbix Daemon for Unregistered Servers	27
<b>Stopping Servers</b>	<b>27</b>
<b>Security of Registered Servers</b>	<b>28</b>
Modifying Server Access	28
Changing the Owners of Registered Servers	29
Determining the User and Group IDs of Running Servers	30
<b>Server Activation Modes</b>	<b>31</b>
Registering Unshared Servers	32
Using Markers to Specify Named Objects	32
Registering Per-Method Servers	34
Secondary Activation Modes	35
<b>Managing Server Port Selection</b>	<b>36</b>
Registering Servers with Specified Ports	36
Controlling Port Allocation with Configuration Variables	37
<b>Chapter 4 Managing the Server Locator</b>	<b>39</b>
Locating Server Locator Files	40
The Server Locator Algorithm	40
Configuration File Formats	41
Using the serverhosts Command	42
Using the servergroups Command	43
Using the grouphosts Command	44
<b>Chapter 5 Managing the Interface Repository</b>	<b>47</b>
Configuring the Interface Repository	48
Registering the Interface Repository Server	48
Adding IDL Definitions	49
Reading the Interface Repository Contents	50
Removing IDL Definitions	50

---

## Part II Orbix GUI Tools

<b>Chapter 6 The Orbix Configuration Explorer</b>	<b>53</b>
<b>Starting the Configuration Explorer</b>	<b>54</b>
<b>Configuring Common Settings</b>	<b>55</b>
<b>Configuring Orbix-Specific Settings</b>	<b>58</b>
<b>Customizing Your Configuration</b>	<b>59</b>
Creating Configuration Variables	60
Creating Configuration Scopes	62
Creating Configuration Files	63
<b>Chapter 7 The Orbix Server Manager</b>	<b>65</b>
<b>Starting the Server Manager</b>	<b>66</b>
<b>Connecting to an Implementation Repository</b>	<b>67</b>
<b>Creating a New Directory</b>	<b>69</b>
<b>Registering a Server</b>	<b>71</b>
Providing Server Access Rights to Users	73
Specifying Server Activation Details	75
<b>Modifying Server Registration Details</b>	<b>78</b>
<b>Launching a Persistent Server</b>	<b>79</b>
<b>Configuring the Server Manager</b>	<b>80</b>
<b>Chapter 8 The Interface Repository Browser</b>	<b>83</b>
<b>Starting the Interface Repository Browser</b>	<b>84</b>
<b>Connecting to an Interface Repository</b>	<b>85</b>
<b>Adding IDL to the Interface Repository</b>	<b>86</b>
<b>Viewing the Interface Repository Contents</b>	<b>87</b>
Viewing Information about IDL Definitions	89
Viewing Source Code for IDL Definitions	89
<b>Exporting IDL Definitions to a File</b>	<b>90</b>
<b>Configuring the Interface Repository Browser</b>	<b>91</b>

## **Part III Appendices**

<b>Appendix A Configuration Variables</b>	<b>95</b>
<b>Appendix B Orbix Daemon Options</b>	<b>99</b>
<b>Appendix C Command Reference</b>	<b>101</b>
<b>Appendix D Error Messages and Exceptions</b>	<b>123</b>
<b>Index</b>	<b>129</b>

# Preface

Orbix is a software environment for building and integrating distributed, object-oriented applications. This guide explains how to configure and manage the components of the Orbix environment. Many Orbix components have associated graphical user (GUI) interfaces. This guide describes the Orbix GUI tools associated with Orbix configuration, the Implementation Repository, and the Interface Repository.

## Audience

Read this guide if you are responsible for any of the following tasks:

- Configuring an Orbix installation.
- Registering servers in the Orbix Implementation Repository.
- Adding IDL definitions to the Orbix Interface Repository.

This guide describes how you can use the command line and Orbix GUI tools to do each of these tasks. It assumes that you are familiar with relevant sections of the *Orbix C++ Programmer's Guide*, and the *Orbix C++ Programmer's Reference*.

## Organization of this Guide

This guide is divided into 3 parts as follows:

### **Part I, Orbix Administration**

#### **Chapter 1, “Overview of Orbix Administration”**

This chapter introduces the main components of the Orbix environment. You should read this chapter first to familiarize yourself with terminology used throughout the guide.

#### **Chapter 2, “Getting Started”**

This is a quick start chapter on how to configure Orbix, start the Orbix daemon process, and how to register a server that automatically starts when it is needed.

#### **Chapter 3, “Managing the Implementation Repository”**

This explains more about using the Implementation Repository including registering servers, displaying and organising server entries, and security issues.

#### **Chapter 4, “Managing the Server Locator”**

This chapter describes how to configure Orbix to find servers on other hosts.

#### **Chapter 5, “Managing the Interface Repository”**

This chapter describes how to configure Orbix to store object interface definitions so that applications can learn about them at runtime.

## **Part II, Orbix GUI Tools**

### **Chapter 6, “Overview of the Orbix GUI Tools”.**

This chapter provides an overview of each of the Orbix GUI tools and describes how you can run these tools. You should read this chapter first.

### **Chapter 6, “The Orbix Configuration Explorer”**

This chapter describes how you can configure an Orbix installation using the Orbix Configuration Tool.

### **Chapter 7, “The Orbix Server Manager”**

This chapter describes how you can register servers in the Orbix Implementation Repository using the Orbix Server Manager.

### **Chapter 8, “The Interface Repository Browser”**

Chapter 8 describes how you can add IDL definitions to the Orbix Interface Repository using the Interface Repository browser.

You should refer to the *OrbixNames Programmer's and Administrator's Guide* for details of the OrbixNames Browser.

## **Part III, Appendices**

### **Appendix A, “Configuration Variables”**

This appendix shows the configuration variables that Orbix recognizes.

### **Appendix B, “Orbix Daemon Options”**

This appendix describes the start-up options that the Orbix daemon can use.

### **Appendix C, “Command Reference”**

This describes the syntax and the options for each Orbix command you can use.

### **Appendix D, “Error Messages and Exceptions”**

This describes how to modify error messages, shows the error formats, and lists tables of standard error messages that Orbix applications can return.

---

## Document Conventions

This guide uses the following typographical conventions:

`Constant width` Constant width (courier font) in normal text represents portions of code and literal names of items such as classes, functions, variables, and data structures. For example, text might refer to the `CORBA::Object` class.

Constant width paragraphs represent code examples or information a system displays on the screen. For example:

```
#include <stdio.h>
```

*Italic* Italic words in normal text represent *emphasis* and *new terms*.

Italic words or characters in code and commands represent variable values you must supply, such as arguments to commands or path names for your particular system. For example:

```
% cd /users/your_name
```

Note: Some command examples may use angle brackets to represent variable values you must supply. This is an older convention that is replaced with *italic* words or characters.

This guide may use the following keying conventions:

No prompt When a command's format is the same for multiple platforms, no prompt is used.

% A percent sign represents the UNIX command shell prompt for a command that does not require root privileges.

# A number sign represents the UNIX command shell prompt for a command that requires root privileges.

> The notation > represents the DOS, Windows NT, or Windows 95 command prompt.

...	Horizontal or vertical ellipses in format and syntax descriptions indicate that material has been eliminated to simplify a discussion.
[]	Brackets enclose optional items in format and syntax descriptions.
{ }	Braces enclose a list from which you must choose an item in format and syntax descriptions.
	A vertical bar separates items in a list of choices enclosed in { } (braces) in format and syntax descriptions.


---

**Note:** Unless otherwise stated, all examples in this guide apply to Orbix on both UNIX and Windows platforms.

---

Part I

# Orbix Administration







# Overview of Orbix Administration

*Orbix is a software environment that allows you to develop distributed applications. This chapter introduces the main components of the Orbix environment.*

As described in the *Orbix C++ Programmer's Guide*, Orbix allows you to build distributed software systems composed of interacting objects. Orbix is a full implementation of the Object Management Group (OMG) Common Object Request Broker Architecture (CORBA).

An Orbix application consists of one or more *client* programs that communicate with *distributed objects* located in *server* programs. Clients can communicate with distributed objects from any host in a network through clearly-defined interfaces specified in the CORBA Interface Definition Language (IDL).

Orbix mediates the communication between clients and distributed objects. This mediation allows clients to communicate with objects without concern for details such as:

- The hosts on which the objects exist.
- The operating system that these hosts run.
- The programming language used to implement the objects.

The Orbix architecture includes several configurable components that support the mediation of communications between clients and objects.

## Components of the Orbix Architecture

An Orbix client invokes IDL operations on a distributed object using normal C++ function calls, as if the object were located in the client's address space. Orbix converts these function calls to a series of network messages and sends these messages to the server process that contains the target object. At the server, Orbix receives these messages and translates them to function calls on the target object, as shown in Figure 1.1.





Figure 1.1: An IDL Operation Call on a Distributed Object

## Servers and the Implementation Repository

Each Orbix server program has a name, unique within its host machine. A server can consist of one or more processes. When a client invokes a method on an object, a server process containing the target object must be available. If the process is not running, the Orbix daemon at the server host attempts to launch the server process automatically.

To allow an Orbix daemon to manage the server processes running in the system, Orbix provides an *Implementation Repository*. The Implementation Repository maintains a mapping from a server's name to the filename of the executable code implementing that server. The server code must therefore be registered with the Implementation Repository.



**Figure 1.2:** Automatic Launch of an Orbix Server Process

As shown in Figure 1.2, the Orbix daemon launches a server process as follows:

1. A client makes its first operation call to an object located in a server.
2. The Orbix daemon reads the server details from the Implementation Repository, including the server launch command.
3. If the required server process is not running, the Orbix daemon executes the server launch command.


To allow the daemon to launch server processes, you must maintain records in the Implementation Repository for each server in your system.

## Clients and the Server Locator

In order to communicate with a distributed object, a client program first obtains a reference to that object. An object reference uniquely identifies an object within a distributed system and includes such information as the name of the server in which the object is located and the host on which the server runs.

If a client uses the Orbix *bind* mechanism to obtain an object reference, the client can allow Orbix to determine at runtime the host on which the server runs. Orbix uses its *server locator* to find a suitable host.

A server with a given name can be supported on any number of hosts in the distributed system. The Orbix server locator allows you to associate a set of hosts with a server name using configuration files.



**Figure I.3:** *The Orbix Server Locator Mechanism*

Figure I.3 illustrates the steps involved in using the server locator:

1. A client binds to an object in a server without specifying the host on which the server runs. In this case, the “initial operation call” is an implicit call made by Orbix when the client binds to the object.
2. The server locator mechanism is implemented in the Orbix daemon. Orbix asks the Orbix daemon process on the client host to determine the location of the server. The server locator reads its configuration files to determine the name of the host on which the server runs.
3. Orbix binds to the target object at the host specified by the server locator.
4. The Orbix daemon at the server host reads the server details from the Implementation Repository.

5. If the required server process is not running, the Orbix daemon executes the server launch command.

To allow the server locator to find a host for an Orbix server, you must add an entry for that server to the server locator configuration files.

### The Interface Repository

Orbix maintains object specifications by storing an object's IDL interface in a database called the *Interface Repository*. Some client applications use the Interface Repository to determine object interfaces and all information about those interfaces at runtime.

A client accesses the Orbix Interface Repository by contacting an Interface Repository server. This is a standard Orbix server that provides a programming interface, defined in IDL, to the Interface Repository.

To allow clients to obtain information about IDL definitions implemented in your system, you must add those definitions to the Interface Repository.

## Administration of Orbix Components

To allow Orbix applications to run in your network, you must do the following:

- Configure Orbix for your network and environment, using the Orbix configuration files.
- Run the Orbix daemon process.
- Register servers in the Implementation Repository.

If your Orbix applications use the Orbix server locator or the Interface Repository, you must also do the following:

- Maintain the server locator configuration files.
- Add IDL definitions to the Interface Repository.

## Orbix C++ Administrator's Guide

---

*Part I* of this guide, *Orbix Administration*, presents the configuration files and command-line utilities that allow you to achieve each of these tasks.

*Part II* of this guide, *Orbix GUI Tools*, presents the graphical user interfaces that provide an alternative way to manage Orbix components.

# 2

## Getting Started

*Several components of Orbix require administration. This chapter describes the basic Orbix administration steps required when running Orbix applications.*

Orbix administration involves the following basic steps:

1. Configuring Orbix for your network and environment.
2. Starting the Orbix daemon (`orbixd`) on each host that Orbix servers run on.
3. Registering servers in the Implementation Repository so that Orbix can start them when needed.
4. Starting client applications that make object requests.
5. Monitoring Orbix to fine tune it and your clients and servers.

Steps 1 and 2 apply when you first install Orbix and only occasionally after that. Steps 3, 4, and 5 are iterative. This guide describes how to perform these steps. This chapter first gives you a quick start to using Orbix and its environment of distributed computing.

# Basic Orbix Configuration

This section describes the configuration settings you may need to modify before starting the Orbix daemon. You can modify the main Orbix configuration settings by editing the Orbix configuration files, or by setting environment variables or by using the Orbix GUI tools. Refer to “The Orbix Configuration Explorer” on page 53 for details of configuring Orbix using GUI tools.

## The Orbix Configuration Files

The Orbix configuration files are located in the `config` directory of your Orbix installation. By default, these are named as follows:

- `iona.cfg`
- `common.cfg`
- `orbix3.cfg`
- `orbixnames3.cfg`

### **iona.cfg**

The `iona.cfg` file is the root configuration file used by Orbix. This file contains links to all other IONA configuration files. You can edit this file to include links to your customized configuration files. The default `iona.cfg` file includes the following information:

```
// In file iona.cfg
cfg_dir = "d:\iona\config\";

include cfg_dir + "common.cfg";
include cfg_dir + "orbix3.cfg";
include cfg_dir + "orbixnames3.cfg";
```

You should set the `cfg_dir` variable to `<iona_install_dir>\config\`.

### common.cfg

The `common.cfg` file contains a list of configuration variables that are common to multiple IONA products. The configuration variables in this file are declared within the scope `Common{...}`, for example:

```
// In file common.cfg
Common {
    # The port number for the Orbix daemon.
    IT_DAEMON_PORT = "1570";

    # The starting port number for daemon-run servers:
    IT_DAEMON_SERVER_BASE = "1570";

    # The full path name of the Implementation Repository
    # directory.
    IT_IMP_REP_PATH = cfg_dir + "Repositories\ImpRep";

    # The full path name of the Interface Repository
    # directory.
    IT_INT_REP_PATH = cfg_dir + "Repositories\IFR";

    # The full path name of the directory holding
    # the locator files.
    IT_LOCATOR_PATH = cfg_dir;

    # The local DNS domain name.
    IT_LOCAL_DOMAIN = "";

    # The full path name to the JRE binary
    # executable that installs with Orbix.
    IT_JAVA_INTERPRETER="C:\IONA\bin\jre.exe";

    # The default classpath to be used when java
    # servers are automatically launched by the daemon.
    IT_DEFAULT_CLASSPATH = cfg_dir +
";C:\IONA\bin\bongo.zip;C:\IONA\bin\marimba.zip;
C:\IONA\bin\NSclasses.zip;C:\IONA\bin\utils.zip;
C:\IONA\bin\rt.jar;C:\IONA\bin\orbixweb.jar;
C:\IONA\Tools\NamingServiceGUI\NSGUI.jar";
};
```

---

**Note:** You can also use the prefix `Common.` to refer to individual entries in this file. For example, `Common.IT_DAEMON_PORT`.

---

After installation, the `common.cfg` file provides default settings for the main environment variables required by Orbix. You can change these default settings by manually editing the configuration file, or by using the Configuration Explorer, or by setting a variable in the user environment. An environment variable, if set, takes precedence over the value set in the configuration file. Environment variables are not scoped with a `Common.` prefix.

### Format of Configuration Files

Each line of the `common.cfg` configuration file has the following form:

```
<entry name> = "<entry value>"
```

Each variable in your configuration file must start at the beginning of a line. Any line that does not start with a variable that Orbix recognizes is ignored. You can add comments to your configuration file in this way. Any entry value can use any desired environment variable.

### **orbix3.cfg**

This file contains configuration variables that are specific to Orbix only. By default, the configuration variables in this file are scoped with the `Orbix.` prefix. You can also use the scope `Orbix{...}`.

```
// In file orbix3.cfg
# The path name to the error messages file.
Orbix.IT_ERRORS = cfg_dir + "ErrorMsgs";

# The maximum number of retries Orbix makes to
# connect to a server.
Orbix.IT_CONNECT_ATTEMPTS = "10";
```

---

**Note:** Orbix uses the `IT` prefix, which represents “IONA Technologies”, to distinguish its configuration and environment variables.

---

The `orbixnames3.cfg` file contains configuration variables that are specific to OrbixNames. Refer to the *OrbixNames Programmer's and Administrator's Guide* for more details.

## Locating the Configuration Files

Orbix must be able to find its root configuration file before the Orbix daemon, the IDL compiler, or application processes run. The Orbix `config` directory is the default location for all configuration files. You can set a different directory or configuration file by setting the `IT_CONFIG_PATH` environment variable. If the `IT_CONFIG_PATH` variable is a directory, that directory should contain the `iona.cfg` file. If the `IT_CONFIG_PATH` environment variable is the full path name of a file, that file is used as the configuration file.

## How Orbix Finds its Configuration

Orbix has a chain of configuration handlers that it looks in when asked for a configuration parameter. These are as follows (in order):

```
[Environment Handler (IT_Environment)] ->
[ScopedConfigFile Handler (IT_ScopedConfigFile)] ->
[OldConfigFileHandler (IT_ConfigFile)]
```

The `Environment` handler allows any configuration variables defined in your environment to take precedence over those defined in configuration files or other user-defined configuration handlers.

The `ScopedConfigFile` handler does the following when searching for the root configuration file (`iona.cfg` by default):

- Checks the environment variable `IT_IONA_CONFIG_FILE`.  
The configuration file does not need to be called `iona.cfg`.
- Checks the environment variable `IT_CONFIG_PATH` and appends `iona.cfg`.
- Searches for `iona.cfg` in the same directory as the Orbix runtime libraries.
- On Windows NT, checks the Registry to find where Orbix was installed and appends `config\iona.cfg`.

- Tries the default installation locations (`c:\iona` on Windows NT, or `/opt/iona` on UNIX systems).

The `OldConfigfile` handler enables you to use `Orbix.cfg` files for backwards compatibility. However, it is recommended that you use the default files supplied with this version of Orbix.

### Using the `dumpconfig` Utility

The `dumpconfig` utility enables you to obtain information about your Orbix configuration. This utility outputs the values of the configuration variables used by Orbix, and the location of the Orbix configuration files in your system. It also reports if there are any syntax errors in your configuration files that would normally go unrecognized by Orbix. The `dumpconfig` utility is especially useful if you need to know where Orbix is being configured from.

The following sections describe more about the `IT_DAEMON_PORT`, `IT_IMP_REP_PATH`, and `IT_LOCAL_DOMAIN` variables. The `IT_DAEMON_SERVER_BASE`, `IT_LOCATOR_PATH`, `IT_ERRORS`, and `IT_INT_REP_PATH` variables are described in later chapters of the guide.

## Locating the Orbix Library Directory on UNIX Platforms

On Solaris platforms, you must set the environment variable `LD_LIBRARY_PATH` to include the Orbix `lib` directory before the Orbix daemon, the IDL compiler, or the Orbix administration commands can run.

On HPUX platforms, you must set the `SHLIB_PATH` environment variable the Orbix `lib` directory.

## Setting the Orbix Daemon Port

Orbix uses the daemon process `orbixd` on each site running Orbix servers to await incoming requests for server activation and to connect new clients to existing server processes. This is not involved in subsequent client/server communications.

The daemon uses one Internet port, and by default this port number is given by the `IT_DAEMON_PORT` entry in `common.cfg`. This is a required variable.

The standard registered port number assigned to `orbixd` by the Internet Engineering Task Force (IETF) is the internet port number 1570. You must ensure that the `IT_DAEMON_PORT` number is the same for all of your network hosts. However, when experimenting with the system, you may wish to install more than one Orbix daemon on a specific machine to isolate a particular set of servers. You must specify a different port for this daemon, by setting the environment variable `IT_DAEMON_PORT` or by using a different root configuration file `iona.cfg`.

## Locating the Implementation Repository

The data held in the Implementation Repository maps from server, application object, and operation names to the path names of executable server files. The location for storing this data is given by the required entry for `IT_IMP_REP_PATH` in the `common.cfg` configuration file. Each Orbix daemon has an associated Implementation Repository.

Occasionally it might be useful for a group of programmers to have their own Implementation Repository store on a particular host. For example, when running a separate daemon with a different daemon port. You can specify a different location by setting the `IT_CONFIG_PATH` to refer to a configuration file that specifies a different location for the `IT_IMP_REP_PATH` entry or by setting the `IT_IMP_REP_PATH` environment variable to override the one in the configuration file.

## Specifying Your Local Internet Domain

You can specify the name of the local Internet domain by using the `IT_LOCAL_DOMAIN` variable.

An example is:

```
IT_LOCAL_DOMAIN iona.com
```

A value for this variable is not always required—however, it is advisable to provide one. For example, it is required if both the host's full name (for example, `alpha.iona.com`) and abbreviated name (for example, `alpha`) are used in Orbix applications.

# Starting The Orbix Daemon

An Orbix daemon runs on each host to control aspects of the distributed system. The daemon is responsible for the following tasks:

- Starting servers when appropriate.
- Connecting clients to servers.
- Managing the Implementation Repository. The daemon accepts requests from the Orbix Implementation Repository commands.
- Searching for an appropriate server using the server locator. The daemon also manages the configuration files for the server locator.
- Providing information from the Interface Repository about the supported interfaces for clients that request it.

A typical start of the Orbix daemon without options is as follows:

```
orbixd
```

## Running the Orbix Daemon as an NT Service

On Windows NT platforms, you can install the Orbix daemon as an NT service as follows:

```
> orbixd -j
```

You must manually start the service on Windows NT platforms as follows:

1. Select **Start**→**Settings**→**Control Panel**→**Services**.
2. Highlight the Orbix daemon entry.
3. Click the **Start** button.

NT starts the service as `<path>\orbixd -b`.

To uninstall this service on Windows NT platforms, do the following:

```
> orbixd -w
```

### Using the `-o` Option to the Orbix Daemon

You should use the `-o` option if you are running `orbixd` as a super-user on UNIX platforms. This option indicates that if the daemon runs with super-user privileges, servers launched by the daemon should run using the specified user ID instead of the root ID.

You should run `orbixd` in this way for the following reasons:

- A client running as root on a remote machine could launch a server with root privileges on a different machine. This poses a serious security risk because a remote user could easily be faked. When the Orbix daemon is launched as `orbixd -o userId`, servers launched by the daemon run using the specified user ID instead of the root ID.
- When the daemon has super-user capabilities, the permissions of servers are indeterminate and depend on the permissions of the first remote user to start a specific server. For example, on UNIX the files written by a server may have different owners on different activations making it possible that the server would be unable to read or write files in future activations.

Refer to Appendix B, “Orbix Daemon Options” on page 99 for more details.

---

**Note:** Any changes you make to the configuration of Orbix do not take effect until you restart the Orbix daemon.

---

## Registering a Server

The `putit` utility registers servers with the Orbix Implementation Repository. You can use the `putit` command in its simplest form as follows:

```
putit server_name command_line
```

For example:

```
putit BankSrv /usr/users/chris/banker
```

The executable file `/usr/users/chris/banker` is registered as the implementation code for the server called `BankSrv` at the local host. You should use the full path name and not a relative path name. This is because Orbix interprets relative path names with respect to the Orbix daemon's current directory, not the `putit` user's current directory.

The `putit` command does not execute the indicated file. The file is automatically launched by Orbix in response to an incoming operation invocation.

---

**Note:** You should ensure that the server name specified in the `putit` command matches exactly the server name used in the server application code.

---

## Checking for an Orbix Daemon

Use the `pingit` utility to determine if an Orbix daemon is running on a particular host. For example:

```
pingit -h host_name
```

If the Orbix daemon is running at the target host, `pingit` displays a message to indicate this. Otherwise, `pingit` displays a `CORBA COMM_FAILURE` exception message.

## Checking for Running Servers

Use the `psit` utility to display information about all of the running servers that a particular Orbix daemon knows about.

One line is output for each server process. Each line of output has the following fields:

Name	The server name.
Marker	The object marker pattern associated with the process.
Code	The data encoder used; for example, XDR.

Comms	The communications protocol used; for example, TCP.
Port	The port number used by the communications system.
Status	One of “automatic”, “manual” or “inactive”.
Per-Client?	Indicates whether the server is a per-client server.
OS-pid	The operating system process.



# 3

## Managing the Implementation Repository

*When you install server applications on a network host, you must register those servers in the Orbix Implementation Repository. This repository allows Orbix to direct client operation calls to objects in servers and to start server processes when necessary. This chapter describes how to manage servers in the Implementation Repository.*

The chapter covers the following topics:

- The Implementation Repository and its entries.
- Basic usage of the Implementation Repository including registering servers, organizing server entries, removing server entries, listing registered servers, and displaying information about an entry.
- How to start a server manually.
- How to stop servers manually.
- The security of servers including how to change ownership of servers and how to modify access control lists.
- How to register servers in specialized activation modes other than simply one server process for all clients.
- How to manage the set of ports Orbix uses to run servers.

This chapter explains how to manage the Implementation Repository using Orbix command-line utilities. Refer to Chapter 7, “The Orbix Server Manager” for details of how you can use Orbix GUI tools.

# Implementation Repository Entries

The Implementation Repository maintains a mapping from a server's name to the filename of the executable code implementing that server. A server must be registered with the Implementation Repository to make use of this mapping. Orbix automatically starts the server (if it is not already running) when a client binds to one of the server's objects or when an operation invocation is made on any object that names that particular server.

When a client first communicates with an object, Orbix uses the Implementation Repository to identify an appropriate server to handle the connection. If a suitable entry cannot be found in the Implementation Repository during a search for a server, an error is returned to the client.

The Implementation Repository maintains its data in entries that include the following information:

- The *server name*.  
Server names can be hierarchical so the Implementation Repository supports directories.
- The *server owner*—usually the user who registered the server.
- The *server permission values*.  
These specify which users have the right to launch the server and which users have the right to invoke operations on objects in the server.
- One or more *activation orders*.  
An activation order associates an object or group of objects with a launch command. A launch command specifies how Orbix starts the server.

### Basic Implementation Repository Usage

Use the `putit` command to create or modify an Implementation Repository entry. For example, the following command registers a shared server called “FirstTrust” on the local host, with the specified executable file:

```
putit FirstTrust /work/bank/banker
```

Activation occurs when any of the objects managed by the `FirstTrust` server is used. In this example there is only one server process associated with this server and all clients share the same server process.

### Registering a Server on a Remote Host

The following command registers a shared server called “FirstTrust” on the remote host “alpha”, with the specified executable file and command-line argument:

```
putit -h alpha FirstTrust  
    "/work/bank/banker -v 1.1"
```

---

**Note:** If the server requires parameters and options, you should use quotes so that the `putit` command does not try to interpret them.

---

Using the `-h hostname` option enables you to use all the utility commands for remote hosts. However, for simplicity, most of the examples in this guide do not use this option and use the local host default instead.

### Organizing Servers Into Hierarchies

Server names may be hierarchically structured, in the same way as UNIX file names. Hierarchical server names are useful in structuring the name space of servers in Implementation Repositories. You can create hierarchical directories by using the `mkdirit` command. For example, you can make a new `banking` registration directory and make a registration within it as follows:

```
mkdirit banking  
putit banking/Berliner /usr/users/joe/banker
```

Thus `banking/Berliner` is a valid, hierarchical server name.

The `rmdirit` command removes a registration directory. This command can take a `-R` option to recursively delete a directory and the Implementation Repository entries and sub-directories within it. The `rmdirit` command returns an error if it is called without the `-R` option on a non-empty registration directory.

For example:

```
lsit
  FirstTrust
  banking
rmdirit banking
  directory not empty
rmdirit -R banking
```

This example uses the `lsit` command to display the Implementation Repository entries and directories.

To move an entry in the hierarchy, first remove it with the `rmit` command and then re-register it with the `putit` command.

## Removing a Registered Server

Use the `rmit` command to remove an Implementation Repository entry. For example, the following command removes a server entry:

```
rmit FirstTrust
```

This simplest format of the command removes the entry and all activation orders for the server.

You can also use the `rmit` command to remove specific activation orders. Use the `-marker` option for the shared or unshared activation modes to remove specific activation orders for individual objects. Use the `-method` option for the per-method call activation mode to remove specific activation orders for individual methods. Activation modes are described in section “Server Activation Modes” on page 31.

### Listing Registered Servers

Use the `lsit` command to list registered servers and directories. For example:

```
# Register a server called International and
# one called printer
putit International /usr/users/joe/banker
putit printer /usr/users/joe/print laser
# Register a server called Berliner.
# "Berlin 98-00-00" are parameters for the
# executable file.
putit Berliner
    /usr/users/joe/banker Berlin 98-00-00
lsit
    International
    Berliner
    printer
```

Use the `-R` option with the `lsit` command to recursively list all server entries in the given directory and its subdirectories.

### Displaying A Server Entry

Use the `catit` command to display information about a specific server's registration entry. The following example assumes the server `Berliner` is registered from the previous example:

```
catit Berliner
name:          Berliner
Activation:    shared
Owner:         smith
Launch:        ;jones;developers;friends;
Invoke:        ;all;
Per-client:    false

Marker  Launch_Command
*       /usr/users/joe/banker Berlin 98-00-00
```

The output includes the following:

name	Server name.
Activation	Activation mode.

Owner	The user who put the in the entry.
Launch	The users and groups who have permission to start or launch the server.
Invoke	The users and groups who have permission to invoke operations on an object controlled by the server.
Per-client	A per-client indicator that indicates whether a new server is to be launched for each client that uses the server.

The final output is a table of activation orders. An activation order is identified with a marker. An asterisk (\*) represents all objects and means that there is only one activation order for the server entry.

## Starting Servers Manually

Most servers are designed to have Orbix start them automatically when a client uses an object. The majority of an administrator's work therefore involves registering servers in the Implementation Repository and managing the registration entries in the repository. However, some servers do need to be started before any clients attempt to use their objects.

Servers that are started by some mechanism external to Orbix are useful for a number of reasons. For example, if a server takes a long time to initialize and it starts when a client request a service, it may cause the client to timeout. In addition, some servers that are meant to run as long-lived daemons may require manual starting. Manual servers are also known as *persistent servers* in CORBA terminology.

## Registering a Manual Server

All servers that are registered in the shared mode can also be started manually. Subsequent invocations on the objects are passed to the running process.

However, if you wish to prevent Orbix from starting a server and make it manual-only, use the following command:

```
putit FirstTrust -persistent
```

This command registers a manual-only server called “FirstTrust” on the local host. No start command is specified to `putit`, because this server cannot be started by Orbix automatically but can only start as a manual server.

The CORBA specification requires that unshared or per-method types of servers fail if an attempt is made to start them manually. This means that manual servers can only be registered as shared servers. Therefore, you cannot use the `-persistent` option with either the `-unshared` or `-per-method` options of the `putit` command. These unshared and per-method servers are described in section “Server Activation Modes” on page 31.

### Starting the Orbix Daemon for Unregistered Servers

In some circumstances, it can be useful not to register servers with the Implementation Repository. Under normal operation, Orbix would know nothing about these servers. However, if you invoke the Orbix daemon with the `-u` option, it maintains an active record of unregistered Orbix servers and clients that may use these servers:

```
orbixd -u
```

When Orbix is started this way, any server process can be started manually. However, no access control is enforced and there is no record of the server in the Implementation Repository.

### Stopping Servers

Just as most servers start automatically when needed, they are usually designed to stop automatically after some period. However, there may be other situations where you need to manually stop a server.

The `killit` command stops a server process by using the `SIGTERM` signal.

1. For example, the following command stops the `Berliner` server on the host `omega`:

```
killit -h omega /Banking/Berliner
```

2. When there is more than one server process, use the marker option and argument to distinguish between different processes. To do this, use the following `killit` command format:

```
killit -m marker server_name
```

# Security of Registered Servers

For each Implementation Repository entry, Orbix maintains two access control lists (ACLs) as follows:

- |        |   |
|--------|---|
| Launch | The users or groups that can launch the associated server. Users on this list, and users in groups on this list, can cause the server to be launched by invoking on one of its objects. |
| Invoke | The users and groups that can invoke operations on any object controlled by the associated server.  |

The entries in the access control list can be user names or group names. The owner of an Implementation Repository entry is always allowed to launch it and invoke operations on its objects. A client normally needs both launch and invoke access to use an automatically-launched server. The following sections describe how to modify ACLs by adding groups and users or removing groups and users from ACLs.

## Modifying Server Access

Use the `chmodit` command to modify the launch or invoke access control lists (ACLs). For example:

1. The following command allows the user `chris` to launch the server `AlliedBank`:  

```
chmodit AlliedBank l+chris
```
2. The following command grants the user `chris` rights to launch any server in the directory `banks/investmentBanks`:  

```
chmodit -a banks/investmentBanks l+chris
```
3. The following command revokes `joe`'s right to invoke all servers in the Implementation Repository directory `banks/commercialBanks`:  

```
chmodit -a banks/commercialBanks i-joe
```
4. There is also a pseudo-group named `all` that you can use to implicitly add all users to an ACL. The following command grants all users the right to invoke the server `banks/commercialBanks/AlliedBank`:  

```
chmodit banks/commercialBanks/AlliedBank i+all
```

On UNIX, the group membership of a user is determined using the user's primary group as well as the user's supplementary groups as specified in the `/etc/group` file.

### Changing the Owners of Registered Servers

Only the owner of an Implementation Repository entry can use the `chmodit` command on that entry. The original owner is the one who uses the `putit` command to register the server. Use the `chownit` command to change ownership. For example, use the following command to change the ownership of server `AlliedBank` to user `mcnamara`:

```
chownit -s AlliedBank mcnamara
```

An Implementation Repository directory may have more than one owner. An ownership ACL is associated with each directory in the Implementation Repository, and this ACL can be modified to give certain users or groups ownership rights on a directory. Only a user on an ownership ACL has the right to modify the ACL. Some other examples of changing ownership include the following:

1. To add the group `iona` to the ownership ACL on the Implementation Repository directory `banks/investmentBanks`, use the following command:

```
chownit -d banks/investmentBanks + iona
```

2. To remove `mcnamara` from the same ACL, do the following:

```
chownit -d banks/investmentBanks - mcnamara
```

3. Orbix supports the pseudo-group `all` that, when added to an ACL, grants access to all callers. The following command grants all users the ownership rights on directory `banks/commercialBanks`:

```
chownit -d banks/commercialBanks + all
```

Spaces *are* significant in this grammar; for example:

**CORRECT**      `chownit -d banks/investmentBanks + iona`

**INCORRECT**    `chownit -dbanks/investmentBanks + iona`

**INCORRECT**    `chownit -d banks/investmentBanks +iona`

### Determining the User and Group IDs of Running Servers

On Windows platforms, the user ID (*uid*) and group ID (*gid*) of a server process launched by the Orbix daemon are the same as those of the daemon itself.

On UNIX platforms, the effective `uid` and `gid` of a server process launched by the Orbix daemon are determined as follows:

1. If `orbixd` is not running as a super-user, such as `root` on UNIX, the `uid` and `gid` of every activated server process is that of `orbixd` itself.  
If `orbixd` is running as `root`, it attempts to activate a server with the `uid` and `gid` of the, possibly remote, principal attempting to activate the server.
2. If the principal is unknown (not a registered user) at the local machine on which `orbixd` is running, `orbixd` attempts to run the new server with `uid` and `gid` of a standard user called “`orbixusr`”.
3. If there is no such standard user “`orbixusr`”, `orbixd` attempts to run the new server with `uid` and `gid` of a user “`nobody`”.  
If there is no such user “`nobody`”, the activation fails and an exception is returned to the caller.

The daemon must be able to execute the server's executable file.

---

**Note:** If you are running `orbixd` as super-user, you should use the `-o` option to the Orbix daemon. This prevents a client running as a super-user on a remote machine from launching a server with super-user privileges on your machine. Refer to “Using the `-o` Option to the Orbix Daemon” on page 17 for more details.

---

# Server Activation Modes

Orbix provides a number of different *modes* for launching servers. You specify the mode of a server when it is registered. Usually, clients are not concerned with the activation details of a server or aware of what server processes are launched. The following primary activation modes are supported by Orbix.

### Shared Activation Mode

In this mode, all of the objects with the same server name on a given machine are managed by the *same* server process on that machine. This is the default activation mode.

If the process is already running when an application invocation arrives for one of its objects, Orbix routes the invocation to that process; otherwise Orbix launches a process.

### Unshared Activation Mode

In this mode, individual objects of a server are registered with the Implementation Repository. As each object is invoked, an individual process is run for that particular object—one process is created per active registered object. You can register each object managed by a server with a different executable file, or any number of objects can share the same executable file.

### Per-method call Activation Mode

In this mode, individual operation names are registered with the Implementation Repository. Inter-process calls can be made to these operations—and each invocation results in the launch of an individual process. A process is launched to handle each individual operation call, and the process is destroyed once the operation has completed. You can specify a different executable file for each operation, or any number of operations can share the same executable file.

The shared mode is most common. The unshared and per-method modes are rarely used. Refer to your server documentation to determine the correct activation modes to use.

### Registering Unshared Servers

The `-unshared` option registers a server in the unshared activation mode. For example:

```
putit -unshared
      NationalTrust /financial/banks/banker
```

This command registers an unshared server called “NationalTrust” on the local host, with the specified executable file. Each activation for an object goes to a unique server process for that particular object. However, all users accessing a particular object share the same server process.

### Using Markers to Specify Named Objects

Each Orbix object has a unique *object reference* that includes the following information:

- A name that is usually referred to as a *marker*.  
An object's interface name and its marker uniquely identify the object within a server. A server programmer can choose the marker names for objects or they can be assigned automatically by Orbix.
- A server name identifying the server in which the object is located.
- A host name identifying the host on which the server is located.

For example, the object reference for a bank account would include the bank account name (marker name), the name of the server that manages the account, and the name of the server's host.

Since objects can be named, shared and unshared server activation policies can specify individual object marker names. For example:

```
l. putit -marker College_Green
      NationalBank /financial/banks/banker
```

This command registers a shared server called “NationalBank” on the local host, with the specified executable file. However, activation only

occurs for the object whose marker matches “College\_Green”. There is at most one server process resulting from this registration request; although you can make other `-marker` registrations for server `NationalBank`. All users share the same server process.

2. 

```
putit -unshared -marker College_Gree
    FirstNational /banks/FNbank_CG
putit -unshared -marker St_Stephens_Green
    FirstNational /banks/FNbank_STG
```

The first command registers an unshared server called “FirstNational” on the local host with the specified executable files and the second adds an activation order (marker and launch command) for the “St\_Stephens\_Green” marker. However, activation only occurs for objects whose marker name is “College\_Green” or “St\_Stephens\_Green” and each activation for a specific object goes to a *unique* server process for that particular object. All users of a specific object share the same server process.

### Using Pattern Matching

You can use pattern matching in activation policies when seeking to identify which server process to communicate with. In particular, you can register a server activation policy for a subset of the server’s objects. Since the number of objects named can get very large, pattern matching also means you do not have to specify a separate policy for every possible object. You specify this object subset by using wildcard characters in a marker pattern. The pattern matching is based on regular expressions, similar to UNIX regular expressions.

You can use pattern matching to specify a set of objects for shared or unshared servers. For example, some registrations can be used as a means of sharing work between server processes in this case, between two processes:

```
putit -marker '[0-4]*'
    NationalBank /work/bank/NBBank
putit -marker '[5-9]*'
    NationalBank /work/bank/NBBank
```

If these two commands are issued, server `NationalBank` can have up to two active processes; one launched for objects whose markers begin with the digits 0 through 4 and the other for markers beginning with digits 5 through 9.

Refer to the entry for the `putit` command in Appendix C, “Command Reference” for a complete list of recognized patterns with examples.

Use the `rmit` command with `-marker` option to modify a server entry. This allows you to remove a specific activation order for a server without removing the entire server entry. You can also use pattern matching with the `rmit` command's `marker` option.

## Registering Per-Method Servers

A per-method server processes each operation call in a separate process.

1. The following command registers a per-method server called “NationalTrust” on the local host with the specified executable file. The activation occurs only if the operation `makeWithdrawal()` is called.

```
putit -per-method -method makeWithdrawal
      NationalTrust /financial/NTbank
```

2. If the `-method` option is used, Orbix assumes that the server is a per-method server.

```
putit -method makeDeposit
      NationalTrust /financial/NTbank
```

You can specify patterns for methods so that operation names matching a particular pattern causes Orbix to use a particular server activation. The use of pattern matching allows a group of server processes to share a workload between them, whereby each server process is responsible for a range of methods. The pattern matching is based on regular expressions similar to UNIX regular expressions.

3. The following command registers a per-method server called “FirstTrust” on the local host with the specified executable file.

```
putit -per-method FirstTrust
      -method 'make*' /financial/banker
```

The activation is to occur only if an operation matching the pattern “make\*” is being called, for example `makeDeposit()` or `makeWithdrawal()`. A separate process is activated for each method call.

---

**Note:** You can only use method pattern matching in the per-method activation mode, thus the `-per-method` option is redundant.

---

Use the `rmit` command with `-method` option to modify a per-method server entry. This allows you to remove a specific activation order for a server without removing the entire server entry. You can also use pattern matching with the `rmit` command's `-method` option.

## Secondary Activation Modes

For each of the primary activation modes, a server can be launched in one of the secondary activation modes described as follows:

### Multiple-client Activation Mode

In this mode, activations of the same server by different users share the same process, in accordance with the selected primary activation mode. This is the default secondary activation mode. No `putit` option is required to specify this mode when registering a server.

### Per-client Activation Mode

In this mode, activations of the same server by different users cause a different process to be launched for each end-user.

Use the `putit -per-client` option to register a server in this secondary activation mode.

### Per-client-process Activation Mode

In this mode, activations of the same server by different client processes cause a different process to be created for each such client process.

Use the `putit -per-client-pid` option to register a server in this secondary activation mode. For example, the following command registers a shared, per-client-process server:

```
putit -per-client-pid  
FirstTrust /work/bank/banker
```

Activation occurs when any of the objects managed by the `FirstTrust` server are used; there is a separate server process for each different client process.

## Managing Server Port Selection

When the Orbix daemon activates a server, the server is activated by the Orbix daemon, it is assigned a port so that clients can communicate with it. There are two ways to control the port numbers assigned to a server:

- Registering the server with a specified port number.
- Using configuration variables to control port numbers.

This section describes each of these approaches.

### Registering Servers with Specified Ports

When registering a server, you can specify the port on which the server should listen using the `-port` option to `putit`. For example, to specify that shared server `FirstTrust` should communicate on port 1597, do the following:

```
putit -port 1597 FirstTrust /work/bank/banker
```

By default, all Orbix applications communicate over the CORBA standard Internet Inter-ORB Protocol (IIOP). The `-port` option is very important for such applications.

If an Orbix server that communicates over IIOP publishes an object reference, for example using the CORBA Naming Service, this reference is valid while the server continues to run. However, if the server exits and then recreates the same object, the published object reference is not valid unless the server always runs on the same port. If your servers require this functionality, you should register them using the `-port` option.

### Controlling Port Allocation with Configuration Variables

You can control the range of server port numbers chosen by the Orbix daemon by using the configuration entries `IT_DAEMON_SERVER_BASE` and `IT_DAEMON_SERVER_RANGE`. The `IT_DAEMON_SERVER_BASE` must be set and the recommended value is 1590. You do not have to set `IT_DAEMON_SERVER_RANGE` which has a default value of 50.

When the Orbix daemon starts a server, the first server port assigned is `IT_DAEMON_SERVER_BASE` plus 1, and the last assigned is `IT_DAEMON_SERVER_BASE` plus `IT_DAEMON_SERVER_RANGE`. For example, using the default values the server ports range from 1591 to 1640.

Once the end of the range is reached, `orbixd` recycles the range in an attempt to find a free port. If no free port is found, an `IMP_LIMIT` system exception is raised to the client application attempting an invocation to the server.

You can set `IT_DAEMON_SERVER_BASE` and `IT_DAEMON_SERVER_RANGE` values by using their entries in the `common.cfg` configuration file, or by setting the corresponding environment variables. Values you set must be greater than 1024 and you should make sure that they do not conflict with other services. Make sure the range you choose is greater than the maximum number of servers you expect to run on the host.



# 4

## Managing the Server Locator

*The Orbix server locator allows client applications to bind to objects in servers without specifying the names of the hosts on which the server runs. This chapter describes how to maintain the server locator configuration files.*

A client connects to a server by obtaining a reference to an object in that server. A client can obtain an object reference in several ways; for example, using the Naming Service or the Orbix-specific bind mechanism. The Orbix bind mechanism allows a client to locate an object by specifying the object's name, the name of the server, and the host on which the server runs.

If a client does not specify the server host name when binding to an object, Orbix uses its server locator to find a host on which the server is registered. The server locator is implemented in the Orbix daemon. If the client uses the server locator mechanism, the Orbix daemon must be running on the client host.

The server locator uses two configuration files when searching for a server. These files are the *server location file* and the *host groups definition file*. The server location file maintains a mapping from a server name to a list of hosts and host groups on which the server runs. The host groups definition file defines names for groups of hosts.

The two configuration files can be maintained either by editing them as normal files or by using the utility commands `serverhosts`, `grouphosts` and `servergroups`.

## Locating Server Locator Files

The server locator uses specific location files to search for the server. On UNIX platforms, the server locator files are:

<code>Orbix.hosts</code>	This <i>server location</i> file maintains a mapping from a server name to a list of hosts and host groups on which the server runs.
<code>Orbix.hostgroups</code>	This <i>host groups definition</i> file defines the groups in which hosts are organized.

On Windows platforms these files are called `orbix.hst` and `orbix.hgp` respectively.

The Orbix daemon searches for the directory that contains these files by looking in the following places:

1. The environment variable `IT_LOCATOR_PATH`.
2. The `IT_LOCATOR_PATH` entry in the Orbix configuration file.

On UNIX platforms, it also looks in the `etc` directory.

## The Server Locator Algorithm

The default server locator searches for a server as follows:

1. The server locator, implemented in the Orbix daemon, reads the locator configuration files to obtain a list of potential hosts for the server.
2. The locator arranges these hosts in a random order. Orbix then iterates through these hosts, attempting to verify the registration of the server at each host in turn.
3. The client binds to the object at the first host at which the server is registered.
4. If the server is registered at none of the configured hosts, the client attempts to bind to the server at the local host. If the server is not registered at the local host, the location attempt fails.

# Configuration File Formats

The main entries for the server locator are held in the server location file. Each line of this file contains the following fields:

```
server_name:list_hosts:list_host_groups
```

The fields are separated by a colon and no white space is allowed between or within the fields. Either of the last two fields can be null (but the two colon characters are still required. If both of the last two fields are null, this is equivalent to a null entry. The fields are interpreted as follows:

<i>server_name</i>	Specifies the server for which host names and host groups are being recorded.
<i>list_hosts</i>	Specifies the list of hosts on which the server runs. The individual host names are separated by a comma.
<i>list_host_groups</i>	Specifies the list of host groups on which the server runs. Host groups are explained later in this section.

Example entries are as follows:

```
bank:alpha,beta,gamma:  
spreadsheet:alpha,beta:financial  
mail::all
```

Only one entry is allowed in this file for any given server name.

There is one special entry in the server location file: the server name `IT_daemon`. The entry for this indicates the single machine to contact in the case that no entry can be found for a particular server. If an entry for a required server cannot be found in the server location file of the caller, Orbix forwards the search to the host entered under `IT_daemon`. That host uses its locator and its version of the server location file to locate the required server, perhaps passing the search to yet another host.

One possible use of this is to have the `IT_daemon` entries for a set of machines arranged so that all of the machines are searched. For example, the entry for this on host `alpha` could be as follows:

```
IT_daemon:beta:
```

On host `beta` it would be as follows:

```
IT_daemon:alpha:
```

The server locator limits the number of hops that it makes in attempting to resolve a server name. Hence a circular dependency between host files, as suggested above, does not cause difficulty.

Orbix allows you to gather hosts into groups for easier management. In particular, you can specify group names as the last field of an entry in the locator's table. Groups are defined in the `hostgroups` definition file. Each line of this file must have the following format:

```
group_name: list_hosts:
```

Note the terminating colon character. An example `hostgroups` definition file is as follows:

```
financial:gamma,delta:  
all:alpha,beta,gamma,delta:
```

## Using the `serverhosts` Command

Use the `serverhosts` command to access the server location file to:

- List the hosts that support a specified server.
- Modify that list by adding or deleting hosts.

The command syntax is as follows:

```
serverhosts server_name [-v] [-h host_name]  
[-r host_list] [-a host_list] [-l]
```

---

**Note:** Because of the host lists, the `server_name` argument comes immediately after the command name, not after the options.

---

The options are as follows:

- r Removes all of the hosts in the given list from the entry for the specified server.
- a Adds all of the hosts in the given list to the entry for the specified server. An entry for the specified server name is created if it does not already exist.
- l Lists all of the hosts for the specified server.

The `-h` option is used to specify the host of the Orbix daemon that should process the request. This defaults to the local host.

If more than one option is specified, they are executed in the following order:

```
-r -a -l
```

## Using the `servergroups` Command

Use the `servergroups` command to access the server location file to do the following:

- List the host groups that support a specified server.
- Modify that list by adding or deleting groups.

The command syntax is as follows:

```
servergroups server_name [-h host_name] [-v]  
[-r group_list] [-a group_list] [-l]
```

---

**Note:** Because of the group lists, the `server_name` argument comes immediately after the command name, not after the options.

---

The options are as follows:

- r Removes all of the groups in the given list from the entry for the specified server.
- a Adds all of the groups in the given list to the entry for the specified server. An entry for the specified server name is created if it does not already exist.
- l Lists all of the groups for the specified server.

The `-h` option is used to specify the host of the Orbix daemon that should process the request. This defaults to the local host.

If more than one option is specified, they are executed in the following order:

```
-r -a -l
```

## Using the `grouphosts` Command

Use the `grouphosts` command to access the `hostgroups` definition file to:

- List the hosts in a specified group.
- Modify that list by adding or deleting hosts.

The command syntax is as follows:

```
grouphosts group_name [-h host_name] [-v]  
          [-r host_list] [-a host_list] [-l]
```

---

**Note:** Because of the host lists, the `group_name` argument comes immediately after the command name, not after the options.

---

The options are as follows:

- r Removes all of the hosts in the given list from the specified group.
- a Adds all of the hosts in the given list to the specified group. The group is created if it does not exist.
- l Lists all of the hosts for the specified group.

The `-h` option is used to specify the host of the Orbix daemon that should process the request. This defaults to the local host.

If more than one option is specified, they are executed in the following order:

```
-r -a -l
```



# 5

## Managing the Interface Repository

*The Interface Repository is the component of Orbix that stores information about IDL definitions and allows clients to retrieve this information at runtime. This chapter describes how to manage the contents of the Interface Repository.*

The Interface Repository maintains full information about the IDL definitions implemented in your system. Given an object reference, a client can determine at runtime the object's type and all information about that type by using the Interface Repository. Clients can also browse contents of the Interface Repository.

To allow a client to obtain information about a set of IDL definitions, you must add those definitions to the Interface Repository. Orbix supports commands that allow you to add IDL definitions to the repository, read the contents of the repository, and remove definitions from it. Each of these commands accesses the Interface Repository through the Interface Repository server.

This chapter explains how to manage the Interface Repository using Orbix command-line utilities. Refer to Chapter 8, "The Interface Repository Browser" for details of how you can use Orbix GUI tools.

## Configuring the Interface Repository

The Interface Repository has its own directory, which is specified by the `IT_INT_REP_PATH` entry in the `common.cfg` configuration file or as an environment variable. `IT_INT_REP_PATH` is a required variable.

You must configure the Interface Repository before the IDL compiler or applications can use it. To configure the Interface Repository, do the following:

1. Specify a value for the `IT_INT_REP_PATH` entry in the `common.cfg` file or as an environment variable. For example:

```
IT_INT_REP_PATH /orbix/IntRep
```

2. Create the corresponding directory if it does not already exist.

```
mkdir /orbix/IntRep
```

3. If the Orbix daemon is running, stop it and then restart it so that it recognizes the new configuration variable:

```
orbixd
```

## Registering the Interface Repository Server

The Interface Repository is accessed through an Orbix server. The interfaces to the Interface Repository objects are defined in IDL and you must register the Interface Repository server using the `putit` command. For example:

```
putit IFR /orbix/ifr/bin/IFR
```

Orbix expects that the server is registered with the name `IFR` as a shared server. The Interface Repository's executable file is in the `bin` directory with the name `IFR`.

The Interface Repository server can be launched by the Orbix daemon, or it can be launched manually. For example, the server executable file can be explicitly run as a background process:

```
/orbix/ifr/bin/IFR
```

This has the advantage that the Interface Repository can initialize itself before any other processes need to use it.

The server executable file can take the following options:

- h            Print a summary of switches.
- L            Immediately load data from the Interface Repository data directory. The default is not to do this, but instead to load each file on demand at runtime as it is required.
- t *time*     Specify the timeout in seconds for the Interface Repository server. The default timeout is infinite.
- v            Print version information about the Interface Repository.

## Adding IDL Definitions

The Orbix utility `putidl` allows you to enter all the definitions in a single IDL source file into the Interface Repository. This utility provides a simple and safe way to add IDL definitions to the repository.

For example, the following command adds the definitions in the file `banksimple.idl` to the Interface Repository:

```
putidl banksimple.idl
```

The `putidl` utility parses the definitions in the file `banksimple.idl` and integrates the definitions into the repository. If the file `banksimple.idl` uses definitions already registered in the repository, `putidl` checks that the definitions are used consistently before updating the repository contents.

If you modify the file `banksimple.idl`, you can update the contents of the Interface Repository by repeating the `putidl` command.

Although `putidl` takes an IDL file as an argument, the Interface Repository does not store information about the file itself. The Interface Repository has no knowledge of the file associated with specific IDL definitions. This means that you cannot remove definitions based on the file in which they were declared. For this reason, it is important that you use modules in your IDL definitions to group definitions in logical units.

## Reading the Interface Repository Contents

The `readifr` utility allows you to read a specified IDL definition from the Interface Repository. For example, to view the definition of interface `Bank` defined in module `Finance`, do the following:

```
readifr Finance::Bank
```

This utility prints the IDL definition to the standard output.

If you use `readifr` to view an IDL interface definition, you can instruct it to also display all derived interfaces. To do this, specify the `-d` option, for example:

```
readifr -d Finance::Bank
```

## Removing IDL Definitions

The `rmidl` utility allows you to remove an IDL definition from the Interface Repository. This utility takes a fully scoped name for an IDL definition as an argument.

For example, to remove information about the IDL operation `create_Account()` defined on interface `Bank` in module `Finance`, do the following:


```
rmidl Finance::Bank::create_Account()
```

The `rmidl` command removes definitions recursively. For example, to remove the module `Finance` and all definitions within this module, do the following:

```
rmidl Finance
```

Part II

# Orbix GUI Tools





# 6

## The Orbix Configuration Explorer

*Components of an Orbix system are configured using a number of configuration files, as described in Chapter 2, “Getting Started”. The Orbix Configuration Explorer allows you to configure Orbix components without modifying the configuration files directly.*

The Orbix configuration files configure the main components of Orbix, and each Orbix installation has at least one copy of each file. The Orbix Configuration Explorer allows you to modify any Orbix configuration file on your system.

The configuration files include settings that affect the configuration of Orbix and settings that affect the configuration of other Orbix products, for example OrbixNames. The Orbix Configuration Explorer allows you to modify all these settings, and to create additional settings. This tool integrates all Orbix configuration in a single user interface.

By default, the Configuration Explorer allows you to configure settings that are:

- Common to multiple IONA products.
- Orbix-specific
- OrbixNames-specific

## Starting the Configuration Explorer

You can run the Configuration Explorer from the Windows **Start** menu, or by entering `configurationexplorer` at the command line. The Configuration Explorer appears as shown in Figure 6.1.




Figure 6.1: Orbix Configuration Explorer

This tool includes the following elements:

- *A menu bar.*
- *A toolbar.*
- *A navigation tree.*

The navigation tree displays icons that represent each configuration file and configuration scope.

- *A text box.*

The **Name** textbox displays the name of the current configuration file or scope.

- *A text pane.*

The *text pane* control contains a **Name** column and a **Value** column as shown in Figure 6.2 on page 56. Each row corresponds to individual configuration file entries. The text pane enables you to view and modify these entries.

At startup, the Orbix Configuration Explorer opens the `iona.cfg` root configuration file. By default, this file is located in the `config` directory of your Orbix installation. The Configuration Explorer navigation tree displays icons that represent the configuration files included in `iona.cfg` as shown in Figure 6.1 on page 54.

## Configuring Common Settings

To configure settings that are common to multiple IONA products, select the **Common** icon in the navigation tree. This icon represents the `Common` configuration scope in the file `common.cfg`. The `Common` variables stored in the default `common.cfg` configuration file then appear in the text pane, as shown in Figure 6.2 on page 56.




Figure 6.2: Common Configuration Settings

The default **Common** configuration settings are as follows:

IT_DAEMON_PORT	The TCP port number on which the Orbix daemon receives communications from clients.
IT_DAEMON_SERVER_BASE	The first TCP port number assigned by the daemon to a server. Each server listens on a single port number for client connection attempts.
IT_IMP_REP_PATH	The full path name of the Orbix Implementation Repository directory.
IT_INT_REP_PATH	The full path name of the Orbix Interface Repository directory.
IT_LOCATOR_PATH	The full path name of the directory that stores the locator configuration files.
IT_LOCAL_DOMAIN	The Internet domain name for your local network.
IT_JAVA_INTERPRETER	The full path name to the Java Runtime Environment binary executable. This installs with Orbix by default.
IT_DEFAULT_CLASSPATH	The default classpath used when Java servers are automatically launched by the daemon.

To update any of these settings, do the following:

1. Select the variable in the text pane.
2. Double-click on this variable in the **Value** column
3. Enter your new setting.
4. Select the **Apply** button to save your setting to the appropriate configuration file.

You cannot undo settings that you have saved to file.

## Configuring Orbix-Specific Settings

To configure settings that apply to Orbix only, select the **Orbix** icon in the navigation tree. This icon represents the Orbix configuration scope in the file `orbix3.cfg`. The Orbix variables stored in the default `orbix3.cfg` configuration file then appear in the text pane, as shown in Figure 6.3.




Figure 6.3: Configuring Orbix-Specific Settings

By default, the **Orbix** configuration settings include the following:

<code>IT_ERRORS</code>	The full path name of the Orbix error messages file.
<code>IT_CONNECT_ATTEMPTS</code>	If a client fails to connect to a server, Orbix retries the connection attempt every two seconds until the client succeeds. This value specifies the maximum number of retry attempts.

To update these settings, do the following:

1. Select the variable in the text pane.
2. Double-click on this variable in the **Value** column to enter your setting.
3. Select the **Apply** button to save your setting to the appropriate configuration file.

You can also modify OrbixNames-specific configuration variables by following these steps. Refer to the *OrbixNames Programmer's and Administrator's Guide* for details of configuration variables that are specific OrbixNames.


## Customizing Your Configuration

By default, the Orbix Configuration Explorer displays the configuration variables contained in the default configuration files. You can use the Orbix Configuration Explorer to customize your configuration by:

- Creating configuration variables.
- Creating configuration scopes.
- Creating configuration files.

### Creating Configuration Variables

By default, the Configuration Explorer displays a default subset of the available configuration variables. You can also create additional configuration variables, as shown in Figure 6.4.



**Figure 6.4:** *Creating Configuration Variables*

To create a configuration variable, perform the following steps:

1. Select the **Create Configuration Variable** button, shown in Figure 6.5 on page 61.
2. Double-click the new entry in the **Name** column of the text pane.
3. Enter a name for your configuration setting.

4. Double-click the entry in the **Value** column.
5. Enter a value for your configuration variable
6. Select the **Apply** button to save your setting to the appropriate configuration file.



**Figure 6.5:** *Creating and Deleting Configuration Variables*

### Valid Names for Configuration Variables and Scopes

You can use the following characters when naming configuration variables and scopes:

[ "\_", "-" ], [ "a"-"z", "A"-"Z" ], [ "0"-"9" ]

---

**Note:** You cannot use spaces when naming configuration variables and configuration scopes.

---

There are no restrictions on the valid characters for configuration values.

### Deleting Configuration Variables

You cannot delete the configuration variables included in the default configuration files. You can only change the values of these variables. However, you can delete any additional variables that you may have created.

To delete a configuration variable, do the following:

1. Select the setting to be deleted from the text pane.
2. Select the **Delete Configuration Variable** button, shown in Figure 6.5.
3. Select the **Apply** button to save your setting to the appropriate configuration file.

Refer to Appendix A, “Configuration Variables” on page 95 for a complete list of both common and Orbix-specific configuration variables.

### Creating Configuration Scopes

The Configuration Explorer displays the configuration variables contained in the default configuration files. You can customize your configuration by creating additional configuration *scopes*. Configuration scopes are containers for configuration variables. Refer to “The Orbix Configuration Files” on page 10 for more details.

In the navigation tree, user-defined configuration scopes are displayed as branching from default configuration scope icons, as shown in Figure 6.6 on page 63.

To create a user-defined configuration scope, do the following:

1. Select **Edit**→**Create Scope** from the menu bar. Alternatively, you can use the **Create Scope** toolbar.
2. In the **Name** text box, enter the name of your configuration scope.
3. Select the **Apply** button to save your setting to the appropriate configuration file.

You can then create new configuration variables within your configuration scope, as described in “Creating Configuration Variables” on page 60.

### Deleting Configuration Scopes

You cannot delete the default configuration scopes included in the default configuration files. However, you can delete any additional scopes that you may have created.

To delete a configuration scope, do the following:

1. From the navigation tree, select the scope to be deleted.
2. Select the **Edit**→**Delete Scope** menu option. Alternatively, you can use the **Delete Scope** button on the toolbar.

Select the **Apply** button to save your setting to the appropriate configuration file.




Figure 6.6: Creating Configuration Scopes

## Creating Configuration Files

You can extend the Configuration Explorer to display custom configuration files. To create a configuration file you should edit your `iona.cfg` file to include the additional configuration file. An icon associated with this configuration file then appears in the Configuration Explorer navigation tree.

You can then create new configuration scopes and variables within your new configuration file as usual, as described in “Creating Configuration Variables” on page 60 and “Creating Configuration Scopes” on page 62.



# 7

## The Orbix Server Manager

*The Implementation Repository is the component of Orbix that maintains registration information about servers and controls their activation. The Orbix Server Manager allows you to manage the Implementation Repository.*

The Implementation Repository maintains a mapping from a server name to the executable code that implements that server. In an Orbix system, the Orbix daemon on each host has an associated Implementation Repository. The Implementation Repository allows the daemon to launch server processes in response to operation calls from Orbix clients.


The Orbix Server Manager allows you to do the following:

- Browse an Implementation Repository.
- Register new servers.
- Modify existing server registration details.

The *Orbix C++ Programmer's Guide* describes the Implementation Repository in detail. This chapter assumes that you are familiar with this description.

## Starting the Server Manager

You can run the Server Manager from the Windows **Start** menu or by entering `srvmgr` at the command line. The main Server Manager window appears as shown in Figure 7.1.



**Figure 7.1:** *Server Manager Main Window*

The **Server Manager** window includes the following elements:

- A *menu bar*.
- A *toolbar*.
- A *navigation tree*.

This tree displays a graphical representation of the contents of an Implementation Repository.

- A *server information pane*.

If you select an item in the navigation tree, the pane to the right of the tree displays detailed information about that item. Information about servers is displayed in a tabbed folder.

- A *status bar*.

You can use the toolbar icons in place of the menu options described in this chapter.

## Connecting to an Implementation Repository

To connect to an Implementation Repository, do the following:


- I. Select **Host**→**Connect**. The **Connect to Host** dialog box appears, as shown in Figure 7.2.



**Figure 7.2:** Connect to Host Dialog Box

2. In the **Host Name** text box, enter the name or IP address of the host on which the required Orbix daemon runs. The default is the local host.
3. In the **Port Number** text box, enter the TCP/IP port number on which the Orbix daemon runs. To make a port number the default, select the **Set as Default Port** check box. The default port number is initially set to 1570.
4. Select the **Connect** button. The main Server Manager window displays the contents of the Implementation Repository. For example, Figure 7.3 shows an Implementation Repository on the local host.

You can disconnect from an Implementation Repository at any time. To disconnect, in the main window, select the required host and then select **Host→Disconnect**.



**Figure 7.3:** Connection to an Implementation Repository


## Creating a New Directory

The Implementation Repository supports the concept of directories. This allows you to structure server names hierarchically, and organize the contents of an Implementation Repository.

To create an Implementation Repository directory, do the following:

1. Select the Implementation Repository on the appropriate host.
2. Select **Directory**→**New**. The **Directory Name** text box appears in the right hand pane of the main window, as shown in Figure 7.4 on page 70.
3. In the **Directory Name** text box, enter the name of the new directory.
4. Select the **Apply** button. The main Server Manager window now includes the new directory when displaying the contents of the Implementation Repository. For example, if you create a `Bank` directory, this directory is displayed in the directory tree after the **Apply** button is selected. This is shown in Figure 7.4 on page 70.

To delete a directory, select the directory in the main **Server Manager** window and then select **Directory**→**Delete**.



**Figure 7.4:** *Creating a New Directory*

## Registering a Server

To register a server, do the following:

1. Select the Implementation Repository directory in which you wish to register the server. For example, to register a server in directory *Bank*, select the icon for this directory in the main window.
2. Select **Server**→**New**. A tabbed folder appears in the right pane of the main window as shown in Figure 7.5 on page 72. This folder is used to record a server's registration details.
3. Enter the server name in the **Server Name** text box on the **General** tab.
4. If the server is an Java server, select the **OrbixWeb Server** check box.
5. By default, only the user who registers the server can run clients that launch the server or invoke operations on server objects.

To provide server access rights to other users, select the **Rights** tab. The **Rights** tab is described in “Providing Server Access Rights to Users” on page 73.

6. The default server primary activation mode is shared. The default secondary activation mode is normal.

To modify the server activation details, select the **Activation** tab. The **Activation** tab is described in “Specifying Server Activation Details” on page 75.




Figure 7.5: Registering a New Server

### Providing Server Access Rights to Users

During server registration, you can provide server access rights to other users by selecting the **Rights** tab in the main window. The **Rights** tab appears as shown in Figure 7.6 on page 74.

Orbix offers two types of access rights:

- Launch rights
- Invoke rights

Launch rights allow clients owned by a specified user to cause the Orbix daemon to activate the server.

Invoke rights allow clients owned by a specified user to invoke operations on objects in the server.

To provide launch or invoke rights to a user, do the following:

1. In the appropriate area, enter the user identifier in the text box. To grant these rights to all users, enter the user name `all`.
2. Select **Add**.

To remove launch or invoke rights for a user, do the following:

1. In the appropriate user list, select the required user identifier.
2. Select **Remove**.

When you have added or removed the required users from the access rights lists, select **Apply** to commit the changes.




Figure 7.6: Providing Server Access Rights

## Specifying Server Activation Details

During server registration, you can specify the server activation details by selecting the **Activation** tab in the Server Manager main window. The **Activation** tab appears as shown in Figure 7.7.





Figure 7.7: Specifying Server Activation Details

### Activation Modes

To specify a server's *primary activation mode*, use the radio buttons in the **Activation Mode** section of the **Activation** tab. The default server primary activation mode is shared.

To specify a server's *secondary activation mode* select the **Advanced** button in the **Activation Mode** section. This launches the **Secondary Activation Modes** dialog box, as shown in Figure 7.8. The default secondary activation mode is normal.



**Figure 7.8:** Secondary Activation Modes

A server registered in shared activation mode can have an associated maximum number of processes. The Orbix daemon launches up to the specified number of processes for that server.

Each new client connection results in a new server process until the maximum number of processes is available. Subsequent client connections are routed to existing server processes using a round-robin algorithm. This provides a primitive form of load-balancing for shared servers.

To specify the number of processes associated with a shared server, enter a positive integer value in the **Max. number of processes associated with this server** text box.

You can associate a well-known TCP/IP port number with servers that communicate using the CORBA-defined Internet Inter-ORB Protocol (IIOP). To specify a well-known IIOP port for a server, select the **Use a Well known IIOP Port** check box and enter a value in the **Port Number** text box.

When you have specified the server activation details, select **OK** to confirm these details.

### Launch Commands

The **Commands** section on the **Activation** tab allows you to modify the launch commands associated with a server. Launch commands depend on the server activation mode, as follows:

#### Shared Activation Mode

If the server activation mode is *shared*:

1. Enter the server launch command in the **Command** text box.
2. Enter a \* character in the **Marker** text box.
3. Select **Add**.

#### UnShared Activation Mode

If the server activation mode is *unshared*:

1. Enter a marker pattern in the **Marker** text box.
2. Enter the launch command for this marker pattern in the **Command** text box.
3. Select **Add**.

Repeat this process for each marker pattern you wish to register.

---

**Note:** A server registered in the Implementation Repository must have at least one launch command.

---

### Per-method Activation Mode

If the server activation mode is *per-method*:

1. Enter a method name in the **Marker** text box.
2. Enter the launch command for this method in the **Command** text box.
3. Select **Add**.

Repeat this process for each method you wish to register.

## Modifying Server Registration Details

When you register a server, the Orbix daemon creates a server registration record in the Implementation Repository. This record stores detailed information about the server.

To modify a server registration record, do the following:

1. Select the server you wish to modify.  
The Server Manager displays the tabbed folder containing all the registration details for the selected server.
2. Select the required tab from the following:
  - ◆ **General**
  - ◆ **Activation**
  - ◆ **Rights**
3. Enter the value in the appropriate section of the tab, as described in “Registering a Server” on page 71.
4. Select the **Apply** button.

## Launching a Persistent Server

Orbix allows you to launch shared servers manually. A manually-launched server is known as a *persistent server*.

To launch a persistent server process, do the following:

1. Select the server you wish to launch. The server must be registered in shared mode.
2. Select **Server**→**Launch**. If successful, this starts the server executable file specified in the server launch command. The icon for the selected server displays a green traffic light while the server process runs, as shown in Figure 7.9.

To kill a shared server process, select **Server**→**Kill**.





Figure 7.9: Launching a Persistent Server

## Configuring the Server Manager

To configure the Server Manager, do the following:

1. In the main Server Manager window, select **Server Manager**→**Options**. The **Options** dialog box appears, as shown in Figure 7.10.



**Figure 7.10:** *The Options Dialog Box*

2. By default, the Server Manager does not connect to an Orbix daemon at startup. To specify that the Server Manager should connect to the Orbix daemon at the local host, select the **Connect to your local host on startup** check box.
3. The Server Manager allows you to register C++ or Java servers. By default, the Server Manager assumes that all servers are C++ servers. To change this default, select **Create Java Servers by default**.

4. You can also select the transport protocol used. The default protocol is IIOIP (Internet Inter-Orb Protocol). To change this default, select the check box labelled **Set the transport protocol to use Orbix**.
5. To enable on-line help, enter the **Location of your internet browser** in the text box provided.
6. Select **OK** to commit the new configuration.

---

**Note:** The main Server Manager window refreshes itself automatically, reflecting updates as they occur. This means that the **Refresh Time** option, used in earlier versions of the Orbix Server Manager, is no longer necessary.

---



# 8

## The Interface Repository Browser

*The Orbix Interface Repository provides persistent storage of IDL definitions and allows CORBA applications to retrieve information about those definitions at runtime. The Interface Repository browser allows you manage IDL definitions in the Interface Repository.*

Some CORBA applications, for example applications that use the Dynamic Invocation Interface (DII) to invoke operations, require runtime access to information about IDL definitions. The Interface Repository allows you to store IDL definitions for retrieval by these applications.


The Interface Repository browser enables you to add IDL definitions to the Interface Repository and view information about those definitions. CORBA applications can retrieve information about those definitions using standard IDL interfaces implemented by the Interface Repository.

The Interface Repository browser also enables you to export IDL definitions from the Interface Repository to a file. This feature makes the Interface Repository browser a useful development tool for managing the availability of IDL definitions in your system.

The *Orbix C++ Programmer's Guide* describes the Interface Repository in detail. This chapter assumes that you are familiar with this description.

## Starting the Interface Repository Browser

To start the Interface Repository browser, use the Windows **Start** menu or enter `orbixifr` at the command line. The main Interface Repository browser window appears as shown in Figure 8.1.



**Figure 8.1:** *The Main Interface Repository Browser Window*

The browser interface includes the following elements:

- *A menu bar.*
- *A tool bar.*
- *A navigation tree.*

This tree displays a graphical representation of the contents of an Implementation Repository.

- A multi-columned list box.

This list box displays information about IDL definitions selected in the navigation tree.

- A status bar.


You can use the toolbar icons in place of the menu options described in this chapter.

## Connecting to an Interface Repository

The Interface Repository is implemented as an Orbix server. The *Orbix C++ Programmer's Guide* describes how you make an Interface Repository server available to your system.

To connect to an Interface Repository server, do the following:

1. Select **Host**→**Connect**. The **Connect** dialog box appears, as shown in Figure 8.2.



**Figure 8.2:** The Connect Dialog Box

2. In the text box, enter the name or IP address of the host on which the Interface Repository server runs.
3. Select **OK**. The navigation tree in the main browser window displays the contents of the Interface Repository.

## Adding IDL to the Interface Repository

The Interface Repository browser allows you to import IDL definitions from a source file. This is a safe mechanism for adding IDL definitions to the Interface Repository which maintains the Interface Repository in a consistent state.

To add IDL definitions to the Interface Repository, do the following:

1. Select **File**→**Import**. The standard **Open File** dialog box for your operating system appears.
2. In the dialog box, enter the name of the source file in which your IDL is defined.
3. Select **OK**. In the main browser window, the navigation tree control displays the contents of the Interface Repository including the new IDL definitions.

Consider the following example IDL source file:

```
// IDL
interface Grid {
    readonly attribute short height;
    readonly attribute short width;

    long get (in short n, in short m);
    void set (in short n,
             in short m, in long value);
};
```

If you import this file into an empty Interface Repository, the main browser window appears as shown in Figure 8.3 on page 87.




Figure 8.3: IDL Definitions in the Interface Repository Browser

## Viewing the Interface Repository Contents


The navigation tree in the main browser window represents the contents of the Interface Repository in terms of containment relationships. As described in the *Orbix C++ Programmer's Guide*, the Interface Repository uses containment relationships to represent the nested structure of IDL definitions.

Consider the following example IDL source file:

```
// IDL
module Finance {
    interface Account {
        readonly attribute float balance;
    };
};
```

```
void makeDeposit (in float amount);  
void makeWithdrawal (in float amount);  
};  
  
interface Bank {  
    Account newAccount ();  
};  
};
```

If you import this file into an Interface Repository, the browser navigation tree represents the fact that the definition of module `Finance` contains interfaces `Account` and `Bank` which in turn contain attribute and operation definitions, as shown in Figure 8.4.



**Figure 8.4:** Containment Relationships in the Interface Repository Browser

### Viewing Information about IDL Definitions

The list box in the main browser window displays information about selected IDL definitions. To view information about an IDL definition, select the navigation tree icon of the container in which the definition is contained. The list box displays information about the contents of the container, including the type and name of each contained definition.

For example, if you select the icon for module `Finance`, the list box displays information about the IDL interface definitions contained within this module, as shown in Figure 8.4 on page 88.

### Viewing Source Code for IDL Definitions

To view the source for an IDL definition, do the following:

1. Navigate to the required IDL definition.
2. Select **View**→**View CORBA IDL**. The **View Interface Definition Language** dialog box displays the IDL source associated with the selected definition.

For example, if you view the source for interface `Bank`, the **View Interface Definition Language** dialog box appears as shown in Figure 8.5 on page 90.



**Figure 8.5:** *The View Interface Definition Language Dialog Box*

## Exporting IDL Definitions to a File


The Interface Repository browser allows you to save an IDL definition to a file. To export an IDL definition from the Interface Repository to a file, do the following:

1. Navigate to the required IDL definition.
2. Select **File**→**Export**. The standard **Save File As** dialog box for your operating system appears.
3. In the dialog box, enter the name of the target file in which you wish to save the IDL definition.
4. Select **OK** to save the definition to the specified file.

## Configuring the Interface Repository Browser

To configure the Interface Repository browser, do the following:

1. Select **Network**→**Options**. The **Interface Repository Options** dialog box appears as shown in Figure 8.6:



**Figure 8.6:** *The Interface Repository Options Dialog Box*

2. By default, the main browser window refreshes every seven seconds. To modify this refresh time, enter a positive integer value in the **Refresh Time** text box.
3. By default, the browser does not connect to an Interface Repository at startup. To specify that the browser should connect to the Interface Repository at the local host, select the **Connect to local host on startup** button.
4. Select **OK** to commit the new configuration.

---


**Note:** You can manually refresh the main browser window at any time. To do this, select **View**→**Refresh**.

---



Part III

Appendices





# Appendix A

## Configuration Variables

There are two forms of Orbix configuration variables: those that are common to multiple IONA products and variables that are specific to Orbix only.

### Common Configuration Variables

You can set the following variables using the Configuration Explorer GUI tool, or by editing the `common.cfg` configuration file, or as environment variables.

Variable	Description
IT_DAEMON_PORT	TCP port number for the Orbix daemon.
IT_DAEMON_SERVER_BASE	The starting TCP port number for servers launched by the Orbix daemon.
IT_DAEMON_SERVER_RANGE	The number set in this variable is used together with that set in <code>IT_DAEMON_SERVER_BASE</code> to determine the range of port numbers available for Orbix servers.
IT_IMP_REP_PATH	The full path name of the Implementation Repository directory.
IT_INT_REP_PATH	The full path name of the Interface Repository directory.
IT_LOCAL_DOMAIN	The name of the local internet domain; for example, <code>iona.com</code> .
IT_LOCATOR_PATH	The full path name of the directory holding the locator files.

### Orbix-Specific Configuration Variables

You can set the following variables using the Configuration Explorer GUI tool, or by editing the `orbix3.cfg` configuration file, or as environment variables:

Variable	Description
<code>IT_CONNECT_ATTEMPTS</code>	The maximum number of retries Orbix makes to connect a client to a server.
<code>IT_DAEMON_PROTOCOL</code>	Defines the protocol that Orbix uses to talk to the daemon. Valid values are <code>POOP</code> (Orbix protocol) or <code>IIOP</code> . This may be required for clients connecting to servers through a firewall. You should use this variable carefully and should not use it with <code>_bind()</code> .
<code>IT_DEFAULT_CODE</code>	The data encoder used; for example, <code>XDR</code> .
<code>IT_DEFAULT_COMMS</code>	The communications protocol used, for example <code>TCP/IP</code> .
<code>IT_ERRORS</code>	The full path name of the error messages file.
<code>IT_IIOP_VERSION</code>	The IIOP version of IORs generated by Orbix servers, and IIOP messages understood by Orbix. Valid values are <code>10</code> and <code>11</code> , representing IIOP 1.0 and IIOP 1.1 respectively. The default value is <code>10</code> .
<code>IT_ENABLE_MULTI_HOMED_SUPPORT</code>	Enables multi-homed support for machines with multiple IP addresses. This is disabled by default and impacts on performance when enabled.
<code>IT_ONEWAY_RESPONSE_REQUIRED</code>	A boolean variable that specifies if an IIOP reply is expected for an outgoing IIOP request containing a <code>oneway</code> operation.  A response to a oneway is useful when you wish to catch system exceptions, or to enable the client to receive IIOP replies with <code>LOCATION_FORWARD</code> status. The default value is <code>false</code> .

---

**Note:** Entries in IONA configuration files are scoped with a prefix; for example, `Common.IT_DAEMON_PORT` or `Orbix.IT_CONNECT_ATTEMPTS`. Environment variables are not scoped.

---

For details of OrbixNames-specific configuration variables, refer to the *OrbixNames Programmer's and Administrator's Guide*.



# Appendix B

## Orbix Daemon Options

The daemon process, `orbixd`, takes the following options:

- `-c filename` Specifies the log file to use for check-point information. In the event that a daemon is terminated, this allows a new daemon to recover information about existing running servers.

Unless an absolute path name is specified, the file is placed in a directory relative to that from which the daemon is launched.
- `-i filename` Outputs the daemon's interoperable object reference (IOR) to the specified file.

Unless an absolute path name is specified, the file is placed in a directory relative to that from which the daemon is launched.
- `-j` (NT-only) Installs the daemon as an NT service. The service must be started manually using the **Services Control Panel**. This starts the daemon with `<path>\orbixd -b`.
- `-l number` (UNIX-only) Specifies the maximum number of socket descriptors, and thus, the maximum number of connections to the daemon.

By default, the maximum number of descriptors is determined by the system's limit. This is normally 64, although this can be increased by a system administrator. The current maximum number that can be set is 1024.

- `-o userId` (UNIX only) Indicates that if the daemon runs with super-user privileges, servers launched by the daemon should run using the specified user ID instead of the root ID. Without this switch, a client running as root on a remote machine could launch a server with root privileges on a different machine.

Using the `-o` switch reduces the security risks associated with easily faked remote user IDs. If the remote user is not root, the server is launched under the user ID of the client process sending the request. This is the default when the `-o` switch is not used.
- `-p` Runs the daemon in protected mode. In this mode, only clients running as the same user as the daemon are allowed to modify the Implementation Repository. No updates are accepted from remote hosts.
- `-r time` Specifies the frequency (in seconds) at which `orbixd`'s child processes should be reaped. The default is 60 seconds.
- `-s` Runs the daemon in silent mode. By default the daemon outputs some trace information.
- `-t` Outputs more than the default trace information while the daemon is running.
- `-u` Allows invocations on a manually-launched unregistered server. This means that the manually-launched (persistent) server does not have to be registered in the Implementation Repository.
- `-x number` Sets the time limit in seconds for establishing that a connection to the daemon is fully operational. The default is 30 seconds.
- `-v` Outputs the daemon version number and a summary of the configuration details that a new daemon process would use. Specifying `-v` does not cause a new daemon to be run.
- `-w` (NT only) Uninstalls the daemon as an NT service.

# Appendix C

## Command Reference

This appendix acts as a reference for the command-line interface to Orbix. The commands described in this appendix allow you to manage the Implementation Repository, the server locator, and the Interface Repository.

### Command Summary

The following table shows the available commands:

<b>Purpose</b>	<b>Commands</b>
Configuration	dumpconfig
Server Registration	putit, rmit
Listing Server Information	lsit, psit, catit
Process Management	pingit, killit
Implementation Repository Directories	mkdirit, rmdirit
Security	chownit, chmodit
Server Locator Management	serverhosts, grouphosts, servergroups
Interface Repository Management	putidl, readifr, rmidl

This appendix describes each command in alphabetical order.

### catit

The `catit` command outputs full information about a given Implementation Repository entry.

#### Syntax

```
catit [-v] [-h host] server_name
```

#### Options

- `-v` Outputs the command version information.
- `-h host` Indicates which host to use.

### chmodit

The `chmodit` command modifies access control for a server. For example, use it to grant launch and invoke rights on a server to users other than the server owner.

#### Syntax

```
chmodit [-v] [-h host]  
  { server | -a directory }  
  { i{+,-}{user, group} |  
    l{+,-}{user, group} }
```

## Options

<code>-v</code>	Outputs the command version information.
<code>-h <i>host</i></code>	Indicates which host to use.
<code>-a</code>	The <code>-a</code> option specifies that a user or group is to be added to an access control list (ACL) for a directory of servers.
<code>i+</code>	By specifying the <code>i</code> option, you can add a user or group to ( <code>i+</code> ) or removed from ( <code>i-</code> ) the invoke ACL.
<code>i-</code>	
<code>l+</code>	By specifying the <code>l</code> option, you can add a user or group to ( <code>l+</code> ) or removed from ( <code>l-</code> ) the launch ACL.
<code>l-</code>	

By default, only the owner of an Implementation Repository entry can launch or invoke the registered server. However, launch and invoke access control lists (ACLs) are associated with each entry in the Implementation Repository and you can modify these ACLs to give certain users or groups the right to launch or invoke a specific server, or a directory of servers.

There is also a pseudo-group name called `all` that you can use to implicitly add all users to an access control list.

## chownit

The `chownit` command makes changes to the ownership of Implementation Repository entries and directories.

### Syntax

```
chownit [-v] [-h host]
    { -s server_name new_owner |
      -d directory { +, - } {user, group} }
```

### Options

- v Outputs the command version information.
- h *host* Indicates which host to use.
- s The -s option enables you to change the ownership of an Implementation Repository entry.
- d The -d option modifies the ACL on a directory allowing you to add (+) or remove (-) a user or group from the list of owners of a directory.

Only the current owner of an Implementation Repository entry has the right to change its ownership.

An Implementation Repository directory can have more than one owner. An ownership access control list (ACL) is associated with each directory in the Implementation Repository, and this ACL can be modified to give certain users or groups ownership rights on a directory. Only a user on an ownership ACL has the right to modify the ACL.

---

**Note:** Spaces *are* significant in this grammar. Spaces must exist between an option and its argument, and on either side of the + or - that follows a directory.

---

Orbix supports the pseudo-group `all` which, when added to an ACL, grants access to all callers.

## dumpconfig

The `dumpconfig` utility outputs the values of the configuration variables used by Orbix, and the location of the Orbix configuration files in your system. It also reports if there are any syntax errors in your configuration files.

### Syntax

```
dumpconfig [-v]
```

### Options

`-v` Outputs the command version information.

## grouphosts

Use the `grouphosts` command to access the hostgroups definition file to list the hosts in a specified group or modify that list by adding or deleting hosts.

The host groups definition file defines the host groups.

### Syntax

```
grouphosts group_name [-v] [-h host]  
          [-r host_list] [-a host_list] [-l]
```

### Options

`-v` Outputs the command version information.

`-h host` Indicates which host to use.

`-r` Removes all of the hosts in the given list from the specified group.

`-a` Adds all of the hosts in the given list to the specified group. The group is created if it does not exist.

`-l` Lists all of the hosts for the specified group.

---

**Note:** Because of the host lists, the `group_name` argument comes immediately after the command name, not after the options.

---

If more than one of the options is specified, they execute in the following order:

```
-r -a -l
```

### killit

The `killit` command kills (stops) a running server process.

#### Syntax

```
killit [-v] [-h host] [-m marker] server_name
```

- v            Outputs the command version information.
- h *host*     Indicates which host to use.
- m           Specifies a marker value to identify a specific object, or set of objects, to which the `killit` command applies.

Where there is more than one server process, use the marker parameter to select between different processes. You require the marker parameter when killing a process in the unshared mode.

The `killit` command uses the `SIGTERM` signal. This command does not remove the entry from the Implementation Repository.

### lsit

The `lsit` command lists entries in an Implementation Repository directory.

#### Syntax

```
lsit [-v] [-h host] [-R] directory
```

#### Options

- v            Outputs the command version information.
- h *host*     Indicates which host to use.
- R           Recursively lists all subdirectories and entries.

## mkdirit

The `mkdirit` command creates a new registration directory.

### Syntax

```
mkdirit [-v] [-h host] directory
```

### Options

- `-v` Outputs the command version information.
- `-h host` Indicates which host to use.

Hierarchical names are extremely useful in structuring the name space of servers in Implementation Repositories.

## pingit

The `pingit` command tries to contact an Orbix daemon to determine if it is running.

### Syntax

```
pingit [-v] [-h host]
```

### Options

- `-v` Outputs the command version information.
- `-h host` Indicates which host to use.

### psit

The `psit` command outputs a list of server processes known to an Orbix daemon.

#### Syntax

```
psit [-v] [-h host]
```

#### Options

- `-v` Outputs the command version information.
- `-h host` Indicates which host to use.

One line is output for each server process. Each line has values for the following fields:

```
Name Marker Code Comms Port Status Per-Client? OS-pid
```

The fields are as follows:

Name	The server name.
Marker	The object marker pattern associated with the process.
Code	The data encoder used; for example, <code>xdr</code> .
Comms	The communications protocol used; for example, <code>tcp</code> .
Port	The port number used by the communications system.
Status	One of “automatic”, “manual” or “inactive”.
Per-Client?	Indicates whether the server is a per-client server.
OS-pid	The operating system process.

## putidl

The `putidl` command allows you to add a set of IDL definitions to the Interface Repository. This command takes the name of an IDL file as an argument. All IDL definitions within that file are added to the repository.

The Interface Repository server must be available for this command to succeed.

### Syntax

```
putidl {[-?]} | [-v] [-h host] [-s] file
```

### Options

- ? Displays the allowed options for this command.
- v Outputs the command version information.
- h *host* Indicates the host at which the Interface Repository server is available.
- s Indicates that the command should run in silent mode.

## putit

The `putit` command creates an entry in the Implementation Repository that represents how Orbix can start a server.

### Syntax

```
putit [-v] [-h host] [-per-client | -per-client-pid]
  [ [-shared | -unshared] [-marker marker] ]
  [ -j | -java [-classpath classpath | -addpath path] ]
  [ -oc ORB_class -os ORB_singleton_class] [ -jdk2 ]
  [ [-per-method [-method method] ]
  [ -port iiop portnumber]
  [ -n number_of_servers] [ -l ]
  serverName [ command_line | -persistent ]
```

### Options

Executing `putit` without any arguments outputs a summary of its options. The options are as follows:

<code>-v</code>	Outputs the utility's version information without executing the command. This option is available on all of the utilities.
<code>-h host</code>	Specifies the host name on which to execute the <code>putit</code> command. By default, the command is executed on the local host.
<code>-per-client</code>	Specifies that a separate server process is used for each user. You can use this activation mode with the shared, unshared, or per-method modes.
<code>-per-client-pid</code>	Specifies that a separate server process is used for each client process. You can use this activation mode with the shared, unshared, or per-method modes.
<code>-shared</code>	Specifies that all active objects managed by a given server on a given machine are contained in the same process. This is the default mode.
<code>-unshared</code>	Specifies that as an object for a given server is invoked, an individual process is activated to handle all requests for that object. Each object managed by a server can (but does not have to) be registered with a different executable file—as specified in <i>command_line</i> .

- `-java` The `-java` switch is an extension of the standard Orbix `putit` command. This indicates that the specified server should be launched via the Java interpreter. You can truncate this switch to `-j`.
- `-oc` *ORB\_class* Passes `-Dorg.omg.CORBA.ORBClass=ORB_class` to the Java interpreter. You should use this switch with the `-os` switch.
- For OrbixWeb servers, the parameter to this switch should be as follows:
- ```
IE.Iona.OrbixWeb.CORBA.ORBClass.
```
- You should pass this string to the Java interpreter before the server class name.
- `-os` *ORB\_singleton\_class* Passes `-Dorg.omg.CORBA.ORBSingletonClass=ORB_singleton_class` to the Java interpreter. You should use this switch with the `-oc` switch.
- For OrbixWeb servers the parameter to this switch should be
- ```
IE.Iona.OrbixWeb.CORBA.ORBSingletonClass.
```
- This string must be passed to the Java interpreter before the servers class name.
- The `-os` and `-oc` switches provide foreign ORB support.

- `-jdk2` Passes the following system properties to the Java interpreter:
- ```
Dorg.omg.CORBA.ORBClass=
    IE.Iona.OrbixWeb.CORBA.ORB

-Dorg.omg.CORBA.ORBSingletonClass=
    IE.Iona.OrbixWeb.CORBA.singletonORB
```
- You must pass this string to the Java interpreter before the server class name. You should use this switch for OrbixWeb servers being executed by JDK1.2.
- `-per method` Specifies that each invocation to a server results in a process being activated to handle that request. Each method can (but does not have to) be registered with a different executable file—as specified in *command\_line*.
- `-port port` Specifies a well-known port number for a server so that Orbix, if necessary, activates a server that communicates on the specified port number. Often required by servers that communicate over the CORBA Internet Inter-ORB Protocol (IIOP).

The following options apply to the shared mode:

`-n number_of_servers` This switch is applicable only to servers registered in shared activation mode. It instructs the daemon to launch up to the specified number of servers. Each new client connection results in a new server being launched as long as the number of clients is less than the number specified in *number\_of\_servers*. When the number of clients equals the number of servers specified in *number\_of\_servers*, new clients are connected to running servers using a round robin algorithm.

The default number of servers is 1.

`-persistent` Specifies that the server can only be launched persistently, that is, manually. The server is never automatically launched by Orbix.

If the `-u` option is passed to the Orbix daemon, such servers do not have to be registered in the Implementation Repository.

The following option applies to the shared and unshared modes:

`-marker marker` Specifies a marker value to identify a specific object, or set of objects, to which the `putit` applies.

Marker names specified using `putit` cannot contain white space.

The following option applies to the per-method mode:

`-method method` Specifies a method name to identify a specific method, or set of methods, to which the `putit` applies.

### Notes

The `putit` command is often used in its simplest form:

```
putit server_name command_line
```

The *command\_line* is an absolute path name specifying the executable file that implements the server. Any command-line parameters to be given to the executable file are appended after the absolute path name in the `putit` command. These parameters are given to the server *every* time it is run by Orbix. However, the parameters must be given explicitly if the executable file is executed manually.

The default settings for `putit` mean that the simplest form of the command is equivalent to any of the following:

```
putit -shared server_name command_line
```

```
putit -shared -marker '*' server_name command_line
```

```
putit -marker '*' server_name command_line
```

By default, `putit` uses the Implementation Repository on the local host. By default, `putit` uses the shared activation mode. Therefore, on any given host, all objects with the specified server name are controlled by the same process. By default also, `putit` registers a server in the multiple-client activation mode. This means that all client processes bind to the same server process.

### Server Activation Modes

Activation modes control how servers are implemented when they become processes of the underlying operating system. The primary activation modes are *shared*, *unshared*, and *per-method*:

- In shared mode, all of the objects with the same server name on a given machine are managed by one process on that machine. If a server is registered in shared mode, it can also be launched manually prior to any invocation on its objects.
- In unshared mode, individual objects are registered with the Implementation Repository, and a process is launched for each such object.

- In per-method mode, individual operations are registered with the Implementation Repository, and each invocation on an operation results in a separate process.

You should note the following:

- The default activation mode is shared.
- For a given server name, you can select only one of shared, unshared, or per-method.
- For each of the modes shared or unshared, a server can be registered in a secondary activation mode:
  - ◆ multiple-client
  - ◆ per-client
  - ◆ per-client-process

The default is multiple-client activation, with the effect that a server process is shared between multiple principals and multiple client processes.

Per-client activation results in a separate server process for each principal (end-user). Per-client-process activation results in a separate server process for each separate client process. Per-client and per-client-process activation is orthogonal to shared, unshared and per-method modes.

- Manually-launched servers behave in a similar way to shared activation mode servers. If a server is registered as unshared or per-method, the server fails if it is launched manually. This is in line with the CORBA specification.

---

**Note:** Per-method servers are activated for a single IDL operation call. As a result, the per-client flag is ignored for per-method servers.

---

### Pattern Matching for Markers and Methods

Pattern matching specifies a set of objects for the `-marker` option, or a set of methods for the `-method` option. Pattern matching allows a group of server processes to share a workload between them, whereby each server process is responsible for a range of object marker values. The pattern matching is based on regular expressions, as follows:

|                     |                                                                                                      |
|---------------------|------------------------------------------------------------------------------------------------------|
| <code>*</code>      | Matches any sequence of characters.                                                                  |
| <code>?</code>      | Matches any single character.                                                                        |
| <code>[SET]</code>  | Matches any characters belonging to the specified set, for example, <code>[abc]</code> .             |
| <code>[!SET]</code> | Matches any characters <i>not</i> belonging to the specified set, for example, <code>[!abc]</code> . |
| <code>[^SET]</code> | Equivalent to <code>[!SET]</code> , for example, <code>[^abc]</code> .                               |

A SET, as presented above, is composed of characters and ranges. A range is specified using a hyphen character `-`.

Finally, since each of the characters `*?!^-[\]` is special, in the sense that it is interpreted by the pattern matching algorithm; each of them can be preceded by a `\` character to suppress its interpretation.

Examples of patterns are:

|                              |                                                                           |
|------------------------------|---------------------------------------------------------------------------|
| <code>hello</code>           | matches "hello".                                                          |
| <code>he*</code>             | matches any text beginning with "he", for example, "he", "help", "hello". |
| <code>he?</code>             | matches any three character text beginning with "he", for example, "hec". |
| <code>[abc]</code>           | matches "a", "b" or "c".                                                  |
| <code>he[abc]</code>         | matches "hea", "heb" or "hec".                                            |
| <code>[a-zA-Z0-9]</code>     | matches any alphanumeric character.                                       |
| <code>[!a-zA-Z0-9]</code>    | matches any non alphanumeric character.                                   |
| <code>_[gs]et_balance</code> | matches <code>_get_balance</code> and <code>_set_balance</code> .         |
| <code>make*</code>           | matches <code>makeDeposit</code> and <code>makeWithdrawal</code> .        |

If an activation order exists in an Implementation Repository entry for a specific object marker or method and another exists for an overlapping set of markers or methods, the particular server that is activated for a given object is non-deterministic. This means that no attempt is made to find an entry registered for best or exact match.

### readifr

The `readifr` command allows you to view an IDL definition stored in the Interface Repository. This command takes the fully scoped name of the IDL definition as an argument and displays that definition. Calling `readifr` with no arguments lists the contents of the entire Interface Repository.

The Interface Repository server must be available for this command to succeed.

#### Syntax

```
readifr {[-?] | [-v] [-h host] [-d] [-t] [-c] [definition_name]}
```

#### Options

- ? Displays the allowed options for this command.
- v Outputs the command version information.
- h *host* Indicates the host at which the Interface Repository server is available.
- d Displays all derived types of an IDL interface.
- c Indicates that the command should not prompt the user for input. This is useful when running `readifr` with no other arguments.

### **rmdirit**

The `rmdirit` command removes a registration directory.

#### **Syntax**

```
rmdirit [-v] [-h host] [-R] directory
```

#### **Options**

- v            Outputs the command version information.
- h *host*     Indicates which host to use.
- R            Recursively deletes the directory and all of the Implementation Repository entries and sub-directories within it.

The `rmdirit` command returns an error if it is called without the `-R` option on a non-empty registration directory.

### **rmidl**

The `rmidl` command allows you to remove an IDL definition from the Interface Repository. This command takes the fully scoped name of the IDL definition as an argument.

The Interface Repository server must be available for this command to succeed.

#### **Syntax**

```
rmidl {[-?] | [-v] [-h host] definition_name}
```

### Options

- ? Displays the allowed options for this command.
- v Outputs the command version information.
- h *host* Indicates the host at which the Interface Repository server is available.

## rmit

Removes an Implementation Repository entry or modifies an entry.

### Syntax

```
rmit [-v] [-h host]  
      [-marker marker | -method method] server_name
```

### Options

- v Outputs the command version information.
- h *host* Indicates which host to use.
- marker *marker* Specifies a marker value to identify a specific object, or set of objects, to which the `rmit` command applies.
- method *method* Specifies a method name to identify a specific method, or set of methods, to which the `rmit` applies.

This command does not kill any currently running processes associated with a server.

You can use pattern matching for markers and methods as described in the `putit` command reference. Refer to `putit` on page 109.

### servergroups

Use the `servergroups` command to access the server location file to list the host groups that support a specified server or modify that list by adding or deleting groups.

The server location file maintains a mapping from a server name to a list of hosts and host groups on which the server runs.

#### Syntax

```
servergroups server_name [-v] [-h host]  
          [-r group_list] [-a group_list] [-l]
```

#### Options

- v        Outputs the command version information.
- h *host*   Indicates which host to use. The -h option is used to specify the host of the Orbix daemon to send the request to; it defaults to the local host.
- r        Removes all of the groups in the given list from the entry for the specified server.
- a        Adds all of the groups in the given list to the entry for the specified server. An entry for the specified server name is created if it does not already exist.
- l        Lists all of the groups for the specified server.

Note that because of the group lists, the *server\_name* argument comes immediately after the command name, not after the options.

If more than one of the options is specified, they are executed in the following order:

```
-r -a -l
```

### serverhosts

Use the `serverhosts` command to access the server location file to list the hosts that support a specified server or modify that list by adding or deleting hosts.

The server location file maintains a mapping from a server name to a list of hosts and host groups on which the server runs.

#### Syntax

```
serverhosts server_name [-v] [-h host]  
          [-r host_list] [-a host_list] [-l]
```

#### Options

- v Outputs the command version information.
- h *host* Indicates which host to use. The -h option is used to specify the host of the Orbix daemon to send the request to; it defaults to the local host.
- r Removes all of the hosts in the given list from the entry for the specified server.
- a Adds all of the hosts in the given list to the entry for the specified server. An entry for the specified server name is created if it does not already exist.
- l Lists all of the hosts for the specified server.

---

**Note:** Because of the host lists, the *server\_name* argument comes immediately after the command name, not after the options.

---

If more than one of the options is specified, they are executed in the following order:

```
-r -a -l
```



# Appendix D

## Error Messages and Exceptions

Orbix has an external text file containing an explanation of all error messages, both for IDL compiler errors and system exceptions. Orbix outputs error messages from the file named by the `IT_ERRORS` environment variable or entry in the `orbix3.cfg` configuration file. This file contains Orbix-specific configuration variables.

### Setting Error Messages

The standard error file can be edited for a particular installation if required. For example, by translating all of the text into French or German, or by providing more verbose explanations of errors than those provided in the standard Orbix release.

Each error is assigned a unique number, and the file contains a line for each error in the form:

```
error_number: error_message_text
```

Rather than changing the standard file distributed with the Orbix release, you can specify an alternative file by using the `IT_ERRORS` entry in the `orbix3.cfg` configuration file. You can also specify a file on a per user basis by setting the value of the `IT_ERRORS` environment variable to a file which contains the list of system error messages.

Within the `IT_ERRORS` file, comments can be inserted using “//”, and “\” can be used as a continuation character if the message needs to extend past the end of a line. IDL compiler errors have been divided into pre-processing, syntax and semantic errors, and their error numbers are arranged within these divisions.

### System Exceptions Specific to Orbix

The following table lists system exceptions specific to Orbix:

| Identifier | Orbix Exception | Description                                         |
|------------|-----------------|-----------------------------------------------------|
| 10500      | FILTER_SUPPRESS | Suppress exception raised in per-object pre-filter. |
| 10520      | LOCATOR         | Locator error.                                      |
| 10540      | ASCII_FILE      | ASCII file error.                                   |
| 10560      | LICENCING       | Licensing error.                                    |
| 10580      | VXWORKS_EX      | VxWorks error.                                      |

### System Exceptions Defined by CORBA

The following table lists the system exceptions defined in the CORBA specification:

| Identifier | Exception     | Description                            |
|------------|---------------|----------------------------------------|
| 10000      | UNKNOWN       | The unknown exception.                 |
| 10020      | BAD_PARAM     | An invalid parameter was passed.       |
| 10040      | NO_MEMORY     | Dynamic memory allocation failure.     |
| 10060      | IMP_LIMIT     | Violated implementation limit.         |
| 10080      | COMM_FAILURE  | Communication failure.                 |
| 10100      | INV_OBJREF    | Invalid object reference.              |
| 10120      | NO_PERMISSION | No permission for attempted operation. |
| 10140      | INTERNAL      | ORB internal error.                    |
| 10160      | MARSHAL       | Error marshalling parameter/result.    |
| 10180      | INITIALIZE    | ORB initialization failure.            |

## Error Messages and Exceptions

---

| Identifier | Exception       | Description                             |
|------------|-----------------|-----------------------------------------|
| I0200      | NO_IMPLEMENT    | Operation implementation unavailable.   |
| I0220      | BAD_TYPECODE    | Bad TypeCode.                           |
| I0240      | BAD_OPERATION   | Invalid operation.                      |
| I0260      | NO_RESOURCES    | Insufficient resources for request.     |
| I0280      | NO_RESPONSE     | Response to request not yet available.  |
| I0300      | PERSIST_STORE   | Persistent storage failure.             |
| I0320      | BAD_INV_ORDER   | Routine invocations out of order.       |
| I0340      | TRANSIENT       | Transient failure; reissue the request. |
| I0360      | FREE_MEM        | Cannot free memory.                     |
| I0380      | INV_IDENT       | Invalid identifier syntax.              |
| I0400      | INV_FLAG        | Invalid flag was specified.             |
| I0420      | INTF_REPOS      | Error accessing interface repository.   |
| I0440      | BAD_CONTEXT     | Error processing context object.        |
| I0460      | OBJ_ADAPTOR     | Failure detected by object adaptor.     |
| I0480      | DATA_CONVERSION | Data conversion error.                  |



Index



---

# Index

## A

- access control lists 28, 103
- access rights to servers 71, 73
- activation modes 31–36, 114
  - multiple-client 35
  - per-client 19, 35, 108
  - per-client-process 35
  - per-method 31, 34
  - setting 71, 75
  - shared 31
  - unshared 31, 32
- activation orders for servers 26
- adding IDL to the Interface Repository 86
- administration, overview 7, 9

## B

- bind 5, 39

## C

- catit 25, 102
- chmodit 28, 102
- chownit 29, 103
- COMM\_FAILURE exception from pingit 18
- common.cfg
  - modifying 55
  - opening in Configuration Explorer 55
- communications protocols 19, 108
- config 13
- Configuration Explorer 53, 59
  - adding configuration files 63
  - adding configuration scopes 62
  - adding configuration variables 60
  - deleting configuration scopes 62
  - deleting configuration variables 61
  - modifying configuration values 55, 58
  - opening iona.cfg 55
  - valid names 61
  - valid values 61
- configuration files
  - common.cfg 55
  - iona.cfg 55
  - orbix3.cfg 58

- configuration files, for server locator 39
- configuration, basic steps 10
- connecting
  - to an Interface Repository 85
- connection attempts 59
- connection retries 96
- connection timeout 100
- CORBA 3
- customizing configuration 59

## D

- daemon
  - configuring
    - Orbix port value 57
    - server base port value 57
- daemon. *See* Orbix daemon
- data encoders 18, 108
- default classpath 57
- directories in Implementation Repository 23
- distributed objects 3
- domains 15, 57, 95
- dumpconfig 14, 104
- dynamic libraries 14

## E

- entries in Implementation Repository 22
- environment variables 13
- error messages 123
  - file 96
- errors file 59
- exceptions 123
- exporting IDL to files 90

## G

- gids 30
- group identifiers 30
- grouphosts 39, 44, 105

## H

- hierarchical server names 23

### I

- IDL 3
- IDL definitions
  - adding to Interface Repository 49
  - removing from Interface Repository 50
- IETF 15
- IFR server 48
- IIOp 77
  - server ports 36
  - well-known ports for servers 112
- Implementation Repository 4, 15, 21–37, 65–81
  - changing owners of servers 29
  - connecting to 67
  - deleting directories 69
  - directories 23
  - directory path 95
  - disconnecting from 68
  - listing details of servers 25
  - listing registered servers 25
  - location of 57
  - modifying server registration details 78
  - permissions to servers 28
  - registering servers 23, 71, 77
  - removing server registrations 24
  - role of Orbix daemon 16
- IMP\_LIMIT 37
- Interface Repository 7, 47–50
  - adding IDL definitions 49
  - configuring 48
  - location of 57
  - reading contents 50
  - removing IDL definitions 50
  - role of Orbix daemon 16
  - server 48
    - command line options 49
- Interface Repository browser 83–91
  - adding IDL definitions 86
  - configuring 91
  - connecting to an Interface Repository 85
  - exporting IDL to files 90
  - refreshing 91
  - starting 84
  - viewing IDL definitions 87–89
- internet domains 15, 57, 95
- invoke permissions to servers 28
- invoke rights to servers 73
- iona.cfg
  - opening in Configuration Explorer 55
- IOR for Orbix daemon 99
- IT\_CONFIG\_PATH 13, 15

- IT\_CONNECT\_ATTEMPTS 59, 96
- IT\_daemon 41
- IT\_DAEMON\_PORT 14, 57, 95
- IT\_DAEMON\_PROTOCOL 96
- IT\_DAEMON\_SERVER\_BASE 37, 57, 95
- IT\_DAEMON\_SERVER\_RANGE 37, 95
- IT\_DEFAULT\_CLASSPATH 57
- IT\_DEFAULT\_CODE 96
- IT\_DEFAULT\_COMMS 96
- IT\_ENABLE\_MULTI\_HOMED\_SUPPORT 96
- IT\_ERRORS 59, 96, 123
- IT\_IIOp\_VERSION 96
- IT\_IMP\_REP\_PATH 15, 57, 95
- IT\_INT\_REP\_PATH 48, 57, 95
- IT\_JAVA\_INTERPRETER 57
- IT\_LOCAL\_DOMAIN 57
- IT\_LOCAL\_DOMAIN 15, 95
- IT\_LOCATOR\_PATH 57, 95
- IT\_ONEWAY\_RESPONSE\_REQUIRED 96

### K

- killit 27, 106

### L

- launch commands for servers 77
- launch permissions to servers 28
- launch rights to servers 73
- LD\_LIBRARY\_PATH 14
- library path 14
- listing registered servers 25
- locators
  - locator files directory 57
  - See server locator
- lsit 24, 25, 106

### M

- manually-started servers 26
- mkdirit 23, 107
- multiple-client activation mode 35

### N

- nobody, user identifier 30

### O

- OMG 3
- Orbix
  - architecture components 4
  - daemon port 14

Orbix daemon  
  checking for 18  
  check-point information 99  
  command options 99  
  security risks 17  
  starting 16  
  trace information 100  
orbix.hgp 40  
Orbix.hostgroups 40  
Orbix.hosts 40  
orbix.hst 40  
orbix3.cfg  
  modifying 58  
  opening in Configuration Explorer 58  
orbixd 4  
  port number 14  
  running 16  
  running as super-user 17, 100  
  running in protected mode 100  
  running in silent mode 100  
  version information 100  
  *See also* Orbix daemon  
orbixusr, user identifier 30  
owners, changing for servers 29

## P

pattern matching, when registering servers 33  
per-client activation mode 19, 35, 108  
per-client-process activation mode 35  
per-method activation mode 31, 34  
permissions for servers 22  
persistent servers 26, 79, 100  
pingit 18, 107  
port numbers  
  for servers 77  
  for the Orbix daemon 57  
ports  
  for Orbix daemon 14, 95  
  for servers 19, 36, 95, 108, 112  
process identifiers 18  
protected mode 100  
protocols 19, 108  
psit 18  
putidl 49, 109  
putit 17, 23, 109

## Q

quick start to Orbix administration 9

## R

readifr 50, 117  
reading contents of the Interface Repository 50  
refreshing  
  the Interface Repository browser window 91  
registering servers 17, 23  
regular expressions 33  
rmdirit 24, 118  
rmidl 50, 118  
rmit 24, 34, 35, 119  
running orbixd in 100

## S

security 17  
  of servers 28  
server locator 5, 39–45  
  configuration files 39  
  format of 41  
  directory path 95  
  role of Orbix daemon 16  
Server Manager 65–81  
  configuring 80  
  connecting to an Implementation Repository 67  
  deleting directories 69  
  disconnecting from an Implementation  
    Repository 68  
  killing persistent servers 79  
  launching persistent server 79  
  launching persistent servers 79  
  modifying server details 78  
  registering servers 71, 77  
    specifying access rights 73  
    specifying activation modes 75, 77  
  starting 66  
servergroups 39, 43, 120  
serverhosts 39, 42, 121  
servers 18  
  access control lists 28  
  access rights 71, 73  
  activation modes 31–36, 71  
  activation orders 22  
  details of registration 25  
  details of running servers 19, 108  
  for Interface Repository 48  
  hierarchical names 23  
  IIOP port numbers 77  
  IIOP ports 112  
  invoke permissions 28  
  killing 79

### servers (*continued*)

- launch commands 77
- launch permissions 28
- launching persistently 79
- listing 25
- managing 21
- modifying registration details 78
- names of 22
- owners of 22, 29
- permissions for 22, 28
- ports 36
- process identifiers 18
- registering 17, 23, 71, 77
- registry 71
- removing registration of 24
- starting 16
- starting manually 26
- stopping 27
- shared activation mode 31
- silent mode, running orbixd in 100
- starting
  - the Interface Repository browser 84
  - the Server Manager 66
- starting servers 16
- stopping servers 27
- super-user, running orbixd as 17, 100

## T

- TCP/IP 19, 108
- tools
  - Configuration Explorer 53
  - Interface Repository browser 83–91
  - Server Manager 65–81
- trace information from Orbix daemon 100

## U

- uids 30
- unshared activation mode 31, 32
- user identifiers 30

## V

- version number, of Orbix 100
- Viewing Information about IDL Definitions 89

## X

- XDR 18, 108